

Pinout & Configuration

Clock Configuration

Project Manager

Tools

Software Packs

Pinout

TIM3 Mode and Configuration

Mode

Slave Mode Trigger Source ☒ Internal ClockChannel1 Channel2 Channel3 Channel4

Configuration

Reset Configuration

☒ Parameter Settings☒ User Constants☒ NVIC Settings☒ DMA Settings

Configure the below parameters :

Search (Ctrl+F)

Counter Settings

Prescaler (PSC - 16 bits value) 7999

Counter Mode Up

Counter Period (AutoReload Register - ... 499


Internal Clock Division (CKD) No Division

auto-reload preload Disable

> Trigger Output (TRGO) Parameters

Pinout view

System view



Pinout & Configuration

Clock Configuration

Project Manager

Tools

▼ Software Packs

▼ Pinout

RCC Mode and Configuration

Mode

High Speed Clock (HSE) Crystal/Ceramic Resonator

Low Speed Clock (LSE) Disable

☐ Master Clock Output

Configuration

Reset Configuration

Parameter Settings

User Constants

NVIC Settings

GPIO Settings

Configure the below parameters :

Search (Ctrl+F)

▼ System Parameters

VDD voltage (V) 3.3 V

Prefetch Buffer Enabled

Flash Latency(WS) 0 WS (1 CPU cycle)

▼ RCC Parameters


HSI Calibration Value 16

HSE Startup Timeout Value (ms) 100

LSE Startup Timeout Value (ms) 5000

Pinout view

System view



Pinout & Configuration

Clock Configuration

Project Manager

Tools

▼ Software Packs

▼ Pinout

NVIC Mode and Configuration

Configuration

✓ NVIC ✓ Code generation


Priority Group .. ▾ ☐ Sort by Preemption Priority and Sub Priority ☐ Sort by interrupts namesSearch Show available interrupts ▾ ☒ Force DMA channels Interrupt

NVIC Interrupt Table	Enabled	Preemption Priority	Sub Priority
Non maskable interrupt	☒	0	0
Hard fault interrupt	☒	0	0
Memory management fault	☒	0	0
Prefetch fault, memory access fault	☒	0	0
Undefined instruction or illegal state	☒	0	0
System service call via SWI instruction	☒	0	0
Debug monitor	☒	0	0
Per .. e	☒	0	0
Time base: System tick timer	☒	0	0
PVD interrupt through EXTI line 16	☐	0	0
Flash global interrupt	☐	0	0
RCC global interrupt	☐	0	0
TIM3 global interrupt	☒	0	0
I2C2 event interrupt	☐	0	0
I2C2 error interrupt	☐	0	0

☐ Enabled Preemption Priority ▾ Sub Priority ▾

Pinout view

System view



Pinout & Configuration

Clock Configuration

Project Manager

Tools

Software Packs

Pinout

I2C2 Mode and Configuration

Mode

I2C I2C

Configuration

Reset Configuration

NVIC Settings

DMA Settings

GPIO Settings

Parameter Settings

User Constants

Configure the below parameters :

Search (Ctrl+F)

Master Features

I2C Speed Mode Standard Mode

I2C Clock Speed (Hz) 100000

Slave Features

Clock No Stretch Mode Disabled

Primary Address Length selection 7-bit


Dual Address Acknowledged Disabled

Primary slave address 0

General Call address detection Disabled

Pinout view

System view



Pinout & Configuration

Clock Configuration

Project Manager

Tools

▼ Software Packs

▼ Pinout

GPIO Mode and Configuration

Configuration

Group By Peripherals

☒ GPIO
 ☒ I2C
 ☒ RCC
 ☒ SYS

Search Signals

Search (Ctrl+F)

☐ Show only Modified Pins

Pin N...	Signal on...	GPIO out...	GPIO mo...	GPIO Pul...	Maximu...	User Label	Modified
PA0-WK...	n/a	n/a	Input mode	No pull-u...	n/a	BUTTON 1	☒
PA1	n/a	n/a	Input mode	No pull-u...	n/a	BUTTON 2	☒
PA2	n/a	n/a	Input mode	No pull-u...	n/a	BUTTON 3	☒
PA12	n/a	Low	Output P...	No pull-u...	Low	FIN	☒

Select Pins from table to configure them. Multiple selection is Allowed.

Pinout view

System view

