EAD95809 - COBOL

	GR.EAD958.COBLIB(EAD95809) - 01.07
000100	IDENTIFICATION DIVISION.
000200	PROGRAM-ID.
000300	EAD95809.
000400	AUTHOR.
000500	LUCAS.
000600	**********
000700	* BALANCE LINE *
00800	**********
000900	*
001000	ENVIRONMENT DIVISION.
001100	CONFIGURATION SECTION.
001200	SPECIAL-NAMES.
001300	DECIMAL-POINT IS COMMA.
001400	INPUT-OUTPUT SECTION.
001500	FILE-CONTROL.
001600	SELECT ARQ-CLIENTES ASSIGN TO CLIENTES
001700	FILE STATUS IS WK-FS-CLIENTES.
001710	SELECT ARQ-LANCAM ASSIGN TO LANCAM
001720	FILE STATUS IS WK-FS-LANCAM.
001730	SELECT ARQ-CLIENTEN ASSIGN TO CLIENTEN
001740	FILE STATUS IS WK-FS-CLIENTEN.
001800	*
001900	DATA DIVISION.
002000	FILE SECTION.

002100	FD	ARQ-CLIENTES		
002200		RECORDING MODE IS F.		
002300	01	REG-CLIENTES.		
002310		05 FD-CHAVE-CLIENTES.		
002400		10 FD-AGENCIA-CLIENTES		PIC X(4).
002500		10 FD-CONTA-CLIENTES		PIC 9(5).
002600		05 FD-NOME-CLIENTES	PIC	A(20).
002700		05 FD-SALDO-CLIENTES	PIC	9(6)V99.
002710	FD	ARQ-LANCAM		
002720		RECORDING MODE IS F.		
002730	01	REG-LANCAM.		
002740		05 FD-CHAVE-LANCAM.		
002750		10 FD-AGENCIA-LANCAM		PIC X(4).
002760		10 FD-CONTA-LANCAM		PIC 9(5).
002761		05 FD-DOC-LANCAM	PIC	9(4).
002770		05 FD-TIPO-LANCAM	PIC	Α.
002780		05 FD-VALOR-LANCAM	PIC	9(6)V99.
002790	FD	ARQ-CLIENTEN		
002791		RECORDING MODE IS F.		
002792	01	REG-CLIENTEN.		
002793		05 FD-CHAVE-CLIENTEN.		
002794		10 FD-AGENCIA-CLIENTEN		PIC X(4).
002795		10 FD-CONTA-CLIENTEN		PIC 9(5).
002798		05 FD-NOME-CLIENTEN	PIC	A(20).
002799		05 FD-SALDO-CLIENTEN	PIC	9(6)V99.
002800	WORK	KING-STORAGE SECTION.		
002900	77	WK-FS-CLIENTES PIC XX		VALUE SPACES.
002910	77	WK-FS-LANCAM PIC XX		VALUE SPACES.

002920	77 WK-FS-CLIENTEN PIC XX VALUE SPACES.
003000	77 WK-SALDO-EDIT PIC ZZZ.ZZ9,99 VALUE ZEROS.
003010	77 WK-VALOR-EDIT PIC ZZZ.ZZ9,99 VALUE ZEROS.
003100	*
003200	PROCEDURE DIVISION.
003300	000-PRINCIPAL SECTION.
003400	001-PRINCIPAL.
003500	PERFORM 101-INICIAR.
003600	PERFORM 201-PROCESSAR UNTIL WK-FS-CLIENTES = '10'
003610	AND WK-FS-LANCAM = '10'.
003700	PERFORM 901-FINALIZAR.
003800	STOP RUN.
003900	************
004000	100-INICIAR SECTION.
004100	101-INICIAR.
004110	PERFORM 102-ABRIR-CLIENTES.
004120	PERFORM 103-ABRIR-LANCAM.
004130	PERFORM 104-ABRIR-CLIENTEN.
004140	102-ABRIR-CLIENTES.
004200	OPEN INPUT ARQ-CLIENTES.
004300	EVALUATE WK-FS-CLIENTES
004400	WHEN '00'
004500	PERFORM 301-LER-CLIENTES
004600	WHEN '35'
004700	DISPLAY 'ARQUIVO CLIENTES NAO ENCONTRADO'
004800	MOVE 12 TO RETURN-CODE
004900	STOP RUN

005000	WHEN OTHER
005100	DISPLAY 'ERRO ' WK-FS-CLIENTES
005200	' NO COMANDO OPEN CLIENTES'
005300	MOVE 12 TO RETURN-CODE
005400	STOP RUN
005500	END-EVALUATE.
005510	103-ABRIR-LANCAM.
005520	OPEN INPUT ARQ-LANCAM.
005530	EVALUATE WK-FS-LANCAM
005540	WHEN '00'
005550	PERFORM 302-LER-LANCAM
005560	WHEN '35'
005570	DISPLAY 'ARQUIVO LANCAM NAO ENCONTRADO'
005580	MOVE 12 TO RETURN-CODE
005590	STOP RUN
005591	WHEN OTHER
005592	DISPLAY 'ERRO ' WK-FS-LANCAM
005593	' NO COMANDO OPEN LANCAMENTOS'
005594	MOVE 12 TO RETURN-CODE
005595	STOP RUN
005596	END-EVALUATE.
005597	104-ABRIR-CLIENTEN.
005598	OPEN OUTPUT ARQ-CLIENTEN.
005599	EVALUATE WK-FS-CLIENTEN
005600	WHEN '00'
005601	CONTINUE
005606	WHEN OTHER
005607	DISPLAY 'ERRO ' WK-FS-CLIENTEN

005608	' NO COMANDO OPEN CLIENTEN'
005609	MOVE 12 TO RETURN-CODE
005610	STOP RUN
005611	END-EVALUATE.
005620	********
005700	200-PROCESSAR SECTION.
005800	201-PROCESSAR
005900	EVALUATE TRUE
006000	WHEN FD-CHAVE-CLIENTES < FD-CHAVE-LANCAM
006100	PERFORM 202-GRAVAR-CLIENTEN
006200	PERFORM 301-LER-CLIENTES
006300	WHEN FD-CHAVE-CLIENTES = FD-CHAVE-LANCAM
006400	PERFORM 203-EXEC-LANCAM
006500	PERFORM 302-LER-LANCAM
006510	WHEN OTHER
006520	DISPLAY 'CHAVE LANCAMENTO : ' FD-CHAVE-LANCAM
006530	' ESTA ERRADA NO DOCUMENTO ' FD-DOC-LANCAM
006540	PERFORM 302-LER-LANCAM
006550	END-EVALUATE.
006560	202-GRAVAR-CLIENTEN.
006561	MOVE FD-SALDO-CLIENTES TO WK-SALDO-EDIT.
006570	DISPLAY ' SALDO FINAL = ' WK-SALDO-EDIT.
006571	DISPLAY ''.
006580	MOVE REG-CLIENTES TO REG-CLIENTEN.
006590	WRITE REG-CLIENTEN.
006591	IF WK-FS-CLIENTEN NOT EQUAL '00'
006592	DISPLAY 'ERRO ' WK-FS-CLIENTEN

006593	' NO COMANDO WRITE CLIENTEN'
006594	MOVE 12 TO RETURN-CODE
006595	STOP RUN
006596	END-IF.
006597	203-EXEC-LANCAM.
006598	EVALUATE FD-TIPO-LANCAM
006599	WHEN 'C'
006600	ADD FD-VALOR-LANCAM TO FD-SALDO-CLIENTES
006601	MOVE FD-VALOR-LANCAM TO WK-VALOR-EDIT
006602	DISPLAY ' CREDITO : ' WK-VALOR-EDIT
006603	WHEN 'D'
006604	IF FD-VALOR-LANCAM > FD-SALDO-CLIENTES
006605	DISPLAY 'SALDO INSUFICIENTE NO DOCUMENTO '
006606	FD-DOC-LANCAM
006607	ELSE
006608	SUBTRACT FD-VALOR-LANCAM FROM FD-SALDO-CLIENTES
006609	MOVE FD-VALOR-LANCAM TO WK-VALOR-EDIT
006610	DISPLAY ' DEBITO : ' WK-VALOR-EDIT
006611	END-IF
006611	END-IF WHEN OTHER
006612	WHEN OTHER
006612 006613	WHEN OTHER DISPLAY 'TIPO LANCAMENTO : ' FD-TIPO-LANCAM
006612 006613 006614	WHEN OTHER DISPLAY 'TIPO LANCAMENTO : ' FD-TIPO-LANCAM ' ESTA ERRADO NO DOCUMENTO ' FD-DOC-LANCAM
006612 006613 006614 006615	WHEN OTHER DISPLAY 'TIPO LANCAMENTO : ' FD-TIPO-LANCAM ' ESTA ERRADO NO DOCUMENTO ' FD-DOC-LANCAM END-EVALUATE.
006612 006613 006614 006615 006620	WHEN OTHER DISPLAY 'TIPO LANCAMENTO : ' FD-TIPO-LANCAM ' ESTA ERRADO NO DOCUMENTO ' FD-DOC-LANCAM END-EVALUATE.
006612 006613 006614 006615 006620 006700	WHEN OTHER DISPLAY 'TIPO LANCAMENTO : ' FD-TIPO-LANCAM ' ESTA ERRADO NO DOCUMENTO ' FD-DOC-LANCAM END-EVALUATE. ***********************************

007100	WHEN '00'
007110	MOVE FD-SALDO-CLIENTES TO WK-SALDO-EDIT
007200	DISPLAY FD-AGENCIA-CLIENTES ' '
007210	FD-CONTA-CLIENTES ' '
007220	FD-NOME-CLIENTES ' '
007240	DISPLAY ' SALDO INICIAL = ' WK-SALDO-EDIT
007300	WHEN '10'
007400	MOVE HIGH-VALUES TO FD-CHAVE-CLIENTES
007500	WHEN OTHER
007600	DISPLAY 'ERRO ' WK-FS-CLIENTES
007700	' NO COMANDO READ CLIENTES'
007800	MOVE 12 TO RETURN-CODE
007900	STOP RUN
008000	END-EVALUATE.
008010	302-LER-LANCAM.
008020	READ ARQ-LANCAM.
008030	EVALUATE WK-FS-LANCAM
008040	WHEN '00'
008050	CONTINUE
008091	WHEN '10'
008093	MOVE HIGH-VALUES TO FD-CHAVE-LANCAM
008094	WHEN OTHER
008095	DISPLAY 'ERRO ' WK-FS-LANCAM
008096	' NO COMANDO READ LANCAM'
008097	MOVE 12 TO RETURN-CODE
008098	STOP RUN
008099	END-EVALUATE.

```
008100 *************************
008200
          900-FINALIZAR SECTION.
008300 901-FINALIZAR.
008400
             CLOSE ARQ-CLIENTES.
010700
             CLOSE ARQ-LANCAM.
             CLOSE ARQ-CLIENTEN.
010800
010900
       IF WK-FS-CLIENTEN NOT EQUAL '00'
                  DISPLAY 'ERRO ' WK-FS-CLIENTEN
011000
011100
                        ' NO COMANDO CLOSE CLIENTEN'
011110
                  DISPLAY 'ERRO AO SALVAR ARQUIVO'
011200
                 MOVE 12 TO RETURN-CODE
011300 END-IF.
```

COMPILADOR

EXECUTÁVEL - EXECO9

ARQ - CLIENTES

ARQ - LANCAM

ARQ - CLIENTEN

SAÍDA