

Конфигурация коммутатора:

```
Switch> enable
Switch# configure terminal
Switch(config)# ip routing
Switch(config)# ipv6 unicast-routing
Switch(config)# vlan 10
Switch(config-vlan)# name ADMIN
Switch(config)# vlan 20
Switch(config-vlan)# name PC
Switch(config)# vlan 30
Switch(config-vlan)# name WIRELESS_CORP
Switch(config)# vlan 40
Switch(config-vlan)# name IP_PHONES
Switch(config)# vlan 50
Switch(config-vlan)# name FILE_SERVER
Switch(config)# vlan 60
Switch(config-vlan)# name WIRELESS_GUEST

Switch(config)# interface vlan 10
Switch(config-if)# ip address 192.168.10.1 255.255.255.240
Switch(config-if)# ipv6 address fd00:1102:2004:10::1/64
Switch(config-if)# no shutdown
Switch(config)# interface vlan 20
Switch(config-if)# ip address 192.168.20.1 255.255.255.240
Switch(config-if)# ipv6 address fd00:1102:2004:20::1/64
Switch(config-if)# no shutdown
Switch(config)# interface vlan 30
Switch(config-if)# ip address 192.168.30.1 255.255.255.224
Switch(config-if)# ipv6 address fd00:1102:2004:30::1/64
Switch(config-if)# no shutdown
Switch(config)# interface vlan 40
Switch(config-if)# ip address 192.168.40.1 255.255.255.240
Switch(config-if)# no shutdown
Switch(config)# interface vlan 50
Switch(config-if)# ip address 192.168.50.1 255.255.255.252
Switch(config-if)# ipv6 address fd00:1102:2004:50::1/64
Switch(config-if)# no shutdown
Switch(config)# interface vlan 60
Switch(config-if)# ip address 192.168.60.1 255.255.255.224
Switch(config-if)# ipv6 address fd00:1102:2004:160::1/64
Switch(config-if)# no shutdown
Switch(config)# ip route 0.0.0.0 0.0.0.0 192.168.10.2
Switch(config)# interface gi0/3
Switch(config-if)# switchport mode access
```

```
Switch(config-if)# switchport access vlan 50
Switch(config)# interface gi0/3
Switch(config-if)# switchport mode access
Switch(config-if)# switchport access vlan 50
Switch(config)# interface range gi0/2,gi0/4,gi0/6-11
Switch(config-if)# switchport mode access
Switch(config-if)# switchport access vlan 20
Switch(config-if)# switchport voice vlan 20

Switch(config)# ip dhcp-server enable
Switch(config)# ip dhcp pool VLAN_30_IPV4
Switch(dhcp-config)# network 192.168.30.0 255.255.255.224
Switch(dhcp-config)# default-router 192.168.30.1
Switch(dhcp-config)# range 192.168.30.2 192.168.60.32
Switch(dhcp-config)# exit
Switch(config)# ipv6 dhcp pool VLAN_60_IPV6
Switch(dhcp-config)# address prefix fd00:1102:2004:30::/64
Switch(dhcp-config)# default-router fd00:1102:2004:30::1/64
Switch(dhcp-config)# exit
Switch(config)# ip dhcp pool VLAN_60_IPV4
Switch(dhcp-config)# network 192.168.60.0 255.255.255.224
Switch(dhcp-config)# default-router 192.168.60.1
Switch(dhcp-config)# range 192.168.60.2 192.168.60.32
Switch(dhcp-config)# exit
Switch(config)# ipv6 dhcp pool VLAN_60_IPV6
Switch(dhcp-config)# address prefix fd00:1102:2004:60::/64
Switch(dhcp-config)# default-router fd00:1102:2004:60::1/64
Switch(dhcp-config)# exit

Switch(config)# username admin password L6jrH5Kf!kP#o
Switch(config)# line vty 0 15
Switch(config-line)# login local
Switch(config-line)# transport input ssh
```