R_CDMX

Physical   Config   CLI   Attributes

IOS Command Line Interface

```
00:00:20: %OSPF-5-ADJCHG: Process 1, Nbr 4.4.4.4 on Serial2/0
from LOADING to FULL, Loading Done


Password:

R_CDMX>enable
Password:
R_CDMX#show running
Building configuration...

Current configuration : 1751 bytes
!
version 12.2
no service timestamps log datetime msec
no service timestamps debug datetime msec
no service password-encryption
!
hostname R_CDMX
!
!
!
enable secret 5 $1$mERr$6ft.YlcVqs09MNclUxIyr.
!
!
!
!
```

Ctrl+F6 to exit CLI focus   Copy   Paste

☐ Top

Physical   Config   CLI   Attributes

IOS Command Line Interface

```
!
!
!
!
!
!
interface FastEthernet0/0
 description Piso 3 de las oficinas de la CDMX.
 ip address 172.16.0.94 255.255.255.224
 duplex auto
 speed auto
!
interface FastEthernet1/0
 description Red de DNS de la organizacion completa
 ip address 172.16.0.254 255.255.255.252
 duplex auto
 speed auto
!
interface Serial2/0
 description Conexion ISP del edificio de a CDMX
 ip address 152.78.212.18 255.255.255.252
!
interface Serial3/0
 no ip address
 clock rate 2000000
 shutdown
!
interface FastEthernet4/0
 no ip address
```

Ctrl+F6 to exit CLI focus   Copy   Paste

☐ Top

Physical   Config   CLI   Attributes

IOS Command Line Interface

```
 no ip address
 shutdown
!
interface FastEthernet5/0
 no ip address
 shutdown
!
interface FastEthernet6/0
 description Piso 4 de las officnas de la CDMX
 ip address 172.16.0.62 255.255.255.192
 duplex auto
 speed auto
!
interface FastEthernet7/0
 description Piso de Oficinas Directivas en la CDMX
 ip address 172.16.0.126 255.255.255.224
 duplex auto
 speed auto
!
interface FastEthernet8/0
 no ip address
 duplex auto
 speed auto
 shutdown
!
interface FastEthernet9/0
 no ip address
```

Ctrl+F6 to exit CLI focus   Copy   Paste

☐ Top

Physical   Config   CLI   Attributes

IOS Command Line Interface

```
 duplex auto
 speed auto
 shutdown
!
router ospf 1
 router-id 1.1.1.1
 log-adjacency-changes
 network 172.16.0.0 0.0.0.63 area 0
 network 172.16.0.64 0.0.0.31 area 0
 network 172.16.0.96 0.0.0.31 area 0
 network 172.16.0.252 0.0.0.3 area 0
 network 152.78.212.16 0.0.0.3 area 0
!
ip classless
!
ip flow-export version 9
!
!
!
no cdp run
!
banner motd ^C***NO ACCEDER SIN AUTORIZACION***^C
!
!
!
!
!
```

Ctrl+F6 to exit CLI focus   Copy   Paste

☐ Top

Physical   Config   CLI   Attributes

IOS Command Line Interface

```
!
banner motd ^C***NO ACCEDER SIN AUTORIZACION***^C
!
!
!
!
!
line con 0
 password consoleCDMX
 logging synchronous
 login
!
line aux 0
!
line vty 0 4
 login
!
!
!
end

R_CDMX#
R_CDMX#
R_CDMX#
R_CDMX#
R_CDMX#
```

Ctrl+F6 to exit CLI focus   Copy   Paste

☐ Top