# **OTP - SMS MISR**

### 1- Username:-

43cd6a9f4985987ea5c8e34e64eb4263771d5180393c85a3e0690b663f80a7ad

### 2- Password:-

d1a162d13d53f57387166ac623ae9cad11841eb36c24b008c4ae2b659cbdd1a8

3- SENDER TOKEN- (Mzadat Masr):-

88a57601ddc738d42cad513ae71a7e740bbea3693e92e2578163c240caa0b699

4- <u>SENDER TOKEN- (shehab Mzad):-</u> af6541e30c94798338a4fd18d263394927957ff6ecb61a862dc6e212918be64c

## 5- GUIDE OTP API:-

#### **OTP API Features**

- · APIs supports POST method only
- Send OTP to single mobile number
- Send It immediately (Fast & Secure Route)
- · Select one of templates
- For test use postman application https://www.postman.com/downloads
- balance Inquiry https://smsmisr.com/api/Balance/? username=xx&password=xx

Base URL (FromURI or FromBody)= https://smsmisr.com/api/OTP/?

(\*) fields are mandatory

In first stage use Testing environment to avoid wasting points

Sender for

testing="b611afb996655a94c8e942a823f1421de42bf8335d24b a1f84c437b2ab11ca27"

ide OTP API	
(*)environment="int"   For Live , 2 For Test	
(*)username="string" Get it from settings   Settings >	
(*)password="string" Get it from settings   Settings >	
(*)sender="string" "XXXX-XXXX-XXXX-XXXX"   Sender	er IDs >
(*)mobile="string" 2011XXXXXX	
(*)template="string" "XXXX-XXXX-XXXX-XXXX" Tem Token	plate
(*)otp="string" XXXXX Max 10	
Request Example : https://smsmisr.com/api/OTP/? environment=2&username=X&password=X&sender=X& &template=X&otp=X	:mobile=X
sponse Codes	
Success, Message Submitted Successfully	4901
Invalid value in username or password field	4903
Invalid value in "sender" field	4904
Invalid value in "mobile" field	4905
Insufficient Credit	4906
Server under updating	4907
Invalid OTP	4908
Invalid Template Token	4909
Invalid Environment	4912
Successful Response { "code": "4901", "SMSID": "12345", "Cost": "1", }	

Templates

Your OTP is XXXXXXXXXX

0f9217c9d760c1c0ed47b8afb5425708da7d98729016a8accfc14f9cc8d1ba83

Your One Time Password (OTP) is XXXXXXXXXX

eb60c2a456825a40a56dd36813e8ba8740b6dbe1c5d6921034bd9508e78d5fac

OTP: XXXXXXXXXX Please use OTP to login to your account

5f0b0e60ee65179573bdad2f7e9da5d4f89547a44cb15ff5a134a5d595cffc47

OTP: XXXXXXXXXXX

Please use OTP to activate your account

57e397e922136ebb17480888a534825d58e19dbeea6aadfd633a8aa4ef0629ed

Please don't share this (OTP) with any one XXXXXXXXXX is your OTP

0ea82e58642f442b7ld24dbd7bbd5fda9960727040lla27bbad5c0ac058c8757

Your OTP is XXXXXXXXXX کود التحقق الخاص بك هو XXXXXXXXXX

e83faf6025ec4ld0f40256d2812629f5fa929ld05c8322f31eea83430250lda8

كلمة العرور لعرة واحدة لحسابك هي XXXXXXXXXX is your OTP

3c37cb381ffcc7c0254a0d9373afaa265921ba495ad942de6c7b6f4f8bb56847

كود التحقق (OTP) الخاص بك هو XXXXXXXXXX

9b04deada138c009fa6a39ee1ca37c476e1501fbfefb8b72b14a90fe8e863dbe

كلمة المرور ثمرة واحدة (OTP) هي XXXXXXXXXX

58a6fba490f281f6c73f6d7db9a221a98c30dc81af70d15951ecc85a54012af5