



Paned — A widget with two adjustable panes

Table of Contents

```
1
          Synopsis
2
          Methods
2.1
          new
2.2
          gtk paned new
          gtk paned add1
2.3
2.4
          gtk paned add2
2.5
          gtk paned pack1
          gtk paned pack2
2.6
2.7
          [gtk paned ] get child1
2.8
          [gtk paned ] get child2
2.9
          [gtk paned ] set position
2.10
          [gtk paned ] get position
2.11
          [gtk paned ] get handle window
          [gtk paned ] set wide handle
2.12
          [gtk paned ] get wide handle
2.13
3
          Signals
3.1
          Supported signals
3.1.1
          accept-position
3.1.2
          cancel-position
          toggle-handle-focus
3.1.3
          Not yet supported signals
3.2
3.2.1
          cycle-child-focus
          cycle-handle-focus
3.2.2
3.2.3
          move-handle
```

```
unit class Gnome::Gtk3::Paned;
also is Gnome::Gtk3::Container;
```

Synopsis

```
my Gnome::Gtk3::Paned $p .= new(:orientation(GTK_ORIENTATION_HORIZONTAL));
my Gnome::Gtk3::ListBox $lb1 .= new(:empty);
my Gnome::Gtk3::ListBox $lb2 .= new(:empty);
$p.gtk-paned-add1($lb1);
$p.gtk-paned-add2($lb2);
```

Methods

new

```
multi method new ( :$orientation! )
```

Create a new object with an orientation set to GTK_ORIENTATION_HORIZONTAL or GTK_ORIENTATION_VERTICAL.

```
multi method new ( :$widget! )
```

Create an object using a native object from elsewhere. See also Gnome::GObject::Object.

```
multi method new ( Str :$build-id! )
```

Create an object using a native object from a builder. See also Gnome::GObject::Object.

gtk_paned_new

Creates a new native pane

```
method gtk_paned_new ( Int $orientation --> N-GObject )
```

Returns a native widget. Can be used to initialize another object using :widget. This is very cumbersome when you know that a oneliner does the job for you: `my Gnome::Gtk3::Paned \$m .= new(:\$orientation);

```
my Gnome::Gtk3::Paned $m;
$m .= :new(:widget($m.gtk_paned_new(GTK_ORIENTATION_HORIZONTAL));
```

gtk paned add1

Adds a child to the top or left pane with default parameters. This is equivalent to \$p.gtk_paned_pack1(\$child-widget, 0, 1).

```
method gtk_paned_add1 ( N-GObject $child-widget )
```

• \$child-widget; Native child widget to add. When a Perl6 widget object is provided, the native widget is retrieved from that object. See example in the synopsis.

gtk_paned_add2

Adds a child to the bottom or right pane with default parameters. This is equivalent to \$p.gtk paned pack2(\$child-widget, 1, 1).

```
method gtk_paned_add2 ( N-GObject $child-widget )
```

• \$child-widget; Native child widget to add. When a Perl6 widget object is provided, the native widget is retrieved from that object. See example in the synopsis.

gtk_paned_pack1

Adds a child to the top or left pane.

```
method gtk_paned_pack1 ( N-GObject $child, Int $resize, Int $shrink )
```

- \$child; the child to add. When a Perl6 widget object is provided, the native widget is retrieved from that object. See example in the synopsis.
- \$resize; should this child expand when the paned widget is resized.
- \$shrink; can this child be made smaller than its requisition.

gtk paned pack2

Adds a child to the bottom or right pane.

```
method gtk_paned_pack2 ( N-GObject $child, Int $resize, Int $shrink )
```

- \$child; the child to add. When a Perl6 widget object is provided, the native widget is retrieved from that object. See example in the synopsis.
- \$resize; should this child expand when the paned widget is resized.
- \$shrink; can this child be made smaller than its requisition.

[gtk paned] get child1

Obtains the first child of the paned widget.

```
method gtk_paned_get_child1 ( --> N-GObject )
```

Returns the first child

```
my Gnome::Gtk3::ListBox $lb .= new(:widget($p.get-child1()));
```

[gtk_paned_] get_child2

Obtains the second child of the paned widget.

```
method gtk_paned_get_child2 ( --> N-GObject )
```

Returns the second child

[gtk paned] set position

Sets the position of the divider between the two panes.

```
method gtk_paned_set_position ( Int $position )
```

• \$position; pixel position of divider, a negative value means that the position is unset.

[gtk paned] get position

Obtains the position of the divider between the two panes.

```
method gtk_paned_get_position ( --> Int )
```

Returns position of the devider.

[gtk paned] get handle window

Returns the GdkWindow of the handle. This function is useful when handling button or motion events because it enables the callback to distinguish between the window of the paned, a child and the handle.

```
method gtk_paned_get_handle_window ( --> N-GObject )
```

Returns a native GdkWindow

[gtk_paned_] set_wide_handle

Sets the "wide-handle" property.

```
method gtk_paned_set_wide_handle ( Int $wide )
```

• \$wide; the new value for the "wide-handle" property, this is 0 or 1.

[gtk_paned_] get_wide_handle

Gets the "wide-handle" property.

```
method gtk_paned_get_wide_handle ( --> Int )
```

Returns 0 or 1 for the wide-handle property.

Signals

Supported signals

accept-position

The accept-position signal is a keybinding signal which gets emitted to accept the current position of the handle when moving it using key bindings.

The default binding for this signal is **Return** or **Space**.

cancel-position

The cancel-position signal is a keybinding signal which gets emitted to cancel moving the position of the handle using key bindings. The position of the handle will be reset to the value prior to moving it.

The default binding for this signal is **Escape**.

toggle-handle-focus

The toggle-handle-focus is a keybinding signal which gets emitted to accept the current position of the handle and then move focus to the next widget in the focus chain.

The default binding is **Tab**.

Not yet supported signals

cycle-child-focus

The cycle-child-focus signal is a keybinding signal which gets emitted to cycle the focus between the children of the paned.

The default binding is **f6**.

cycle-handle-focus

The cycle-handle-focus signal is a keybinding signal which gets emitted to cycle whether the paned should grab focus to allow the user to change position of the handle by using key bindings.

The default binding for this signal is **f8**.

move-handle

The move-handle signal is a keybinding signal which gets emitted to move the handle when the user is using key bindings to move it.

Generated using Pod::Render, Pod::To::HTML, Camelia[™] (butterfly) is © 2009 by Larry Wall