Neo4j 安装

下载 Neo4j

1. 访问 neo4j 官网下载, 官网地址: https://neo4j.com/

Neo4j企业版3.5.13 2019年11月27日 发行说明 阅读更多 操作系统 下载 Linux / Mac Neo4j 3.5.13 (焦油) SHA-256	企业服务器	社区服务器	Neo4j 桌面
Neo4j 3.5.13 (焦油)	-	更多	
Linux / Mac	操作系统		下载
	Linux / Mac	N	
Neo4j 3.5.13 (zip) SHA-256	视窗	1	

2. 访问微云数据主页: http://we-yun.com/index.php/blog/releases-56. html, 提供国内 ftp 下载地址: ftp://neo4j.55555.io/neo4j/3.5.6/

安装

tar zxvf neo4j-community-3.5.6-unix.tar.gz -C ../servers/

```
cd /export/servers/neo4j-community-3.5.6/
vim conf/neo4j.conf

dbms.connectors.default_listen_address=0.0.0.0
dbms.connectors.default_advertised_address=0.0.0.0
```

```
dbms.connectors.default_listen_address=0.0.0.0

# You can also choose a specific network interface, and configure a r
port for each connector, by setting their individual listen_address

# The address at which this server can be reached by its clients. Thi
# it may be the address of a reverse proxy which sits in front of the
# individual connectors below.

dbms.connectors.default_advertised_address=0.0.0.0
```

vi /etc/profile

export NEO4J_HOME=/export/servers/neo4j-community-3.5.6 export PATH=:\$NEO4J_HOME/bin:\$PATH


source /etc/profile

启动 neo4j 服务

neo4j start

访问 web

http://192.168.52.129:7474/browser/



登录界面默认填充了用户名 neo4j。

输入默认密码 neo4j 后,修改密码 123456,进入 neo4j

Python 访问 Neo4j

安装驱动

pip install neo4j-driver

导包

from neo4j import GraphDatabase

建立连接

传递 Cypher 语句

```
session.run("CREATE (a:Persion {name:'alice'})")
result=session.run("MATCH (a:Persion) RETURN a.name")
for i in result:
    print(i['a.name'])
```

```
result = session.run("MATCH (a:Persion) RETURN a")
for i in result:
    print(i['a'])
```

关闭连接

session.close()

