

Assignment # 2

Objective:

- Working with the EC2 Instances
- Create an EC2 Instance
- Connect to the Instance








Step 1: Choose an Amazon Machine Image (AMI)

Cancel and Exit

An AMI is a template that contains the software configuration (operating system, application server, and applications) required to launch your instance. You can select an AMI provided by AWS, our user community, or the AWS Marketplace; or you can select one of your own AMIs.





Step 2: Choose an Instance Type

Amazon EC2 provides a wide selection of instance types optimized to fit different use cases. Instances are virtual servers that can run applications. They have varying combinations of CPU, memory, storage, and networking capacity, and give you the flexibility to choose the appropriate mix of resources for your applications. Learn more about instance types and how they can meet your computing needs.

Filter by: All instance families Current generation Show/Hide Columns

Currently selected: t2.micro (- ECUs, 1 vCPUs, 2.5 GHz, -, 1 GiB memory, EBS only)

Family ~	Type 🔻	vCPUs (j) 🔻	Memory (GiB)	Instance Storage (GB) (i) +	EBS-Optimized Available	Network Performance (i) -	IPv6 Support i
t2	t2.nano	1	0.5	EBS only	-	Low to Moderate	Yes
t2	t2.micro Free tier eligible	1	1	EBS only	-	Low to Moderate	Yes
t2	t2.small	1	2	EBS only	-	Low to Moderate	Yes
t2	t2.medium	2	4	EBS only	-	Low to Moderate	Yes
t2	t2.large	2	8	EBS only	-	Low to Moderate	Yes
t2	t2.xlarge	4	16	EBS only	-	Moderate	Yes
t2	t2.2xlarge	8	32	EBS only	-	Moderate	Yes
t3	t3.nano	2	0.5	EBS only	Yes	Up to 5 Gigabit	Yes

Cancel


Previous

Review and Launch

Next: Configure Instance Details

English (US) ▼

Feedback




Feedback



Step 4: Add Storage

Your instance will be launched with the following storage device settings. You can attach additional EBS volumes and instance store volumes to your instance, or edit the settings of the root volume. You can also attach additional EBS volumes after launching an instance, but not instance store volumes. Learn more about storage options in Amazon EC2.



Add New Volume

Free tier eligible customers can get up to 30 GB of EBS General Purpose (SSD) or Magnetic storage. Learn more about free usage tier eligibility and usage restrictions.

Cancel

Previous

Review and Launch

Next: Add Tags

Feedback




Step 5: Add Tags

A tag consists of a case-sensitive key-value pair. For example, you could define a tag with key = Name and value = Webserver.

A copy of a tag can be applied to volumes, instances or both.

Tags will be applied to all instances and volumes. Learn more about tagging your Amazon EC2 resources.




Cancel

Previous

Review and Launch

Next: Configure Security Group



Cancel

Previous

Review and Launch

Edit instance details Instance Details


Tags



Storage

Edit storage

Edit tags



Launch Status

Your instances are now launching

The following instance launches have been initiated: i-0173ee5b2a851ad01 View launch log

Get notified of estimated charges
Create billing alerts to get an email notification when estimated charges on your AWS bill exceed an amount you define (for example, if you exceed the free usage tier).

How to connect to your instances

Your instances are launching, and it may take a few minutes until they are in the running state, when they will be ready for you to use. Usage hours on your new instances will start immediately and continue to accrue until you stop or terminate your instances.

Click View Instances to monitor your instances' status. Once your instances are in the running state, you can connect to them from the Instances screen. Find out how to connect to your instances.


- ▼ Here are some helpful resources to get you started
- · How to connect to your Linux instance
- Amazon EC2: User Guide
- · Learn about AWS Free Usage Tier
- Amazon EC2: Discussion Forum


While your instances are launching you can also


- Create status check alarms to be notified when these instances fail status checks. (Additional charges may apply)
- · Create and attach additional EBS volumes (Additional charges may apply)
- Manage security groups


View Instances













i-0173ee5b2a851ad01 (Maazserver)

Public IPs: 18.116.13.247 Private IPs: 172.31.10.56