LYRA RECORDER

User Manual · Version 1.0

1. Introduction

Lyra Recorder is a professional audio capture application for Android. It supports spontaneous capture, where speed matters, and calibrated capture, where the recording environment is assessed before recording.

Its visual instruments provide practical, relative signal guidance. They are not calibrated acoustic laboratory instruments.

2. Two recording modes

Direct REC

Press REC to begin recording immediately, without a session calibration. HPF, LIMITER and AUTO PAUSE are unavailable in this mode. Use the GAIN knob and the live displays to adjust the recorded signal. Suitable for situations where immediate capture is essential.

Calibrated REC

Press CAL and follow the on-screen instructions. After successful calibration, the functions that depend on a valid calibration profile can be used. Then press REC. Suitable for interviews, conferences and controlled sessions.

3. Calibration

Press CAL to evaluate the microphone signal and recording environment. The guided session procedure includes two stages:

• **Silence reference:** remain quiet while the application measures the ambient noise floor.

• **Normal voice reference:** speak at the level and distance expected during the recording.

The results help establish relative signal indications and silence-detection conditions. If ambient noise is excessive, AUTO PAUSE may be unavailable. The CAL indicator becomes bright green when a valid calibration is active. Recalibrate when the environment or microphone conditions change.

Device-dependent reference behavior and environmental calibration serve different purposes; a session calibration should not be understood as an absolute sound-pressure-level measurement.

4. Controls

REC	Start recording in direct or calibrated mode.
STOP	Stop the current recording and save the file.
MARK	Add a marker and optional text note at the current position while recording.
CAL	Start the guided session calibration.
GAIN	Rotary control for recording gain; use the meters to assess level.
HPF	Optional high-pass filter for low-frequency rumble; requires a valid calibration.
LIMITER	Optional protection against signal overload; requires a valid calibration.
MONITOR	Live audio monitoring through an appropriate connected output.
AUTO II	Automatic pause/resume based on detected silence; options OFF, 1 s and 2 s, subject to calibration and ambient conditions.
P.BACK	Open the playback screen.
LIBRARY	Browse, manage and select the format of saved recordings.

5. Meters and visual references

Analog VU — RMS · REL

The analog needle represents sustained signal level (relative RMS), rather than instantaneous peak level. Use it to assess changes in average recording intensity. The colored scale provides practical visual zones; it is not an absolute sound-pressure-level reading.

Peak indicator — PK ····· FS

The peak indication is separate from the RMS needle and helps warn of high instantaneous signal levels relative to full scale (FS). Do not interpret the needle position as a guarantee that peaks cannot occur. Use the LIMITER where appropriate and continue to observe peak warnings.

Spectrum — FREQUENCY · Hz

The live spectrum shows how signal energy is distributed across frequency, with an axis extending toward 20 kHz. The display is intended for relative visual analysis; band magnitudes vary with the microphone, gain, source and device.

Waveform · FS

The live waveform shows signal variation over time on a normalized full-scale reference, with markings at +1, 0 and -1. It helps identify activity, relative amplitude and transients.

6. Playback

Press P.BACK to open playback. Each recording provides an overall waveform and a detailed view around the current position. Use the transport controls to play, pause and navigate, including -30 s, -10 s, +10 s and +30 s jumps. Markers appear on the recording timeline; select a marker to reach its saved position and note.

7. Files and formats

Supported output formats are WAV (uncompressed, 16-bit PCM at 44.1 kHz) and AAC (compressed at 256 kbit/s). Select the default format in LIBRARY. Recordings are stored locally and can be shared or exported through the Android share interface.

8. Trial and licensing

Lyra Recorder offers a 21-day trial period. Continued use after the trial requires the one-time purchase offered through Google Play. Initial trial registration and license checks may require an internet connection; short offline periods are supported subject to license validation.

9. Practical tips

• Calibrate in conditions representative of the intended recording; repeat when the room, noise level or microphone conditions change.

• If AUTO PAUSE is unavailable because of background noise, record without it or move to a quieter location.

• Use HPF for unwanted low-frequency noise and LIMITER when sources may become unexpectedly loud.

• Watch both relative RMS and peak indications. A stable RMS needle does not rule out short peaks.

• Mark important events during recording so they can be located quickly during playback.