




TIM3 Mode and Configuration

Mode

Slave Mode Disable 

Trigger Source Disable 

☒ Internal Clock

Channel1 Disable 

Channel2 Disable 

Channel3 Disable 

Channel4 Disable 

Combined Channels Disable 

☐ XOR activation

☐ One Pulse Mode

Configuration

Reset Configuration

 Parameter Settings
  User Constants
  NVIC Settings
  DMA Settings

NVIC Interrupt Table	Enabled	Preemption Priority	Sub Priority
TIM3 global interrupt	☒	0	0

TIM3 Mode and Configuration

Mode

Slave Mode	Disable	▼
Trigger Source	Disable	▼
☒ Internal Clock		
Channel1	Disable	▼
Channel2	Disable	▼
Channel3	Disable	▼
Channel4	Disable	▼
Combined Channels	Disable	▼
☐ XOR activation		
☐ One Pulse Mode		

Configuration

Reset Configuration

☒ Parameter Settings ☒ User Constants ☒ NVIC Settings ☒ DMA Settings

Configure the below parameters :

Search (Ctrl+F)		↶	↷	i
▼ Counter Settings				
Prescaler (PSC - 16 bits value)	7199			
Counter Mode	Up			
Counter Period (AutoReload Register -	4999			
Internal Clock Division (CKD)	No Division			
auto-reload preload	Disable			
▼ Trigger Output (TRGO) Parameters				
Master/Slave Mode (MSM bit)	Disable (Trigger input effect not delayed)			

GPIO Mode and Configuration

Configuration

Group By Peripherals

GPIO I2C RCC

Search Signals

Search (Ctrl+F) ☐ Show only Modified Pins

Pin Na...	Signal on ...	GPIO outp...	GPIO mode	GPIO Pull...	Maximum ...	User Label	Modified
PA0-WKUP	n/a	Low	Output Pu...	No pull-up ...	Low	motor_drive	☒
PA1	n/a	n/a	Input mode	Pull-up	n/a		☒
PA2	n/a	n/a	Input mode	Pull-up	n/a		☒
PA3	n/a	n/a	Input mode	Pull-up	n/a		☒

PA1 Configuration :

GPIO mode

Input mode

GPIO Pull-up/Pull-down

Pull-up

User Label