```
BR2 aarch64=y
BR2_ARM_FPU_VFPV4=y
BR2 CCACHE=y
BR2 TOOLCHAIN BUILDROOT GLIBC=y
BR2_PACKAGE_HOST_LINUX_HEADERS_CUSTOM_4_19=y
BR2_TOOLCHAIN_BUILDROOT_CXX=y
BR2 TARGET GENERIC ROOT PASSWD="12345"
BR2_SYSTEM_DHCP="eth0"
BR2_ROOTFS_OVERLAY="/home/marcelle/overlay_source"
BR2_ROOTFS_POST_BUILD_SCRIPT="board/raspberrypi3-64/post-build.sh board/
raspberrypi3-64/mp3_player_post_build.sh"
BR2_ROOTFS_POST_IMAGE_SCRIPT="board/raspberrypi3-64/post-image.sh"
BR2_ROOTFS_POST_SCRIPT_ARGS=" - - aarch64"
BR2_LINUX_KERNEL=y
BR2_LINUX_KERNEL_CUSTOM_TARBALL=y
BR2_LINUX_KERNEL_CUSTOM_TARBALL_LOCATION="$(call github,raspberrypi,linux,raspberrypi-
kernel_1.20190819-1)/linux-raspberrypi-kernel_1.20190819-1.tar.gz
BR2_LINUX_KERNEL_DEFCONFIG="bcmrpi3"
BR2_LINUX_KERNEL_DTS_SUPPORT=y
BR2_LINUX_KERNEL_INTREE_DTS_NAME="broadcom/bcm2710-rpi-3-b broadcom/bcm2710-rpi-3-b-
plus broadcom/bcm2837-rpi-3-b"
BR2_LINUX_KERNEL_NEEDS_HOST_OPENSSL=y
BR2_PACKAGE_ALSA_UTILS=y
BR2_PACKAGE_ALSA_UTILS_ALSACONF=y
BR2_PACKAGE_ALSA_UTILS_APLAY=y
BR2_PACKAGE_ATEST=y
BR2_PACKAGE_ATEST=y
BR2_PACKAGE_AUMIX=y
BR2_PACKAGE_BLUEZ_ALSA=y
BR2_PACKAGE_BLUEZ_ALSA_HCITOP=y
BR2_PACKAGE_BLUEZ_ALSA_RFCOMM=y
BR2_PACKAGE_ESPEAK=y
BR2_PACKAGE_ESPEAK_AUDIO_BACKEND_ALSA=y
BR2_PACKAGE_MPV=y
BR2_PACKAGE_PULSEAUDIO=y
BR2_PACKAGE_PULSEAUDIO_DAEMON=y
BR2_PACKAGE_RPI_BT_FIRMWARE=y
BR2_PACKAGE_RPI_BT_FIRMWARE=y
BR2_PACKAGE_RPI_FIRMWARE=y
# BR2 PACKAGE RPI FIRMWARE INSTALL DTB OVERLAYS is not set
BR2 PACKAGE RPI WIFI FIRMWARE=y
BR2_PACKAGE_AUBTO=y
BR2_PACKAGE_AUDIOFILE=y
BR2_PACKAGE_BCG729=y
BR2_PACKAGE_LIBID3TAG=y
BR2_PACKAGE_LIBMAD=y
BR2_PACKAGE_BLUEZ_TOOLS=y
BR2_PACKAGE_BLUEZ5_UTILS_OBEX=y
BR2_PACKAGE_BLUEZ5_UTILS_CLIENT=y
BR2_PACKAGE_BLUEZ5_UTILS_DEPRECATED=y
BR2_PACKAGE_BLUEZ5_UTILS_EXPERIMENTAL=y
BR2_PACKAGE_BLUEZ5_UTILS_PLUGINS_HEALTH=y
BR2_PACKAGE_BLUEZ5_UTILS_PLUGINS_MIDI=y
BR2_PACKAGE_BLUEZ5_UTILS_PLUGINS_NFC=y
BR2_PACKAGE_BLUEZ5_UTILS_PLUGINS_SAP=y
BR2 PACKAGE BLUEZ5 UTILS TEST=y
BR2 PACKAGE OPENSSH=y
BR2 PACKAGE WPA SUPPLICANT=y
BR2 PACKAGE WPA SUPPLICANT AUTOSCAN=y
BR2 PACKAGE UTIL LINUX=y
BR2 PACKAGE UTIL LINUX WALL=y
BR2 PACKAGE UTIL LINUX WRITE=y
BR2 TARGET ROOTFS EXT2=y
BR2_TARGET_ROOTFS_EXT2_4=y
```

BR2_TARGET_ROOTFS_EXT2_SIZE="300M" # BR2_TARGET_ROOTFS_TAR is not set BR2_PACKAGE_HOST_DOSFSTOOLS=y BR2_PACKAGE_HOST_GENIMAGE=y BR2_PACKAGE_HOST_MTOOLS=y