🎰 Game Testing: Opening, Betting, Mode Switching, and Audio Functionality...

ℹ️ Game opening:

TC ID	Test Case Name	Preconditions	Steps	Expected Result
TC-001	Verify game opens successfully on desktop	Player is logged in and has access to the selected game. Supported desktop browser is used.	1. Open the game launch page. 2. Select the required game. 3. Open the game. 4. Wait for the game to finish loading.	The game opens successfully without errors.
TC-003	Verify game loads completely without errors	Player is logged in and has access to the selected game. Stable internet connection is available.	1. Open the selected game.2. Wait until the game finishes loading.3. Observe the game interface.	The game loads completely without a stuck loading screen, blank screen, missing elements, or unexpected error messages.
TC-004	Verify game UI is displayed correctly after opening	Player is logged in and the selected game is available.	1. Open the game.2. Wait until the game is fully loaded.3. Check the game interface.	All applicable UI elements are displayed correctly, including reels, symbols, Spin button, bet controls, balance, settings, and other available controls. No elements are overlapping, cut off, or incorrectly positioned.

TC-005	Verify player balance is displayed correctly when opening the game	Player is logged in and has a known account balance.	1. Note the player's balance before opening the game.2. Open the selected game.3. Check the balance displayed inside the game.	The balance displayed inside the game matches the player's actual account balance.
TC-006	Verify correct currency is displayed when opening the game	Player is logged in and has a configured account currency.	1. Open the selected game.2. Check the currency displayed in the game.	The player's configured account currency is displayed correctly in the game.
TC-007	Verify default bet amount is displayed correctly when opening the game	Player is logged in. The game has a configured default bet amount.	1. Open the selected game.2. Check the displayed bet amount.	The correct default bet amount is displayed when the game is opened and is available for placing a bet.
TC-008	Verify game can be opened from the game lobby	Player is logged in. The selected game is available in the game lobby.	1. Navigate to the game lobby.2. Locate the selected game.3. Click/tap the game.4. Wait for the game to load.	The selected game opens successfully and the player is not redirected to an incorrect game or page.
TC-009	Verify game opens successfully using the direct game URL -	Player is logged in and has access to the selected game. A valid game URL is available.	1. Open the game URL in a supported browser.2. Wait for the game to load.	The correct game opens successfully and all applicable game information is loaded correctly.

Place a bet:

Balance & Deduction Accuracy

TC ID	Test Case Name	Steps	Expected Result
TC-010	Correct deduction on valid bet	Place a bet of a fixed amount (e.g., 10) with sufficient balance	Balance reduces by exactly the bet amount; new balance = old balance − bet
TC-011	Deduction reflects immediately in UI	Place a bet and observe balance display	Balance updates in real-time without needing refresh/reload
TC-012	Multiple sequential bets	Place several bets in a row	Each bet deducts correctly; cumulative deduction = sum of all bets
TC-013	Min bet deduction	Place the minimum allowed bet	Correct minimal amount deducted
TC-014	Max bet deduction	Place the maximum allowed bet	Correct maximum amount deducted, no overflow errors

Winning:

TC ID	Test Case Name	Steps	Expected Result
TC-015	Balance unchanged when no win	Play a round with no win	No win popup/animation appears; UI returns to idle state normally
TC-016	Balance updates only after animation completes	Win a round with animation	Win amount transfering after animation will be end.

TC-017	Balance updates without requiring manual refresh	Win a round	Balance updates automatically in real-time, no page/app refresh needed
TC-018	Balance updates before next bet is allowed	Win a round, attempt to place next bet immediately	Next bet uses the updated (post-win) balance, not the stale pre-win balance

Insufficient Funds Handling

TC ID	Test Case Name	Steps	Expected Result
TC-019	Bet greater than balance	Attempt to bet more than current balance	Bet is rejected; error message shown; no deduction occurs
TC-020	Bet exactly equal to balance	Bet the full remaining balance	Bet accepted; balance becomes 0; no negative balance
TC-021	Zero balance bet attempt	With balance = 0, attempt any bet	Bet blocked; prompt to deposit/top-up shown
TC-022	Balance depleted mid-session	Play until balance hits 0 during a round	Game gracefully stops accepting further bets; appropriate message displayed
TC-023	Bet below minimum limit	Enter a bet amount lower than game's minimum	Bet rejected with validation message; no deduction
TC-024	Bet above table/game max limit, entering manually	Enter a bet exceeding max limit	Bet rejected; no deduction/return the max bet amount.

TC-025	Negative bet amount	Manually input a negative value	Request rejected, no deduction.

Timing:

TC ID	Test Case Name	Steps	Expected Result
TC-026	Double-click / rapid bet submission	Click "Place Bet" multiple times quickly	Only one deduction occurs per intended bet; no duplicate charges
TC-027	Concurrent bets across multiple tabs/devices	Log in on two sessions, place bets simultaneously	Balance updates consistently across sessions; no race condition allowing overdraw

Post-Bet / Rollback Scenarios

TC ID	Test Case Name	Steps	Expected Result
TC-028	Bet cancelled before round starts (if allowed) - eg: Aviator	Place bet, then cancel within allowed window	Full amount refunded/restored to balance
TC-029	Round fails to start after deduction	Simulate game engine failure after bet deducted	System auto-refunds the deducted amount

Game History:

TC ID	Test Case Name	Steps	Expected Result
TC-030	Balance history/statement accuracy	Place several bets, check transaction history page	All deductions listed accurately in chronological order



Demo/Real - Mode Switch

TC ID	Test Case Name	Steps	Expected Result
TC-031	Launch game in demo mode	Open game via "Demo" option	Game launches successfully in demo mode; demo indicator visible
TC-032	Launch game in real money mode	Open game via “Real Money" option	Game launches successfully in real mode; real balance displayed
TC-033	Switch from demo to real mode mid-session	While in demo mode, select "Real" option	Game reloads/switches into real mode correctly; demo balance discarded
TC-034	Switch from real to demo mode mid-session	While in real mode, select "Play for Fun/Demo" option	Game reloads/switches into demo mode correctly; real balance not affected

Balance Handling During Switch

TC ID	Test Case Name	Steps	Expected Result
TC-035	Demo balance is separate from real balance	Play in demo, note demo balance; switch to real mode	Real balance shown is unaffected by demo balance/activity
TC-036	Demo balance resets appropriately	Play in demo mode, spend/win virtual credits, switch away and return to demo	Demo balance resets to default starting value (per game design)
TC-037	Real balance persists correctly after switching from demo	Play in demo, switch to real mode	Real balance shown matches actual wallet balance (no demo contamination)

TC-038	No real funds used while in demo mode	Play multiple rounds in demo mode	Real wallet balance remains completely untouched throughout
TC-039	Switching modes does not carry over bet amount incorrectly	Set a specific bet amount in demo, switch to real mode	Bet amount either resets to default or correctly carries over per game design (verify intended behavior)
TC-040	Autoplay stops when switching modes	Enable autoplay in one mode, attempt to switch mode	Autoplay stops automatically before/during the switch
TC-041	Switching mode with insufficient real balance	Switch from demo to real mode with 0 or low real balance	Real mode still loads correctly; deposit prompt shown if balance is 0 (no crash)
TC-042	Rapid repeated mode switching	Quickly switch between demo and real mode multiple times	No crashes, freezes, or balance/state corruption from rapid toggling

ℹ Music/Audio turn On/Off

TC ID	Test Case Name	Steps	Expected Result
TC-043	“Background music” plays on game launch	Open the game	Background music starts playing automatically (or per platform autoplay policy)
TC-044	Win sound plays on win	Trigger a winning round	Win sound effect plays, matching win tier (small/medium/big win)
TC-045	“Sound Effect” plays on game launch	Open the game and spin once	After the spin, there should be sound in slot games.

TC-046	Big win/mega win celebration sound	Trigger a large win	Special big-win sound/fanfare plays, distinct from regular win sound
TC-047	Mute all sound via master toggle	Tap the mute/sound icon	All sound (music + effects) stops immediately
TC-048	Unmute restores all sound	Tap mute icon again to unmute	All sound resumes correctly (music and effects both return)
TC-049	Mute background music only	If separate control exists, mute music only	Music stops; sound effects (spin, win, click) still play
TC-050	Mute sound effects only	If separate control exists, mute SFX only	Sound effects stop; background music continues playing
TC-051	Mute state during active spin	Mute sound while reels are spinning	Sound cuts off immediately without glitch/cutoff artifact
TC-052	Volume set to max doesn't distort/clip (background, sound effect)	Set volume to maximum	Sound plays clearly without distortion, crackling, or clipping
TC-053	change sounds volume (background, sound)	Change sounds min, middle, max	Sound Changing
TC-054	Sound setting persists after closing and reopening game	Mute sound, close game, reopen	Game reopens with sound still muted. (Depends game rules)
TC-055	Sound setting persists across different games	Mute sound in Game A, open Game B (same Provider, lobby)	Mute setting carries over to Game B
TC-056	Sound setting resets appropriately per device (if device-specific)	Mute on Device A, check Device B	Setting is either independent per device

			or synced per account, per intended design — verify consistency
TC-057	Sound works correctly with Bluetooth/wired headphones	Connect headphones, play game	Audio routes correctly through headphones, no delay or dropout
TC-058	Sound behavior during phone call interruption (mobile)	Receive a call while playing	Game audio pauses appropriately during call, resumes after call ends

Cross-Browser Compatibility

TC ID	Test Case Name	Steps	Expected Result
TC-059	Game loads on **Google Chrome**	Open game on latest Chrome version	Game loads fully, all assets render, fully playable
TC-060	Game loads on **Mozilla Firefox**	Open game on latest Firefox version	Game loads fully, all assets render, fully playable
TC-061	Game loads on **Safari**	Open game on latest Safari version (Mac/iOS)	Game loads fully, all assets render, fully playable
TC-062	Game loads on **Microsoft Edge**	Open game on latest Edge version	Game loads fully, all assets render, fully playable
TC-063	Game loads on **Opera**	Open game on latest Opera version	Game loads fully, all assets render, fully playable

TC-064	Game on older browser version/any, if possible	Open game on an older but still supported browser version	Game loads with acceptable performance, no critical feature breakage
TC-065	In-private/**incognito** mode compatibility	Open game in incognito/private browsing mode	Game loads and functions correctly, no broken storage-dependent features
TC-066	Browser zoom in/out	Zoom browser to 50%, 100%, 150%, 200%	UI scales or adjusts without breaking layout, elements not cut off or overlapping
TC-067	Multiple browser tabs open simultaneously	Open same game in two tabs of the same browser	Error message “multiple session not allowed”
TC-068	Browser refresh mid-session	Refresh page while playing	Game reloads cleanly, session/balance state recovers correctly

Device Compatibility

TC ID	Test Case Name	Steps	Expected Result
TC-069	Game loads on Android phone (various OEMs)	Test on Samsung, Google Pixel, Xiaomi, etc.	Game loads and plays correctly across different Android devices
TC-070	Game loads on iPhone (various models)	Test on latest and older supported iPhone models	Game loads and plays correctly across iPhone models
TC-071	Game loads on Android tablet	Open game on Android tablet	UI adapts correctly to tablet screen size, fully playable
TC-072	Game loads on iPad	Open game on iPad	UI adapts correctly to iPad screen size, fully playable

TC-073	Interruption handling – incoming call	Receive a call while playing on mobile	Game pauses/handles interruption gracefully, resumes correctly after
TC-074	Interruption handling – notification pull-down	Pull down notification shade mid-game	Game state remains intact when returning to game
TC-075	Low battery mode	Enable low power/battery saver mode, play game	Game remains functional, possibly with reduced animations, no crash
TC-076	Mobile data vs WiFi	Play game on mobile data, then switch to WiFi mid-session	Game continues functioning smoothly across network type switch

Localization / Multi-language

TC ID	Test Case Name	Steps	Expected Result
TC-077	Language selector is accessible	Open settings/menu, locate language option	Language selector is easy to find and opens correctly
TC-078	Default language matches account/browser setting	Open game without manually selecting language	Game loads in correct default language based on account setting or browser locale
TC-079	Switching language updates UI text	Select a different language from the list	All visible text (buttons, menus, labels) updates to selected language
TC-080	Language setting persists after reload	Switch language, refresh page/app	Selected language remains active after reload
TC-081	Win/loss messages translated	Trigger a win and a loss	Win/loss popup text displayed in correct

			language
TC-082	Error messages translated	Trigger an error (e.g., insufficient balance)	Error message shown in correct selected language
TC-083	Date/time format matches locale (in history)	Check transaction history timestamps	Date/time displayed in correct regional format (DD/MM vs MM/DD, 12h vs 24h)
TC-084	Sound/voiceover localization (if applicable)	Switch language where game has voiceovers	Voice/audio cues match selected language
TC-085	Language switch mid-session	Change language while actively playing	UI updates immediately without requiring full game restart (or reloads cleanly if restart is by design)
TC-086	Consistent language across game and lobby/platform	Change game from game lobby	changing game from lobby should affect on another game.
TC-087	Currency mismatch with language.	Select a language whose region typically uses different currency than account's actual currency	Language and currency remain correctly independent — Game currency doesn't change just because language changed
TC-088	Language persists through demo/real mode switch	Switch language, then switch between demo and real mode	Language setting remains consistent across both modes
	No mixed-language text in single screen	Check each screen carefully after language switch	No screen shows a mix of two languages simultaneously (indicates incomplete translation load)