

#### **OFFICE OF INFORMATION TECHNOLOGY**

HOSTEL WIRED CONNECTION SETUP GUIDE FOR WINDOWS

VERSION 1.0

18 JANUARY 2017

#### **Table of Contents**

| Purpose                                                         | 3    |
|-----------------------------------------------------------------|------|
|                                                                 |      |
| New configuration                                               | 3    |
|                                                                 |      |
| Updating your credentials (Upon changing your network password) | . 13 |

### Purpose

1. The purpose of this guide is to demonstrate to users how to setup a connection to the hostel's wired connection using a device running the Windows Operating System.

### New configuration

- 1. Follow the below steps based on the operating system that you are using.
  - Windows 7

Click on start menu. Type: "services.msc" and then press: "Enter".



Windows 8


Under Search, type: "local services".




## • Windows 10

Go to Step 4.

2. Right click on: "Wired AutoConfig" and select: "Properties".



3. Change Startup type to Automatic and click: "Start" then "OK".



- 4. Follow the below steps based on the operating system that you are using.
  - Windows 7

Click on start menu and select Control Panel.




Windows 8

Under Search, type: "Control Panel" and select: "Control Panel".



• Windows 10

Click on start menu and select Control Panel.



- 5. Select: "Network and Sharing Center" or "Network and Internet" depending on your Control Panel view.
  - Large Icon View




Category View




6. Click on "Change adapter settings".




- 7. Right click on "Local Area Connection" or "Ethernet". Choose "Properties".
  - Windows 7 (Local Area Connection)




• Windows 8 and Windows 10 (Ethernet)



8. Click on the "Authentication" tab. Check "Enable IEEE 802.1x authentication, Remember my credentials for this connection each time I'm logged on", and. "Fallback to unauthorized network access". Choose "Microsoft Protected EAP (PEAP)" as network authentication method. Then click: "Settings".




9. Check only the "Enable Fast Reconnect" checkbox. Choose "Secured password (EAP-MSCHAP v2)" as the "Authentication Method". Then click on "Configure".




10. Uncheck: "Automatically use my Windows logon name and password (and domain (if any)" check box. Click: "OK".




11. Click: "OK".



#### 12. Click: "Additional Settings".



13. Check: "Specify authentication mode", Select "User authentication" and click on "Save credentials".




14. Key in your student network credentials when prompted. Click: "OK".

**Username**: < Enter your Network Username; e.g. 1234567)

Password: <Enter your Network Username Password>



15. Click: "OK".



- 16. You will be successfully connected to SUTD network upon keying in the correct credentials.
  - Windows 7 (Bottom left of screen)




• Windows 8 / 10 (Under Network Connections)



# Updating your credentials (Upon changing your network password)

- 1. Repeat step 1 to 12.
- 2. Click: "Replace credentials".



3. Key in your updated student network credentials when prompted.

Click: "OK".

Username: <Enter your Network Username; e.g. 1234567)

Password: <Enter your Network Username Password>



- 4. Upon successful update of the credentials, you will be connected to SUTD network.
  - Windows 7 (Bottom left of screen)



Windows 8 / 10 (Under Network Connections)

