

План IP адресации V4

	Подсеть	Диапазон	Хосты
Филиал 1			
VLAN1	85.91.28.0/29	.1-.6	ХостВ 85.91.28.2 ХостD 85.91.28.3 interface VLAN1 85.91.28.1
VLAN2	85.91.28.8/29	.9-.14	ХостС 85.91.28.10 ХостЕ 85.91.28.11 interface VLAN2 85.91.28.9
VLAN3	85.91.28.16/29	.17-.22	ХостF 85.91.28.18 interface VLAN3 85.91.28.17
R1	85.91.28.24/30 85.91.28.28/30	.25-.26 .29-.30	interface Fa0/0.1 85.91.28.1 (VLAN1) interface Fa0/0.2 85.91.28.9 (VLAN2) interface Fa0/0.3 85.91.28.17 (VLAN3) interface Se0/0/0 85.91.28.29 (R0) interface Se0/0/1 85.91.28.35 (R2)
Филиал 2			
R2	85.91.28.24/30 85.91.28.32/30 85.91.28.36/30 85.91.28.40/29	.25-.26 .33-.34 .37-.38 .41-.46	ХостG 85.91.28.42 interface Fa0/0 85.91.28.41 (Host G) interface Se0/0/0 85.91.28.33 (R0) interface Se0/0/1 85.91.28.26 (R1) interface Se0/3/0 85.91.28.37 (R3)
R3	85.91.28.36/30 85.91.28.48/29	.37-.38 .49-.54	ХостK 85.91.28.50 interface Fa0/0 85.91.28.49 (Host K) interface Se0/0/0 85.91.28.38 (R2)
Центральный офис			
R0	85.91.28.28/30 85.91.28.32/30 85.91.28.56/30 123.45.67.80/29	.29-.30 .33-.38 .57-.62 .81-.88	ХостА 85.91.28.58 interface Fa0/0 85.91.28.57 (Host A) interface Fa0/1 123.45.67.81 (HSRP) interface Se0/0/0 85.91.28.30 (R1) interface Se0/2/1 85.91.28.34 (R2)
Сеть "Интернет"			
R4	123.45.67.80/29 123.45.67.88/29	.81-.86 .89-.94	ХостH 123.45.67.89 HSRP слева 123.45.67.89 HSRP справа 123.45.67.92 interface Fa0/0 (R0) 123.45.67.82 interface Fa0/1 123.45.67.90(Host H)
R5	123.45.67.80/29 123.45.67.88/29	.81-.86 .89-.94	ХостH 123.45.67.89 HSRP слева 123.45.67.89 HSRP справа 123.45.67.92 interface Fa0/0 (R0) 123.45.67.83 interface Fa0/1 123.45.67.91(Host H)