

MDN Plus now available in [your](#) country! Support MDN [and](#) make it your own. [Learn more](#) ✨

Element.removeAttribute()

The [Element](#) method **removeAttribute()** removes the attribute with the specified name from the element.

Syntax

```
removeAttribute(attrName)
```

Parameters

attrName

A string specifying the name of the attribute to remove from the element. If the specified attribute does not exist, `removeAttribute()` returns without generating an error.

Return value

None ([undefined](#)).

Usage notes

You should use `removeAttribute()` instead of setting the attribute value to `null` either directly or using [setAttribute\(\)](#). Many attributes will not behave as expected if you set them to `null`.

DOM methods dealing with element's attributes:

Not namespace-aware, most commonly used methods	Namespace-aware variants (DOM Level 2)	DOM Level 1 methods for dealing with Attr nodes directly (seldom used)	DOM Level 2 namespace-aware methods for dealing with Attr nodes directly (seldom used)
setAttribute (DOM 1)	setAttributeNS	setAttributeNode	setAttributeNodeNS
getAttribute (DOM 1)	getAttributeNS	getAttributeNode	getAttributeNodeNS
hasAttribute (DOM 2)	hasAttributeNS	-	-
removeAttribute (DOM 1)	removeAttributeNS	removeAttributeNode	-

Examples

```
// Given: <div id="div1" align="left" width="200px">
document.getElementById("div1").removeAttribute("align");
// Now: <div id="div1" width="200px">
```

Specifications

Specification

Specification
DOM Standard # ref-for-dom-element-removeattribute ⁽¹⁾

Browser compatibility

[Report problems with this compatibility data on GitHub](#)

	Chrome	Edge	Firefox	Opera	Safari	Chrome Android	Firefox for Android	Opera Android
removeAttribute	Chrome 1	Edge 12	Firefox 1	Opera 8	Safari 1	Chrome 18 Android	Firefox 4 for Android	Opera 10 Android

Tip: you can click/tap on a cell for more information.

Full supportSee implementation notes.

Last modified: Sep 13, 2022, [by MDN contributors](#)