Java Web Development Basics

Java EE Workshop – Servlets & JSP

MeTube v.3

MeTube is like YouTube, "ama ne bash" like an old Bulgarian Sage once said. You have been tasked to implement this application for literally no money, by the richest man on earth. There are several requirements you must follow in the implementation.

In this part you will extend the MeTube application by adding **Admin** functionality.

1. Database Requirements

Extend the **Database** of the application by adding:

UserRole

Can be either "User" or "Admin".


TubeStatus

• Can be either "Pending", "Approved" or "Declined".

Add a **UserRole** property to the **User** entity and a **TubeStatus** property to the **Tube** entity.

2. Templates


Admins have access to an additional button on their navbar.



That button redirects to the **Pending Tubes page (url = "/admin/tube/pending")**

It should look like this:























NOTE: All the templates have been given to you as .html files. You need to make .jsp files from them.

NOTE: The templates do **NOT require additional CSS** for you to write. Only **bootstrap** and the **given css** are enough.

Functional Requirements

The first registered User in the database should be given role — "Admin". All others should be regular Users.

Tubes are created with status — "Pending" by default. Tubes with status Pending can only be seen by an Admin on the **Pending Tubes** page or by a **User** on their **Profile page**. An Admin can **Approve** or **Decline** Tubes from the Pending Tubes page.

Approved Tubes are visualized on the Index page.

Declined Tubes can only be accessed by the **Uploader**'s **Profile Page**.

Security Requirements

The Security Requirements are mainly access requirements. Configurations about which users can access specific functionalities and pages.

- **Guest** (not logged in) users can access **Index** page.
- Guest (not logged in) users can access Login page.
- **Guest** (not logged in) users can access **Register** page.
- Users (logged in) can access Home page.
- **Users** (logged in) can access **Profile** page.
- **Users** (logged in) can access **Upload** functionality.
- **Users** (logged in) can access **Details** functionality.
- **Users** (logged in) can access **Logout** functionality.
- Admins (logged in, with role "Admin") can access the Pending Tubes functionality.
- Admins (logged in, with role "Admin") can access the Approve Tubes functionality.
- Admins (logged in, with role "Admin") can access the Decline Tubes functionality.















