COMP2611: Computer Organization

Introduction (For L2 students)

Course's homepage http://course.cse.ust.hk/comp2611

Lecture

4:30-5:50, Wed/Fri, Room 2502 (Lift 25/26)

Instructor: Cindy LI Xin <u>lixin@cse.ust.hk</u>

Office: RM 3535

You also need to attend Tutorials and Labs, which are useful necessary supplements to lectures

Reading the textbook is also a very important part in the workflow of this course.

Course Facebook: search HKUST CSE COMP2611 Spring 2015

□ Grading

- 2 Quizzes 15% (2 x 7.5%)
- Course Project 15%
- Midterm Exams 30%
 - Mar 21 (Sat) 10:00am
- Final Exam 40%

□ Policies

- Course project should be individual work; both 'provider' and 'copier' will be penalized equally and harshly
- Skipping the midterms or final examination without prior approval will automatically lead to an "F" grade for the course

- □ How do computers represent data? Electrical signals (two states)
 - Therefore computing relies on base 2 to represent numbers.
- □ What is base 2 anyway?
 - We actually use base 10 (decimal) in our daily calculations
 - 1452 is actually: $\frac{1}{10^3} \frac{4}{10^2} \frac{5}{10^1} \frac{2}{10^0}$
 - Base 10 has 10 digits 0, 1, 2, 3, 4, 5, 6, 7, 8 and 9
 - O Base 2 (binary) uses two digits or (Bits) 0 and 1
 - $8_{10} = 1000_2$; $17_{10} = 10001_2$
 - Conversion from base 10 to 2 is done via successive divisions by 2
- Many other bases have been used over the millennia
 - Base 60 (Sumerians civilization in Iraq, remnants are found in timekeeping)
 - Base 1 | | | | | | | | | | | | | (herringbone) 一丁下正
 - Base 16 (hexadecimal) very useful in Computer Science (seen later)
 - 0, 1, 2, 3, 4, 5, 6, 7, 8, 9, A, B, C, D, E, F

■ When dealing with a size (e.g., Memory or file)

- O Kilo − 2¹⁰ or 1024
- Mega 2²⁰ or 1024 Kilo

- Peta 2⁵⁰ or 1024 Tera
- ... **C**

Example:

- The memory in my computer is 4 Gigabytes
- The PPT file for this lecture is2.5 Megabytes

- When dealing with a rate/frequency (e.g., # instructions per second, # clock ticks per second)
 - \circ Kilo -10^3 or 1000
 - \circ Mega -10^6 or 1000 Kilo
 - \circ Giga -10^9 or 1000 Mega
 - Tera -10^{12} or 1000 Giga
 - Peta 10¹⁵ or 1000 Tera
 - O ...

Example:

- The speed of my network card is
 1 Gigabit per second
- The speed of my Intel processor is
 2.89 Gigahertz

Computers have led to a **third revolution** for civilization: agricultural -> industrial -> **information**

□ Desktop computers:


- Run a variety of general purpose software
- Designed to achieve good performance at low cost

□ Embedded computers:

- Usually hidden as a component of a system (e.g., mobile phone, cars, airplanes, ATM machines, Smart card, ...)
- Run a predefined program
- Subject to a stringent power/performance/cost constraint


□ Servers and Networked computers:

- High storage and computing capacity, performance and reliability
- Used to run large programs for multiple users
- Only accessible via a network
- Range from small servers to building sized, to several thousand computers in a grid






■ Examples of embedded system





■ Examples of server


□ Number of Distinct Processors sold between 1997 and 2007 in millions




Why you're Here?


- ☐ Why do you take COMP2611?
- □ What have you heard about COMP2611 from senior students?
- ☐ What do you expect to learn from COMP2611?


Computer in the Oooooooooold Days





What did the Programmer Do?






How does computer understand your instruction?



```
swap(int v[], int k)
{int temp;
  temp = v[k];
  v[k] = v[k+1];
  v[k+1] = temp;
}
```

"What" you will learn in COMP2611

- □ How programs are translated from high level programming language to machine language
- How the hardware executes programs written in machine language
- ☐ The interface between the hardware and the software or the Instruction Set Architecture (ISA)
- What determines the performance of a program and how it can be improved
- How hardware designers improve the performance
- ☐ How to measure and analyze computer performance
- To tell why a design is good or bad Chapter 1
- How computers work
- Computer Arithmetic and implementation Chapter 3
- Issues affecting design of modern processors Chapters 2, 4 (and 7)
- Exploiting memory hierarchy Chapter 5
- I/O Chapter 6 (depending on the progress)



□ Application software

- Written in high-level language
- Ex: Comp2011 assignment written in C++


☐ System software

- Compilers: translates HLL code to machine code
- Operating System: service code
 - Handle input/output
 - Manage memory and storage
 - Schedule tasks & share resources

□ Hardware

- O Processor,
- o memory,
- I/O controllers

for human



for machine

High-level language program (in C)

Assembly (low-level) language program (for MIPS)

Binary machine language program (for MIPS)

```
swap(int v[], int k)
{int temp;
  temp = v[k];
  v[k] = v[k+1];
  v[k+1] = temp;
}

swap:
  muli $2, $5,4
```

```
muli $2, $5,4
add $2, $4,$2
lw $15, 0($2)
lw $16, 4($2)
sw $16, 0($2)
sw $15, 4($2)
jr $31
```

□ High-level language

- Level of abstraction closer to the problem domain
- Helps increase productivity, portability and simplify debugging

□ Assembly language


- Binary instructions represented in symbolic notation
- One to one mapping with binary instructions
- Assemblers translate from Assembly language to machine language

□ Hardware representation

- Computers only deal with binary digits (bits)
- Instructions and data are encoded as bit strings

```
swap(int v[], int k)
{int temp;
  temp = v[k];
  v[k] = v[k+1];
  v[k+1] = tem p;
        C compiler
swap:
   m u li $2, $5,4
   add $2,$4,$2
        $15,0($2)
        $16, 4($2)
        $16,0($2)
        $15,4($2)
      $31
        Assembler
```

 Impossible to understand computer components by looking at every single transistor. Instead, **abstraction** is needed.



☐ Key ideas:


- Both hardware and software are organized into hierarchical layers.
- Hierarchical organization helps to cope with system complexity.
- Lower-level details are hidden to offer a simpler view at the higher levels.
- Interaction between levels occurs only through well-defined interface.

□ Example:

 Interface between hardware and software: Instruction set architecture (ISA) An **instruction set architecture (ISA)** provides an **abstract interface** between hardware and low-level software.

- Advantage: allows different implementations of varying cost and performance to follow the same instruction set architecture (i.e., to run the same software).
 - Example: 80x86, Pentium, Pentium II, Pentium III, Pentium 4 all implement the same ISA
- □ Some instruction set architectures:
 - 80x86/Pentium/K6 (offers different implementations)
 - O MIPS
 - PowerPC
 - **O ARM**
 - **O HP PA-RISC**
 - Sparc

Anything in Common?







Five Basic Components (all kinds of computers)

□ Input:


- To communicate with the computer
- Data and instructions transferred to the memory


□ Output:

- To communicate with the user
- Data is read from the memory

□ Memory:


- Large store to keep instructions and data
- □ **Processor**, which consists of:
 - O Datapath: processes data according to instructions.
 - **Control**: commands the operations of input, output, memory, and datapath according to the instructions.






Opening the Box: in My College Days








☐ AMD Barcelona: 4 processor cores






- □ Volatile main memory (RAM)
 - Used by the processor to store programs and data
 - Loses instructions and data when powered off
- Non-volatile secondary memory
 - Magnetic disk
 - Flash memory
 - Optical disk (CDROM, DVD)











What are These Technologies?









Technology Trends

- Increased capacity and performance
- □ Reduced cost

□ Processor:


- **Logic capacity**: ~30% per year
- Clock rate: ~20% per year

■ Memory:

- DRAM capacity: ~60% per year (or ~4X every 3 years)
- **Memory speed**: ~10% per year
- Cost per bit: decreases ~25% per year


□ Disk:


○ **Capacity**: ~60% per year



Year	Technology used in computers	Relative performance per unit cost
1951	Vacuum tube	1
1965	Transistor	35
1975	Integrated circuit (IC)	900
1995	Very large scale integrated (VLSI) circuit	2,400,000
2005	Ultra large scale integrated circuit	6,200,000,000

Microprocessor Transistor Counts 1971-2011 & Moore's Law





- ☐ Five basic components of a computer
 - input, output, memory, processor (datapath + control)
- □ Principle of abstraction

Help cope with design complexity by hiding low level details

- □ Instruction set architecture
 - Important abstraction interfaces hardware with low-level software