

Hollow Room Editing Guide for Rafal

Practical checklist for opening curated runtime rooms, creating safe editable copies, validating, playtesting, and exporting room bundles.

Purpose

This guide is for reviewing and editing existing runtime rooms safely. Curated rooms are source templates; opening one creates an editable copy in your selected profile slot, so canonical runtime JSON is never mutated by accident.

What You Can Edit

Area	Allowed in Room Designer	Notes
Layout	Ground, holes, rocks, macro footprint-aware chunks	Footprint is chosen at creation time and cannot be resized in-place.
Spawns	Safe start, reward marker, normal/flying/fast/heavy/charger/turret/splitter enemy spawns	Boss/key/shop markers stay controlled by branch logic for now.
Doors	available, door, secret, inactive	Inactive ports stay visible in the editor but are omitted from runtime export.
Preview	Graybox or Scene mode	Scene mode is visual-only; gameplay still comes from HollowRuntime V2 JSON.

Open a Curated Runtime Room

- Open Unity and run the game or open `Assets/\_Hollow/Scenes/RoomDesigner.unity`.
- Select a profile slot, then open `Room Designer`.
- In the library, use the `Curated Runtime Rooms` section.
- Choose a room such as `Approved Crossroads 1x1` or `Combat Macro L 3-Cell`.
- Opening a curated row creates a draft named like `... - Edit Copy` in the selected profile slot.
- Edit the copy, not the source. Delete/duplicate/open actions for local drafts work as normal.

Current Curated Room Set

Runtime ID	Shape	Why it matters
combat_macro_single_1x1	1x1	Baseline small combat room.
combat_macro_wide_2x1	2x1	Horizontal macro-room with multiple side ports.
combat_macro_tall_1x2	1x2	Vertical macro-room with multiple north/south lanes.
combat_macro_block_2x2	2x2	Large block room for macro connectivity checks.
combat_macro_l_3cell	L	L-shape branch topology and boundary check.
approved_crossroads_single_1x1	1x1	Approved small-room content sample.
approved_lane_wide_2x1	2x1	Wide lane room with stronger obstacle rhythm.
approved_watchtower_tall_1x2	1x2	Tall room with ranged/flying encounter anchors.

Runtime ID	Shape	Why it matters
approved_quadrant_block_2x2	2x2	Large room with quadrant obstacle structure.
approved_broken_I_3cell	L	Approved L-room content sample.

Core Controls

Action	Keyboard	Controller / UI fallback
Move cursor	WASD or arrows	D-pad / left stick
Cycle tool	Q / E	Shoulders
Layer up/down	Z / X	Triggers
Place / erase	Space or Enter / Delete	South / East
Eyedropper	F	West
Labels	Tab	North
Preview mode	V	Preview button
Camera mode	C	Camera button
Zoom	- / +	Zoom - / Zoom + buttons
Playtest / export	P / J / U	HUD actions when available

Validation Before Handoff

- There must be exactly one safe start on walkable ground.
- There must be at least one enemy spawn for branch-ready combat rooms.
- There must be at least one non-inactive exposed door port.
- Markers cannot sit on holes or blocking rocks.
- Warnings are allowed for low enemy density, no reward marker, or all doors on one side, but review them before export.

Export and Approval Workflow

- Use `J` to export the validated bundle: designer project JSON, runtime HollowRuntime V2 JSON, USDA companion, and validation report.
- The exported runtime JSON is the gameplay truth; USDA is only a visual/semantic companion.
- Send the exported bundle for review. Do not directly overwrite files in `DesignerApproved` unless Martin approves the room.
- After approval, the runtime JSON can be placed in `Assets/\_Hollow/Data/Rooms/DesignerApproved/`, then curated drafts can be regenerated.