

Software metrics


Delivery Metrics

Deployment Frequency: Measures how often updates are released to production.

Lead Time: The total time from request to full deployment of a product or feature, encompassing the entire development and delivery workflow. A key indicator of organizational efficiency.

Cycle Time: The time it takes to complete a specific part of the workflow, from development start to task completion. This metric highlights team productivity and potential bottlenecks.

Lead Time for Changes: Measures the time from a code commit to deployment in production. Short lead times indicate efficient automated workflows.



Stability Metrics

Change Failure Rate: Tracks the percentage of deployments that need immediate fixes or rollbacks.

Mean Time Between Failures (MTBF): The average time between successive system failures. A high MTBF suggests system stability, while low MTBF calls for improvements in reliability and fault tolerance.

Mean Time to Detect (MTTD): The average time to identify a failure, performance issue, or security problem. Low MTTD ensures quick response to minimize impact on users and business.

Mean Time to Recovery (MTTR): The average time needed to restore a service after a failure. A low MTTR reflects efficient incident response, with practices like continuous monitoring and automated recovery.

Flow Metrics


Flow Metrics (introduced by the *Flow Framework* by Mik Kersten) help teams understand the **efficiency of the software delivery process itself** — identifying bottlenecks, handoff delays, and waste in the value stream. They measure how work items (features, bugs, risks, technical debts) flow from idea to production. The main Flow Metrics are:

Flow Time: Measures the total time it takes for a work item to go from “start” (when development begins) to “finish” (when value is delivered to users).

- Indicates how long customers wait for value.
- Related to DORA’s *Cycle Time*, but considers the *entire value stream*, not just code-to-deploy.



Flow Time




Flow Efficiency: The ratio between *active time* (when work is progressing) and *total flow time* (including waiting).

- Highlights process inefficiencies, approval delays, and overburdened teams.
- High variability or low efficiency signals bottlenecks or context switching.



Flow Efficiency




Flow Load: The total number of active work items in progress.

- Helps manage team capacity and prevent overload.
- Strongly correlates with *cycle time* and *quality* — when load is too high, delivery slows and error rates rise.




Flow Load




Flow Distribution: Tracks the proportion of different types of work (e.g., features, defects, technical debt, risks).

- Balancing these categories ensures sustainable development — too little time on debt and risk reduction leads to long-term fragility.



Flow Velocity: The number of work items completed per unit of time.

- Measures delivery throughput.
- Should be analyzed together with Flow Time and Efficiency to avoid focusing solely on output.



DORA metrics


The [DORA metrics](#) were developed by the DevOps Research and Assessment (DORA) organization, which spent years studying engineering teams and their DevOps processes. They also deliver an interesting [annual report](#).




These metrics are valuable because:

- they **correlate with business outcomes** and employee satisfaction, offering industry standards for benchmarking.
- push teams to focus on **continuous improvement**.

- **only four key metrics are needed** to differentiate elite engineering teams from mediocre ones.



How to improve metrics within an organization?



- **Monitor**
- **Reduction of Codebase Size (also PR size)**

- **Automation (CI/CD Pipelines, Deployments Strategies)**

Resources

- <https://www.youtube.com/watch?v=H3nlvHQHb5E>
- <https://www.youtube.com/watch?v=7d5Sah0M6Zg>