ASSIGNMENT-1

a) Create a directory /hadoop/hdfs/ in HDFS

```
hadoop@hadoop-VirtualBox:~$ hdfs dfs -mkdir -p /hadoop/hdfs/
24/07/02 19:02:36 WARN util.NativeCodeLoader: Unable to load native-hadoop library for your platform... using builtin-java classes wh
ere applicable
hadoop@hadoop-VirtualBox:~$
```

b) Create a temp directory in Hadoop. Run HDFS command to delete "temp" directory.

```
hadoop@hadoop-VirtualBox:~$ hdfs dfs -mkdir /hadoop/hdfs/temp
24/07/02 19:04:33 WARN util.NativeCodeLoader: Unable to load native-hadoop library for your platform... using builtin-java classes wh
ere applicable
hadoop@hadoop-VirtualBox:~$ hdfs dfs -rm -r /hadoop/hdfs/temp
24/07/02 19:05:16 WARN util.NativeCodeLoader: Unable to load native-hadoop library for your platform... using builtin-java classes wh
ere applicable
24/07/02 19:05:19 INFO fs.TrashPolicyDefault: Namenode trash configuration: Deletion interval = 0 minutes, Emptier interval = 0 minut
es.
Deleted /hadoop/hdfs/temp
hadoop@hadoop-VirtualBox:~$
```

c) List all the files/directories for the given hdfs destination path.

```
hadoop@hadoop-VirtualBox:~$ hdfs dfs -ls /hadoop/
24/07/02 19:08:11 WARN util.NativeCodeLoader: Unable to load native-hadoop library for your platform... using builtin-java clas
ere applicable
Found 1 items
drwxr-xr-x - hadoop superg<u>r</u>oup 0 2024-07-02 19:05 /hadoop/hdfs
```

d) Command that will list the directories in /hadoop folder.

```
h<mark>adoop@hadoop-VirtualB</mark>ox:~$ hdfs dfs -ls -d /hadoop/*
24/07/02 19:10:10 WARN util.NativeCodeLoader: Unable to load native-hadoop library for your platform... using builtin-java classes
ere applicable
drwxr-xr-x - hadoop superg<u>r</u>oup 0 2024-07-02 19:05 /hadoop/hdfs
```

e) Command to list recursively all files in hadoop directory and all subdirectories in hadoop directory

```
hadoop@hadoop-VirtualBox:~$ hdfs dfs -ls -R /hadoop/
24/07/02 19:11:38 WARN util.NativeCodeLoader: Unable to load native-hadoop library for your platform... using builtin-java classes wh
ere applicable
drwxr-xr-x - hadoop supergroup 0 2024-07-02 19:05 /hadoop/hdfs
hadoop@hadoop-VirtualBox:~$
```

f) List all the directory inside /hadoop/hdfs/ directory which starts with "dir"

```
hadoop@hadoop-VirtualBox:~$ hdfs dfs -ls -d /hadoop/hdfs/dir*
24/07/02 19:37:36 WARN util.NativeCodeLoader: Unable to load native-hadoop library for your platform..
ere applicable
ls: `/hadoop/hdfs/dir*': No such file or directory
hadoop@hadoop-VirtualBox:~$
```

g) Create a temp.txt file. Copies this file from local file system to HDFS

```
hadoop@hadoop-VirtualBox:~$ nano temp.txt
hadoop@hadoop-VirtualBox:~$ nano temp.txt
hadoop@hadoop-VirtualBox:~$ hdfs dfs -put temp.txt/
24/07/02 19:48:59 WARN util.NativeCodeLoader: Unable to load native-hadoop library for your platform... using builtin-java classes where applicable
put: `.': No such file or directory
hadoop@hadoop-VirtualBox:~$ hdfs dfs -put temp.txt /
24/07/02 19:49:38 WARN util.NativeCodeLoader: Unable to load native-hadoop library for your platform... using builtin-java classes where applicable
```

h) Copies the file from HDFS to local file system.

```
hadoop@hadoop-VirtualBox:~$ hdfs dfs -get /temp.txt
24/07/02 19:51:33 WARN util.NativeCodeLoader: Unable to load native-hadoop library for yo
ere applicable
get: `temp.txt': File exists_
```

i) Command to copy from local directory with the source being restricted to a local file reference.

/hadoop/hdfs										
Permission	Owner	Group	Size	Last Modified	Replication	Block Size	Name			
-rw-rr	hadoop	supergroup	19 B	7/2/2024, 7:11:41 PM	1	128 MB	asign.txt			

j) Command to copies to local directory with the source being restricted to a local file reference.



k) Command to move from local directory source to Hadoop directory.

/hadoop									
Permission	Owner	Group	Size	Last Modified	Replication	Block Size	Name		
drwxr-xr-x	hadoop	supergroup	0 B	7/2/2024, 7:11:41 PM	0	0 B	hdfs		
-rw-rr	hadoop	supergroup	34 B	7/2/2024, 7:14:37 PM	1	128 MB	temp.txt		

l) Deletes the directory and any content under it recursively.

```
hadoop@hadoop-VirtualBox:~$ hdfs dfs -rm -r /hadoop/hdfs/asign.txt
24/07/02 20:18:34 WARN util.NativeCodeLoader: Unable to load native-hadoop library for your platform... using builtin-java classes wh
ere applicable
24/07/02 20:18:38 INFO fs.TrashPolicyDefault: Namenode trash configuration: Deletion interval = 0 minutes, Emptier interval = 0 minut
es.
Deleted /hadoop/hdfs/asign.t<u>x</u>t
```

m) List the files and show Format file sizes in a human-readable fashion.

n) Take a source file and outputs the file in text format on the terminal.

```
hadoop@hadoop-VirtualBox:~$ hdfs dfs -text /hadoop/temp.txt
24/07/02 20:30:17 WARN util.NativeCodeLoader: Unable to load native-hadoop library for your platform... using builtin-java classes wh
ere applicable
this is temp file,containing data
```

o) Display the content of the HDFS file test on your /user/hadoop2 directory.

```
h<mark>adoop@hadoop-VirtualBox:~$ hdfs dfs -cat /hadoop/test.txt</mark>
24/07/02 20:37:48 WARN util.NativeCodeLoader: Unable to load native-hadoop library for your platform... using builtin-java classes wh
ere applicable
how ara you
```

p) Append the content of a local file test1 to a hdfs file test2.

```
hadoop@hadoop-VirtualBox:~$ hdfs dfs -appendToFile test1.txt /hadoop/test.txt
24/07/02 20:40:56 WARN util.NativeCodeLoader: Unable to load native-hadoop library for your platform... using builtin-java classes wh
ere applicable
```

q) Show the capacity, free and used space of the filesystem
hadoop@hadoop-VirtualBox:~\$ hors drs -dr -h /
24/07/02 20:42:36 WARN util.NativeCodeLoader: Unable to load native-hadoop library for your platform... using builtin-java classes wh
ere applicable
Filesystem Size Used Available Use%
hdfs://localhost:9000 19.6 6 240 K 10.9 G 0%

r) Shows the capacity, free and used space of the filesystem. Add parameter Formats the sizes of files in a human-readable fashion.

```
hadoop@hadoop-VirtualBox:~$ hdfs dfs -du -h /hadoop/
24/07/02 20:44:47 WARN util.NativeCodeLoader: Unable to load native-hadoop library for your platform... using builtin-java classes wh
ere applicable
0 /hadoop/hdfs
34 /hadoop/temp.txt
54 /hadoop/test.txt
```

s) Show the amount of space, in bytes, used by the files that match the specified file pattern.

```
hadoop@hadoop-VirtualBox:~$ hdfs dfs -du -s /hadoop/test.txt
24/07/02 20:49:44 WARN util.NativeCodeLoader: Unable to load native-hadoop library for your platform... using builtin-java classes wh
ere applicable
54 /hadoop/test.txt
```

t) Show the amount of space, in bytes, used by the files that match the specified file pattern. Formats the sizes of files in a human-readable fashion.

```
hadoop@hadoop-VirtualBox:~$ hdfs dfs -du -s -h /hadoop/test.txt
24/07/02 20:50:48 WARN util.NativeCodeLoader: Unable to load native-hadoop library for your platform... using builtin-java classes wh
ere applicable
54 /hadoop/test.txt
```

u) Check the health of the Hadoop file system.

v) Command to turn off the safemode of Name Node.

```
hadoop@hadoop-VirtualBox:~$ hdfs dfsadmin -safemode leave
24/07/02 20:54:23 WARN util.NativeCodeLoader: Unable to load native-hadoop library for your platform... using builtin-java classes wh
ere applicable
Safe mode is OFF
```

w) HDFS command to format NameNode.

hdfs namenode -format

x) Create a file named hdfstest.txt and change it number of replications to 3.

hadoop@hadoop-VirtualBox:~\$ hdfs dfs -setrep 3 /hadoop/hdfstest.txt
24/07/02 21:06:13 WARN util.NativeCodeLoader: Unable to load native-hadoop library for your platform... using builtin-java classes where applicable
Replication 3 set: /hadoop/hdfstest.txt

y) Write command to display number of replicas for hdfstest.txt file

hadoop@hadoop-VirtualBox:~\$ hdfs dfs -stat %r /hadoop/hdfstest.txt
24/07/02 21:07:46 WARN util.NativeCodeLoader: Unable to load native-hadoop library for your platform... using builtin-java classes wh
ere applicable
3

z) Write command to Display the status of file "hdfstest.txt" like block size. filesize in bytes.

hadoop@hadoop-VirtualBox:~\$ hdfs dfs -stat "%b %o %r %n %y %u %g" /hadoop/hdfstest.txt
24/07/02 21:09:53 WARN util.NativeCodeLoader: Unable to load native-hadoop library for your platform... using builtin-java classes wh
ere applicable
19 134217728 3 hdfstest.txt 2024-07-02 18:01:25 hadoop supergroup

aa) Write HDFS command to change file permission from rw - r - r to rwx-rw-r for hdfstest.txt.

Hdfs dfs -chmod 777 /hadoop/hdfstest.txt