★安装前请务必退出杀毒软件


InstallShield

打开 windows-setup.exe,右键以**管理员身份**运行安装,中间过程请全部默认,尽量不要修改安装路径。如 C盘大小确实不够(需要大约10G),请在别的盘符先创建文件夹,命名为 Thales(若安装 8.0 及以下版本开发包,文件夹名称为 Gemalto Sentinel),安装的文件放到这个文件夹路径下。

8.3 版本开发包需要安装在 win10 系统。若您的开发电脑是 win7 或者 win8, 需要安装 8.0 版本的开发包。

对于终端客户使用则不受限制,终端客户使用支持 win7/win8/win10 以及新的 server 系统。





Cancel

Next >

Sentinel LDK THALES

License Agreement

Please read the following license agreement carefully.

SENTINEL LDK PRODUCT END USER LICENSE AGREEMENT

IMPORTANT INFORMATION - PLEASE READ THIS AGREEMENT CAREFULLY BEFORE USING THE CONTENTS OF THE PACKAGE AND/OR BEFORE DOWNLOADING OR INSTALLING THE SOFTWARE PRODUCT. ALL ORDERS FOR AND USE OF THE SENTINEL® LDK PRODUCTS (including without limitation, the Developer's Kit, libraries, utilities, diskettes, CD_ROM, DVD, Sentinel keys, the software component of Sentinel LDK, and the Sentinel LDK Software Protection and Licensing Guide) (hereinafter "Product") SUPPLIED BY THALES DIS CPL USA, Inc., or one of its affiliates, (in each case, referred to hereinas "THALES") ARE AND SHALL BE, SUBJECT TO THE TERMS AND CONDITIONS SET FORTH IN THIS AGREEMENT.

BY OPENING THE PACKAGE CONTAINING THE PRODUCTS AND/OR BY DOWNLOADING THE SOFTWARE (as defined hereunder) AND/OR BY INSTALLING THE SOFTWARE ON YOUR COMPUTER AND/OR BY USING THE PRODUCT, YOU ARE ACCEPTING THIS AGREEMENT AND AGREEING TO BE





Installation Options

✓ Vendor Suite

Sentinel Vendor Suite includes all Sentinel LDK developer tools – including Envelope for application protection, ToolBox for API exploration and generation, and all API samples and interfaces. Sentinel Vendor Suite must be installed to integrate licensing and protection into your application.

- ✓ Entitlement Management System
 - O Sentinel EMS hosted by Thales
 - O Sentinel LDK-EMS hosted by Thales or on your network
 - Sentinel LDK-EMS install on this machine

Sentinel LDK-EMS, the Entitlement Management System of Sentinel LDK, is a front-end component used for license generation and management. This option installs Sentinel LDK-EMS on this machine. After you complete this installation, configure the Sentinel LDK-EMS connection using the Sentinel LDK launcher.


For configuration instructions, click the link below.


Sentinel LDK Installation Guide

<u>N</u>ext >

Cancel

InstallShield





Sentinel LDK THALES

Installing Sentinel LDK

The program features you selected are being installed.

Staging

Sentinel Vendor Suite.msi



这里等待时间比较久,会自动安装 SQL Server2019 以及 openJDK 等。

Sentinel LDK - Installation Wizard

Sentinel LDK THALES


Installation Wizard Completed

The Installation Wizard has successfully installed Sentinel LDK. Click Finish to exit the wizard.

✓ Launch Sentinel LDK


<u>F</u>inish

安装结束后,提示如下信息:




请点击"**不是现在**",先确认 EMS 能否登录。


点开 LDK-EMS,配置 EMS 地址: http://127.0.0.1:8080/ems/login.html






输入用户名和密码(默认都是 admin),按照提示修改密码,登录成功后即表明 LDK 开发包安装成功。







之后安装我们提供的3个补丁,也都是右键以管理员身份安装,全部默认。

 LDK
 SLDK_8.3.001
 2021/12/9 12:06
 应用程序


 LDK
 SLDK_8.3.002
 2021/12/14 11:20
 应用程序

 LDK
 SLDK_8.3.100
 2021/12/23 13:18
 应用程序

若您需要安装汉化包,可以打开安装后的路径: C:\Program Files (x86)\Thales\Sentinel LDK\VendorTools\VendorSuite\translations,右键管理员身份安装 Sentinel_LDK_8.3_zh-CHS.exe。



安装好之后,界面显示如下:



此时 Sentinel LDK 开发包安装过程全部完成。