

Profile Algorithms Sample Configuration

Q

To Profile Coordinates - Line - Baseline Intersections

×

Parameter

Protokoll

Intersection Line Layer

sample_source_data — waterways [EPSG:25832]

...

Profil Baseline

sample_source_data — baseline [EPSG:25832]

...

Elevation Raster

sample_dem [EPSG:25832]

...

Z-Factor / Ueberhoehung

1

✕

↑

↓

Profil_Line Intersection Points

[Temporärlayer erzeugen]

...

☒ Öffne Ausgabedatei nach erfolgreicher Ausführung

Line - Baseline Intersections

Get the intersections from a line layer with the baseline and transform them to profile coordinates.

A baseline can have breakpoints.

Select one line feature or use an one feature layer as Baseline.

0%

Abbruch

Erweitert

Als Batchprozess starten...

Starte

Schließen

Parameter

Protokoll

Point Layer

sample_source_data — directed points_for_structural_planes

Profil Baseline

sample_source_data — baseline [EPSG:25832]

Baseline Buffer(used if no points selection)

100,000000

Elevation Raster

sample_dem [EPSG:25832]

Z-Factor / Ueberhoehung

1,000000

Z-Value Field [optional]

horizontal direction in degrees

1.2 EINFALLRI

angle of depression in degrees

1.2 EINFALLWI

Result Line Length [optional]

1000,000000

Profil_Plane Intersections

[Temporärlayer erzeugen]

☒ Öffne Ausgabedatei nach erfolgreicher Ausführung

Plane - Baseline Intersections (Directed Points)

This function calculates the intersection lines of a series of planes with the vertical cross-section plane.

For each directed point objekt it will calculate a intersection line on each base line segment. It is conform with calculation of the apparent dip.

The planes are defined by a reference point with a horizontal direction and a vertical angle.

The parameter **horizontal direction** means the directional angle from north, measures clockwise in degrees. (north=0°; east=90°; west=270°)

The parameter **angle of depression** (true dip) means the angle between the horizontal and the direction of fall in degrees. (horizontal=0°; nadir=90°)

The parameter **Result Line Length** regulates the length of the intersection line in the cross section plane.

Kinked base lines are permitted and will be fully processed.

0%

Abbruch

Erweitert

Als Batchprozess starten...

Starte

Schließen

Parameter

Protokoll

Intersection Polygon Layer

 sample_source_data — geologic_polygons [EPSG:25832] ...

Profil Baseline

 sample_source_data — baseline [EPSG:25832] ...

Elevation Raster

 sample_dem [EPSG:25832] ...

Z-Factor / Ueberhoehung

1

Output Geometry Type

Lines

Profil_Polygon Intersections

[Temporärlayer erzeugen] ...

☒ Öffne Ausgabedatei nach erfolgreicher Ausführung

Polygon - Baseline Intersections

Get the intersections from a polygon layer with the baseline and transform them to profile coordinates.

The intersection range can be represented through points or lines.

A baseline can have breakpoints.

Select one line feature or use an one feature layer as Baseline.

0%

Abbruch

Erweitert ▾

Als Batchprozess starten...

Starte

Schließen

Parameter

Protokoll

Point Layer

 sample_source_data — log_geological_strata [EPSG:25832] 

Profil Baseline

 sample_source_data — baseline [EPSG:25832] 

Baseline Buffer (used if no points selection)

100,000000 

Elevation Raster

 sample_dem [EPSG:25832] 

Z-Factor / Ueberhoehung

1,000000  

Z-Value Field [optional]

1.2 GEL_HOEHE 

Depth (Start) [optional]

1.2 TIEFE_VON 

Depth (End) [optional]

1.2 TIEFE_BIS 

Profil_Points

[Temporärlayer erzeugen] 

☒ Öffne Ausgabedatei nach erfolgreicher Ausführung

Points (incl. Bore Axis)

Transforms a point layer or selection to profile coordinates with considering of elevation.

If points has z values, they will used.

If the the point z value are in a feature attribute, you can use it for elevation.

If the points have no relationship to an elevation value, elevation is used from a Raster DEM.

This Function is processing only the points inside a buffer around the Baseline or if there is a selection, all selected points.

Extrapolation is not supported. Points have to be perpendicular to the baseline.

Select one line feature or use an one feature layer as Baseline.

A baseline can have breakpoints.

If the baseline is a polylinestring, there could be blind spots. Points in blind spots will be ignored.

0%

Abbruch

Erweitert ▾

Als Batchprozess starten...

Starte

Schließen

Parameter

Protokoll

Profil Baseline

sample_source_data — baseline [EPSG:25832]

Elevation Raster

sample_dem [EPSG:25832]

Z-Factor / Ueberhoehung

1

☐ Use Raster Values = 0

☒ Use Raster Values < 0

☐ Use Raster NoData

Baseline Gradient

[Temporärlayer erzeugen]

☒ Öffne Ausgabedatei nach erfolgreicher Ausführung

Raster Gradient

Transforms a single Line to profile coordinates with considering of elevation.

A baseline can have breakpoints.

Select one line feature or use an one feature layer as Baseline.

NoData, zero and negative Values in the elevation raster can excluded in the final output line.

0%

Abbruch

Erweitert ▾

Als Batchprozess starten...

Starte

Schließen