









```
Multilayer Switch0
    Physical Config CLI Attributes
     Switch>en
     SwitchFen
SwitchFonf t
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)$int range fa0/1-2
Switch(config-if-range)$channel_protocol lacp
Switch(config-if-range)$channel group 1 mode active
$ Ambiguous command: "Channel group 1 mode active"
Switch(config-if-range)$wiremory
      % Invalid input detected at '^' marker.
     Switch(config-if-range) #ex
Switch(config) #wr memory
      % Invalid input detected at '^' marker.
      Switch(config) #ex
      Switch# %SYS-5-CONFIG_I: Configured from console by console
      wr memory
Building configuration...
       Switch#conf t
     Switchfconf t
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config)#inr range fa0/3-4
Switch(config-if-range)#channel-protocol lacp
Switch(config-if-range)#channel-group 2 mode active
Switch(config-if-range)#
Creating a port-channel interface Port-channel 2
      %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/3, changed state to down
      %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/3, changed state to up
      %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/4, changed state to down
      %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/4, changed state to up
      % Invalid input detected at '^' marker.
      Switch(config-if-range) #wr memory
      % Invalid input detected at '^' marker.
     Switch(config-if-range) #ex
Switch(config) #ex
Switch#
$SYS-5-CONFIG I: Configured from console by console
wr memory
Building configuration...
[OK]
Switch#conf t
Enter configuration commands, one per line. End with CNTL/Z.
Switch(config) #int range fa0/5-6
Switch(config-if-range) #channel-protocol lacp
Switch(config-if-range) #channel-group 3 mode active
Switch(config-if-range) #
      Switch(config-if-range)#
Creating a port-channel interface Port-channel 3
       %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/5, changed state to down
       %LINEPROTO-5-UPDOWN: Line protocol on Interface FastEthernet0/5, changed state to up
```

