

# Classes

## Python repr method

The Python \_\_repr\_\_() method is used to tell Python what the *string representation* of the class should be. It can only have one parameter, self , and it should return a string.

```
class Employee:
    def __init__(self, name):
        self.name = name

    def __repr__(self):
        return self.name

john = Employee('John')
print(john) # John
```

## Python class methods

In Python, *methods* are functions that are defined as part of a class. It is common practice that the first argument of any method that is part of a class is the actual object calling the method. This argument is usually called **self**.

```
# Dog class
class Dog:
    # Method of the class
    def bark(self):
        print("Ham-Ham")

# Create a new instance
charlie = Dog()

# Call the method
charlie.bark()
# This will output "Ham-Ham"
```

## **Instantiate Python Class**

In Python, a class needs to be instantiated before use. As an analogy, a class can be thought of as a blueprint (Car), and an instance is an actual implementation of the blueprint (Ferrari).

```
class Car:
   "This is an empty class"
   pass
# Class Instantiation
ferrari = Car()
```



## **Python Class Variables**

In Python, class variables are defined outside of all methods and have the same value for every instance of the class.

Class variables are accessed with the instance.variable or class name.variable syntaxes.

```
class my_class:
   class_variable = "I am a Class
Variable!"

x = my_class()

y = my_class()

print(x.class_variable) #I am a Class
Variable!

print(y.class_variable) #I am a Class
Variable!
```

# Python init method

In Python, the .\_\_init\_\_() method is used to initialize a newly created object. It is called every time the class is instantiated.

```
class Animal:
    def __init__(self, voice):
        self.voice = voice

# When a class instance is created, the instance variable
# 'voice' is created and set to the input value.
cat = Animal('Meow')
print(cat.voice) # Output: Meow

dog = Animal('Woof')
print(dog.voice) # Output: Woof
```

# Python type() function

The Python type() function returns the data type of the argument passed to it.

```
a = 1
print(type(a)) # <class 'int'>

a = 1.1
print(type(a)) # <class 'float'>

a = 'b'
print(type(a)) # <class 'str'>

a = None
print(type(a)) # <class 'NoneType'>
```



#### **Python class**

In Python, a class is a template for a data type. A class can be defined using the class keyword.

```
# Defining a class
class Animal:
   def __init__(self, name,
number_of_legs):
     self.name = name
     self.number_of_legs = number_of_legs
```

# Python dir() function

In Python, the built-in dir() function, without any argument, returns a list of all the attributes in the current scope.

With an object as argument, dir() tries to return all valid object attributes.

```
class Employee:
    def __init__(self, name):
        self.name = name

    def print_name(self):
        print("Hi, I'm " + self.name)

print(dir())

# ['Employee', '__builtins__', '__doc__',
    '__file__', '__name__', '__package__',
    'new_employee']

print(dir(Employee))

# ['__doc__', '__init__', '__module__',
```

'print name']

# \_\_main\_\_ in Python

In Python, \_\_main\_\_ is an identifier used to reference the current file context. When a module is read from standard input, a script, or from an interactive prompt, its \_\_name\_\_ is set equal to \_\_main\_\_ .

Suppose we create an instance of a class called CoolClass . Printing the type() of the instance will result in:

This means that the class CoolClass was defined in the current script file.



<class '\_\_main\_\_.CoolClass'>

code cademy