Application Lecture 2: Network Performance

7COM1030 - Multicast and Multimedia Networking

Dr. Xianhui Che (Cherry)

x.che@herts.ac.uk

School of Computer Science University of Hertfordshire, UK







Performance Management

- How smoothly is the application running?
- The goal is to measure and make available various aspects of network performance so that internetwork performance can be maintained at an acceptable level.
- ▶ Examples of performance variables:



Throughput




Response time



- Multicast and Multimedia Networking

Network utilization



Response Time

- ▶ Typical measurement:
 - End-to-End Delay (ETE) is the response time in the application level.
 - TCP or UDP Transmission Delay is the measurement of network delay in the transport level.

M1030 - Multicast and Multimedia Networking

- ETE delay is normally used to evaluate network performance. This measurement is widely used in the industrial field.
- Network delay in the transport layer is used to observe the protocol performance. This measurements are mostly used in the academic and research field.

7COM1030 - Multicast and Multimedia Networking

Universit

Acceptable ETE Delay

▶ ETE delay should be maintained at ≤ ms level. Each protocol may have different requirement for the ETE delay.

Case Study:

- The size of a typical webpage is about 50kb.
- Surveys have shown that internet users will start to lose interests if the web page is not displayed after 10 seconds; and after 20 seconds if the page is still not displayed properly, most users will give up and close the page connection.
- Hence, to achieve the best performance, the ETE delay needs to be kept under 0.2ms;
- To achieve acceptable performance, the ETE delays should be 0.4ms at most.

Application Lecture 2 - Network Performance

7COM1030 - Multicast and Multimedia Networking

University of Hertfordshire



Throughput

▶ Throughput is the data transfer rate. Measures the data amount being transferred per time unit.

Unit	Symbol	10×	2 ×
Kilo-bits per second	Kb/s	10 ³	2 ¹⁰
Mega-bits per second	Mb/s	10 ⁶	2 ²⁰
Giga-bits per second	Gb/s	10 ⁹	2 ³⁰
Tera-bits per second	Tb/s	10 ¹²	2 ⁴⁰
Peta-bits per second	Pb/s	10 ¹⁵	2 ⁵⁰
Exa-bits per second	Eb/s	10 ¹⁸	260
Zetta-bits per second	Zb/s	10 ²¹	2 ⁷⁰
Yotta-bits per second	Yb/s	10 ²⁴	280

30 - Multicast and Multimedia Networking

Throughput Measurement

- Usual measurements are:
 - What is the current throughput of a network that runs a certain traffic
 - profile? What is the maximum throughput given a certain network topology and link capacity?
- Current Throughput is determined by the following elements in the network:
 - Traffic profile of applications (services)
 - Congestion situation
- Maximum Throughput, a.k.a. Network Capacity, gives the limit for the data transporting in the network. Two ways to obtain this value:
 - By pushing the simulation to the extreme (recommended)
 - By measurement based on equation (not exactly accurate)


Application Lecture 2 - Network Performance


- Multicast and Multimedia Networking



Goodput

- Goodput is an effective measurement for the network efficiency.
- It only measures the useful bits throughput during an end-to-end transmission, excluding protocol overheads, re-transmission, acknowledgement, etc.
- Goodput is always smaller than throughput.
- Goodput stats can be collected at the transport layer.
- A good technique to collect TCP goodput is to measure the ACK sequence number.






Network Utilization

▶ Can be calculated by

current throughput/maximum throughput

- An alternative is to measure the link utilization, which is much easier and more straightforward.
- A good network solution is to try to achieve the maximum network utilization so that network resources are not wasted.
- The network reaches saturation state once the maximum network utilization level is met.




11030 - Multicast and Multimedia Networking

Application Lecture 2 - Network Performance

Link Capacity vs. Network Capacity

- Throughput increases with the link utilization.
- The network normally reaches the maximum capacity before the links reach the maximum utilization. The reason for that is the network will be very likely congested before the link reaches its full utilization. When the maximum network utilization has been met, it is not for sure the case of link utilization.



Questions?

Email: x.che@herts.ac.uk

• Office: LB218

Tel: 01707 286206