


## Ip Configurations In Router Interface




The image shows a terminal window for a router configuration and a corresponding network diagram. The terminal window displays the following commands and output:

```
ROUTER
!
end
ROUTER(config)# ip add
ROUTER(config)#int e0/0
ROUTER(config-if)#ip add 50.0.0.1 255.0.0.0
ROUTER(config-if)#no sh
ROUTER(config-if)#
ROUTER(config-if)#do sh ip int br
Interface                IP-Address      OK? Method Status  Prot
-----                -
Ethernet0/0              50.0.0.1        YES manual up      up
Ethernet0/1              unassigned      YES TFTP  down    down
Ethernet0/2              unassigned      YES TFTP  down    down
Ethernet0/3              unassigned      YES TFTP  down    down

ROUTER(config-if)#do wr
Building configuration...
[OK]
ROUTER(config-if)#
```

The network diagram illustrates a connection between a router and a PC. The router is labeled "ROUTER" and has an interface "e0/0" with the IP address "50.0.0.1". The PC is labeled "Win" and has the IP address "50.0.0.10". The connection is labeled "SSH - TELNET".

## Ip Configurations In PC



The image shows a Windows PC configuration window and a command prompt. The "Internet Protocol Version 4 (TCP/IPv4) Properties" window is open, showing the "General" tab. The IP address is set to "50.0.0.10", the subnet mask is "255.0.0.0", and the default gateway is "50.0.0.1". The "Obtain an IP address automatically" option is selected. The "Administrator: Command Prompt" window is also open, showing the command "ping 50.0.0.1" and its output:

```
C:\Users\user>ping 50.0.0.1
Pinging 50.0.0.1 with 32 bytes of data:
Reply from 50.0.0.1: bytes=32 time<1ms TTL=255
Reply from 50.0.0.1: bytes=32 time<1ms TTL=255
Reply from 50.0.0.1: bytes=32 time<1ms TTL=255
Reply from 50.0.0.1: bytes=32 time<1ms TTL=255

Ping statistics for 50.0.0.1:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 0ms, Average = 0ms
C:\Users\user>
```

The network diagram on the right shows a connection between a PC and a router. The PC is labeled "Win" and has the IP address "50.0.0.10". The router is labeled "ROUTER" and has an interface "e0/0" with the IP address "50.0.0.1".

## Create Console Password

ROUTER

```
ROUTER(config-if)#exit
ROUTER(config)#~
^
% Invalid input detected at '^' marker.

ROUTER(config)#
ROUTER(config)#li
% Ambiguous command: "li "
ROUTER(config)#lin
ROUTER(config)#line c
ROUTER(config)#line console 0
ROUTER(config-line)#pass
ROUTER(config-line)#password testconsole
ROUTER(config-line)#login
ROUTER(config-line)#exit
ROUTER(config)#
ROUTER(config)#
ROUTER(config)#ena
ROUTER(config)#enable s
ROUTER(config)#enable secret enable
ROUTER(config)#
ROUTER(config)#
ROUTER(config)#
ROUTER(config)#
```



ET

ROUTER

```
ROUTER con0 is now available


Press RETURN to get started.

User Access Verification
Password:
ROUTER#
ROUTER#
ROUTER#conf t
Enter configuration commands, one per line. End with CNTL/Z.
ROUTER(config)#
ROUTER(config)#
ROUTER(config)#
ROUTER(config)#lin
```




ET

## Create Enable Secret Password




## Enable Telnet



NETWORK  
TECHNOLOGIES

## SSH - TELNET



SN SUREN NETWORK  
PLAY WITH TECHNOLOGIES

## SSH - TELNET

