






HO-EDGE#

HO-EDGE#conf t

Enter configuration commands, one per line. End with CNTL/Z.

HO-EDGE(config)#int e0/0

HO-EDGE(config-if)#ip add 10.0.0.1 255.0.0.0

HO-EDGE(config-if)#no sh

HO-EDGE(config-if)#exit

HO-EDGE(config)#

HO-EDGE(config)#

HO-EDGE(config)#int e0/1

HO-EDGE(config-if)#ip add 20.0.0.1 255.0.0.0

HO-EDGE(config-if)#no sh

HO-EDGE(config-if)#exit

HO-EDGE(config)#

HO-EDGE(config)#ip dhcp pool LAN

HO-EDGE(dhcp-config)#network 10.0.0.0 255.0.0.0

HO-EDGE(dhcp-config)#default-router 10.0.0.1

HO-EDGE(dhcp-config)#dns-server 8.8.8.8

HO-EDGE(dhcp-config)#exit

HO-EDGE(config)#

*Sep 12 08:41:53.421: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)

HO-EDGE(config)#

```
HO-EDGE(config)#ip route 0.0.0.0 0.0.0.0 20.0.0.2
HO-EDGE(config)#
HO-EDGE(config)#
HO-EDGE(config)#int e0/0
HO-EDGE(config-if)#ip nat inside
HO-EDGE(config-if)#ex
*Sep 12 08:48:23.551: %LINEPROTO-5-UPDOWN: Line protocol on Interface NVI0, chan
ged state to up
HO-EDGE(config-if)#exit
HO-EDGE(config)#
HO-EDGE(config)#int e0/1
HO-EDGE(config-if)#ip nat outside
HO-EDGE(config-if)#exit
HO-EDGE(config)#
HO-EDGE(config)#
HO-EDGE(config)#access-list 1 permit 10.0.0.0 0.255.255.255
HO-EDGE(config)#
HO-EDGE(config)#ip nat inside source list 1 int e0/1 overload
HO-EDGE(config)#
HO-EDGE(config)#
```



Google

[Advanced search](#)

Google offered in: [हिन्दी](#) [বাংলা](#) [తెలుగు](#) [मराठी](#) [தமிழ்](#) [ગુજરાતી](#) [ಕನ್ನಡ](#) [മലയാളം](#) [ਪੰਜਾਬੀ](#)

[Advertising](#)[Business Solutions](#)[About Google](#)[Google.co.in](#)

© 2026 - [Privacy](#) - [Terms](#)

```
--DC-EDGE#conf t
Enter configuration commands, one per line.  End with CNTL/Z.
DC-EDGE(config)#int e
*Sep 12 09:27:41.008: %PNP-6-PNP_DISCOVERY_STOPPED: PnP Discovery stopped (Config Wizard)
DC-EDGE(config)#int e0/0
DC-EDGE(config-if)#ip add 192.168.1.1 255.255.255.0
DC-EDGE(config-if)#no sh
DC-EDGE(config-if)#ex
DC-EDGE(config)#
DC-EDGE(config)#int e0/1
DC-EDGE(config-if)#ip add 30.0.0.2 255.0.0.0
DC-EDGE(config-if)#no sh
DC-EDGE(config-if)#ex
DC-EDGE(config)#
DC-EDGE(config)#ip route 0.0.0.0 0.0.0.0 30.0.0.1
DC-EDGE(config)#
DC-EDGE(config)#int e0/0
DC-EDGE(config-if)#ip nat inside
DC-EDGE(config-if)#ex
DC-EDGE(config)#i
*Sep 12 09:29:47.414: %LINEPROTO-5-UPDOWN: Line protocol on Interface NVI0, changed state to upn
DC-EDGE(config)#int e0/1
DC-EDGE(config-if)#ip nat outside
DC-EDGE(config-if)#ex
DC-EDGE(config)#
DC-EDGE(config)#ip nat inside source static 192.168.1.10 30.0.0.10
DC-EDGE(config)#ip nat inside source static 192.168.1.20 30.0.0.11
DC-EDGE(config)#
DC-EDGE(config)#
```

Welcome to Virtual PC Simulator, version 1.3 (0.8.1)

Dedicated to Daling.

Build time: May 7 2022 15:27:29

Copyright (c) 2007-2015, Paul Meng (mirnshi@gmail.com)

Copyright (c) 2021, Alain Degreffe (alain.degreffe@eve-ng.net)

All rights reserved.

VPCS is free software, distributed under the terms of the "BSD" licence.

Source code and license can be found at vpcs.sf.net.

For more information, please visit wiki.freecode.com.cn.

Modified version for EVE-NG.

Press '?' to get help.

Executing the startup file

VPC1> ip 192.168.1.10/24 192.168.1.1

Checking for duplicate address...

VPC1 : 192.168.1.10 255.255.255.0 gateway 192.168.1.1

VPC1> █

Welcome to Virtual PC Simulator, version 1.3 (0.8.1)
Dedicated to Daling.
Build time: May 7 2022 15:27:29
Copyright (c) 2007-2015, Paul Meng (mirnshi@gmail.com)
Copyright (c) 2021, Alain Degreffe (alain.degreffe@eve-ng.net)
All rights reserved.

VPCS is free software, distributed under the terms of the "BSD" licence.
Source code and license can be found at vpcs.sf.net.
For more information, please visit wiki.freecode.com.cn.
Modified version for EVE-NG.

Press '?' to get help.

Executing the startup file

VPC2> ip 192.168.1.20/24 192.168.1.1
Checking for duplicate address...
VPC2 : 192.168.1.20 255.255.255.0 gateway 192.168.1.1

VPC2> █

C:\WINDOWS\system32\cmd.exe

C:\Documents and Settings\user>

C:\Documents and Settings\user>ping 30.0.0.10

Pinging 30.0.0.10 with 32 bytes of data:

Reply from 30.0.0.10: bytes=32 time=5ms TTL=61

Reply from 30.0.0.10: bytes=32 time=3ms TTL=61

Reply from 30.0.0.10: bytes=32 time=2ms TTL=61

Reply from 30.0.0.10: bytes=32 time=5ms TTL=61

Ping statistics for 30.0.0.10:

Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),

Approximate round trip times in milli-seconds:

Minimum = 2ms, Maximum = 5ms, Average = 3ms

C:\Documents and Settings\user>ping 30.0.0.11

Pinging 30.0.0.11 with 32 bytes of data:

Reply from 30.0.0.11: bytes=32 time=5ms TTL=61

Reply from 30.0.0.11: bytes=32 time=4ms TTL=61

Reply from 30.0.0.11: bytes=32 time=5ms TTL=61

Reply from 30.0.0.11: bytes=32 time=4ms TTL=61

Ping statistics for 30.0.0.11:

Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),

Approximate round trip times in milli-seconds:

Minimum = 4ms, Maximum = 5ms, Average = 4ms

C:\Documents and Settings\user>