



Local Area Connection Properties

General Advanced

Internet Protocol (TCP/IP) Properties

General

You can get IP settings assigned automatically if your network supports this capability. Otherwise, you need to ask your network administrator for the appropriate IP settings.

☐ Obtain an IP address automatically

☒ Use the following IP address:

IP address: 50 . 0 . 0 . 10

Subnet mask: 255 . 0 . 0 . 0

Default gateway: 50 . 0 . 0 . 1

☐ Obtain DNS server address automatically

☒ Use the following DNS server addresses:



Preferred DNS server: . . .

Alternate DNS server: . . .

Advanced...


OK

Cancel



Connection Status

Connected
01:38:52
1.0 Gbps



Disable

Close

Details

Local Area Connection
LAN or High-Speed Internet



QEMU (Linux-1)



ENABLE=yes

NAME=Ethernet

IPADDRESS=172.16.0.10

CIDRLEN=16

NETWORK=172.16.0.0

NETMASK=255.255.0.0

GATEWAY=172.16.0.1

BROADCAST=172.16.255.255

DHCP=no

- /etc/sysconfig/network-scripts/ifcfg-eth0 1/9 11%



NAME=Ethernet

IPADDRESS=172.16.0.10

CIDRLEN=16

```
NETWORK=172.16.0.0
```

NETMASK=255.255.0.0

GATEWAY=172.16.0.1

BROADCAST=172.16.255.255

DHCP=no

—

25

2

—

—

—



4

1

1

1

www



QEMU (Linux-1)

172.16.0.10

172.16.0.20



```
# service network restart
Removing default gateway for Ethernet interface ..... [ OK ]
shutting down Ethernet interface eth0 ..... [ OK ]
shutting down loopback interface lo ..... [ OK ]
bringing up loopback interface lo ..... [ OK ]
bringing up Ethernet interface eth0 ..... [ OK ]
set up default gateway ..... [ OK ]
#
```



QEMU (Linux-1)



```
shutting down Ethernet interface eth0 ..... [ OK ]
shutting down loopback interface lo ..... [ OK ]
bringing up loopback interface lo ..... [ OK ]
bringing up Ethernet interface eth0 ..... [ OK ]
set up default gateway ..... [ OK ]
# ipconfig
-bash: ipconfig: command not found
127# ifconfig
eth0      Link encap:Ethernet  HWaddr 50:93:4C:01:AD:00
          inet addr:172.16.0.10  Bcast:172.16.255.255  Mask:255.255.0.0
          UP BROADCAST RUNNING MULTICAST  MTU:1500  Metric:1
          RX packets:247 errors:0 dropped:0 overruns:0 frame:0
          TX packets:820 errors:0 dropped:0 overruns:0 carrier:0
          collisions:0 txqueuelen:1000
          RX bytes:30152 (29.4 KiB)  TX bytes:253254 (247.3 KiB)

lo        Link encap:Local Loopback
          inet addr:127.0.0.1  Mask:255.0.0.0
          UP LOOPBACK RUNNING  MTU:16436  Metric:1
          RX packets:0 errors:0 dropped:0 overruns:0 frame:0
          TX packets:0 errors:0 dropped:0 overruns:0 carrier:0
          collisions:0 txqueuelen:0
          RX bytes:0 (0.0 B)  TX bytes:0 (0.0 B)
```



Server Manager ▸ Dashboard



Manage

Tools

View

Help

Dashboard

Local Server

All Servers

File and Storage

IIS

Network Connections

< > << All Control Panel Items > Network Connections

Search Network Connections


Organize ▾

Disable this network device

Disconnect this connection

Rename this connection

>>

Ethernet
Network 3
Intel(R) PRO/1000 MT Net

Ethernet Status

Ethernet Properties

Networking

Co

Th

Co

Co

Co

Co

Co

Co

Co

Co

Co

Co

Co

Internet Protocol Version 4 (TCP/IPv4) Properties

General

You can get IP settings assigned automatically if your network supports this capability. Otherwise, you need to ask your network administrator for the appropriate IP settings.

☐ Obtain an IP address automatically☒ Use the following IP address:

IP address:

172 . 16 . 0 . 20

Subnet mask:

255 . 255 . 0 . 0

Default gateway:

172 . 16 . 0 . 1

☐ Obtain DNS server address automatically☒ Use the following DNS server addresses:

Preferred DNS server:

. . .

Alternate DNS server:

. . .

☐ Validate settings upon exit

Advanced...

OK

Cancel

1 item 1 item selected

Hide

Server Manager ▸ Dashboard

Manage Tools View Help

Add Roles and Features Wizard

Select server roles

DESTINATION SERVER
server2016

Before You Begin

Installation Type

Server Selection

Server Roles

Features

Confirmation

Results

Select one or more roles to install on the selected server.

Roles

- ☐ Active Directory Federation Services
- ☐ Active Directory Lightweight Directory Services
- ☐ Active Directory Rights Management Services
- ☐ Device Health Attestation
- ☐ DHCP Server
- ☐ DNS Server
- ☐ Fax Server
- ☒ File and Storage Services (1 of 12 installed)
- ☐ Host Guardian Service
- ☐ Hyper-V
- ☐ MultiPoint Services
- ☐ Network Policy and Access Services
- ☐ Print and Document Services
- ☐ Remote Access
- ☐ Remote Desktop Services
- ☐ Volume Activation Services
- ☒ Web Server (IIS) (8 of 43 installed)
- ☐ Windows Deployment Services
- ☐ Windows Server Essentials Experience
- ☐ Windows Server Update Services

Description

Active Directory Certificate Services (AD CS) is used to create certification authorities and related role services that allow you to issue and manage certificates used in a variety of applications.

Hide

< Previous

Next >

Install

Cancel

BPA results

Performance

BPA results



wwwroot

File Home Share View

← → ↕ ↑ > This PC > Local Disk (C:) > inetpub > wwwroot

Search wwwroot

	Name	Date modified	Type	Size
★ Quick access				
Desktop	iisstart	8/29/2026 12:39 PM	Chrome HTML Do...	1 KB
Downloads	iisstart	8/29/2026 12:39 PM	PNG image	98 KB
Documents				
Pictures				
This PC				
Network				

2 items

C:\Documents and Settings\user>ping 172.16.0.10

Pinging 172.16.0.10 with 32 bytes of data:

Reply from 172.16.0.10: bytes=32 time=3ms TTL=63

Reply from 172.16.0.10: bytes=32 time=1ms TTL=63

Reply from 172.16.0.10: bytes=32 time=2ms TTL=63

Reply from 172.16.0.10: bytes=32 time=1ms TTL=63

Ping statistics for 172.16.0.10:

Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),

Approximate round trip times in milli-seconds:

Minimum = 1ms, Maximum = 3ms, Average = 1ms

C:\Documents and Settings\user>ping 8.8.8.8

Pinging 8.8.8.8 with 32 bytes of data:

Reply from 8.8.8.8: bytes=32 time=147ms TTL=127

Reply from 8.8.8.8: bytes=32 time=220ms TTL=127

Reply from 8.8.8.8: bytes=32 time=297ms TTL=127

Reply from 8.8.8.8: bytes=32 time=373ms TTL=127

Ping statistics for 8.8.8.8:

Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),

Approximate round trip times in milli-seconds:

Minimum = 147ms, Maximum = 373ms, Average = 259ms

C:\Documents and Settings\user>ping 172.16.0.20

Pinging 172.16.0.20 with 32 bytes of data:

Reply from 172.16.0.20: bytes=32 time=1ms TTL=127

Reply from 172.16.0.20: bytes=32 time=1ms TTL=127

Reply from 172.16.0.20: bytes=32 time=1ms TTL=127

Reply from 172.16.0.20: bytes=32 time=1ms TTL=127

Ping statistics for 172.16.0.20:

Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),

Approximate round trip times in milli-seconds:

Hello World! This file is located in /home/thttpd

QEMU (Win)

File Edit View History Bookmarks Tools Help

http://172.16.0.10/ IIS Windows Server

172.16.0.20 Search

Windows Server

Internet Information Services

Welcome Bienvenue Tervetuloa

ようこそ Benvenuto 歡迎

Bem-vindo


Bienvenido Hoş geldiniz ברוכים הבאים


Vítejte Καλώς ορίσαστε Välkommen 환영합니다 Добро пожаловать Üdvözlünk

Willkommen Velkommen

Witamy

Microsoft





Server Manager ▸ Dashboard

Manage Tools View Help

Dashboard

Local Server

All Servers

DNS

File and Storage

Network Connections

<< All Control Panel Items > Network Connections

Search Network Connections

Organize ▾

Disable this network device... Diagnose this connection... Rename this connection... >>

Ethernet
Network 3
Intel(R) PRO/1000 MT Net

Ethernet Properties

Networking

Internet Protocol Version 4 (TCP/IPv4) Properties

General

You can get IP settings assigned automatically if your network supports this capability. Otherwise, you need to ask your network administrator for the appropriate IP settings.

☐ Obtain an IP address automatically☒ Use the following IP address:

IP address:

8 . 8 . 8 . 8

Subnet mask:

255 . 0 . 0 . 0

Default gateway:

8 . 0 . 0 . 1

☐ Obtain DNS server address automatically☒ Use the following DNS server addresses:

Preferred DNS server:

. . .

Alternate DNS server:

. . .

☐ Validate settings upon exit

Advanced...

OK

Cancel

1 item 1 item selected

BPA results



Dashboard

WELCOME TO SERVER MANAGER

Add Roles and Features Wizard

Select server roles

DESTINATION SERVER
server2016

Before You Begin

Installation Type

Server Selection

Server Roles

Features

Confirmation

Results

Select one or more roles to install on the selected server.

Roles

- ☐ Active Directory Certificate Services
- ☐ Active Directory Domain Services
- ☐ Active Directory Federation Services
- ☐ Active Directory Lightweight Directory Services
- ☐ Active Directory Rights Management Services
- ☐ Device Health Attestation
- ☐ DHCP Server
- ☒ DNS Server (Installed)
- ☐ Fax Server
- ☒ File and Storage Services (1 of 12 installed)
- ☐ Host Guardian Service
- ☐ Hyper-V
- ☐ MultiPoint Services
- ☐ Network Policy and Access Services
- ☐ Print and Document Services
- ☐ Remote Access
- ☐ Remote Desktop Services
- ☐ Volume Activation Services
- ☐ Web Server (IIS)
- ☐ Windows Deployment Services

Description

Active Directory Certificate Services (AD CS) is used to create certification authorities and related role services that allow you to issue and manage certificates used in a variety of applications.

Hide

< Previous

Next >

Install

Cancel




Server Manager



DNS Manager

File Action View Help



- DNS
 - SERVER2016
 - Forward Lookup Zones
 - com
 - hotstar
 - Reverse Lookup Zones
 - Trust Points
 - Conditional Forwarders

Name	Type	Data	Timestamp
www	Host (A)	172.16.0.10	

Hide

Events

Services

Performance

BPA results

Events

Performance

BPA results


QEMU (DNS)



Server Manager

DNS Manager

File Action View Help



DNS

SERVER2016

Forward Lookup Zones

com

in

netflix

Reverse Lookup Zones

Trust Points

Conditional Forwarders

Name

www

Type

Host (A)

Data

172.16.0.20

Timestamp

Hide



My Documents

My Computer

My Network Places


Recycle Bin

Internet Explorer

Cisco ASDM

Old Java

PUT



QEMU (Win)



File Edit View History Bookmarks Tools Help

http://www.hotstar.com/

IIS Windows Server

www.hotstar.com

Search

Hello World! This file is located in /home/thttpd

Windows Server

Internet Information Services

Welcome

Bienvenue


Tervetuloa

ようこそ

Benvenuto

歓迎

Bem-vindo



Bienvenido

Hoş geldiniz

ברוכים הבאים

Welkom

Vítejte

Καλώς
ορίσαστε

Välkommen

환영합니다

Добро
пожаловать

Üdvözöljük

Microsoft

Willkommen

Velkommen



مرحبا

欢迎

Witamy