

# <u>Mohammad Saeed Pourmazar</u>



https://github.com/MohammadSaeedPourmazar



https://gitlab.com/MohammadSaeedPourmazar



https://medium.com/@MohammadSaeedPourmazar



https://dev.to/MohammadSaeedPourmazar



https://www.youtube.com/@MohammadSaeedPourmazar



https://www.instagram.com/MohammadSaeedPourmazar



https://www.facebook.com/MohammadSaeedPourmazar



https://www.linkedin.com/in/MohammadSaeedPourmazar/



https://orcid.org/0009-0008-9383-419X

# Uninstall Prometheus From Ubuntu

## 1. Stop Prometheus Service:

If Prometheus is running as a service, stop it first.

#### sudo systemctl stop prometheus

If Prometheus was started using a different method (e.g., via a binary or Docker), stop it accordingly.

# 2. Disable Prometheus Service (Optional):

If you no longer want Prometheus to start automatically on boot, disable it.

sudo systemctl disable prometheus

# 3. Remove Prometheus Package:

If you installed Prometheus using a package manager (e.g., apt or yum), you can uninstall it by running:

sudo apt-get remove --purge prometheus

If you installed Prometheus from source, skip this step and proceed to the next.

### 4. Delete Prometheus Data:

Prometheus stores its data (metrics, time series) by default in /var/lib/prometheus. To delete all Prometheus data, you can simply remove this directory:

sudo rm -rf /var/lib/prometheus

This will delete all stored data from Prometheus.

## 5. Remove Configuration Files (Optional):

If you want to remove all Prometheus configuration files as well, you can delete the Prometheus configuration directory. It's usually located in /etc/prometheus:

#### sudo rm -rf /etc/prometheus

You may also want to remove any logs, which might be in /var/log/prometheus or other log directories depending on your setup.

sudo rm -rf/var/log/prometheus

# 6. Remove System User (Optional):

If Prometheus was installed under a specific user, and you want to remove that user, run:

#### sudo userdel prometheus

This step is optional if you want to clean up the system user created for Prometheus.

### 7. Check for Leftover Files:

You can also search for any leftover Prometheus files on your system:

sudo find / -name "\*prometheus\*" -exec rm -rf {} \;

This will completely uninstall Prometheus and delete its data from your system.