



A-1) Boot into ColdWalletOS and wait for it to tell you to insert HotWalletOS if it's not already

```
[ 1.366300] ata1.00: ATA-7: QEMU HARDDISK, 2.5+, max UDMA/100
[ 1.366562] ata1.00: 1796096 sectors, multi 16: LBA48 NCQ (depth 32)
[ 1.366793] ata1.00: applying bridge limits
[ 1.367208] ata2: SATA link down (SStatus 0 SControl 300)
[ 1.367534] ata1.00: configured for UDMA/100
[ 1.368001] scsi 0:0:0:0: Direct-access   ATA       QEMU HARDDISK   2.5+ PQ: 0 ANSI: 5
[ 1.368258] ata6: SATA link down (SStatus 0 SControl 300)
[ 1.382198] sd 0:0:0:0: [sda] 1796096 512-byte logical blocks: (920 MB/877 MiB)
[ 1.383606] sd 0:0:0:0: [sda] Write Protect is off
[ 1.383870] sd 0:0:0:0: [sda] Write cache: enabled, read cache: enabled, doesn't support DPO or FUA
[ 1.384145] sd 0:0:0:0: [sda] Preferred minimum L/O size 512 bytes
[ 1.385012] sda: sda1 sda2 sda3
[ 1.385664] sd 0:0:0:0: [sda] Attached SCSI disk
Begin: Loading essential drivers ... done.
Begin: Running /scripts/init-premount ... [ 1.563552] usb 1-2: New USB device found, idVendor=0627, idProduct=0001, bcdDevice= 0.00
[ 1.564721] usb 1-2: New USB device strings: Mfr=1, Product=3, SerialNumber=10
[ 1.564943] usb 1-2: Product: QEMU USB Tablet
[ 1.565178] usb 1-2: Manufacturer: QEMU
[ 1.565393] usb 1-2: SerialNumber: 28754-0000:00:02:1:00.0-2
[ 1.572178] hid: raw HID events driver (C) Jiri Kosina
[ 1.580297] usbcore: registered new interface driver usbhid
[ 1.580763] usbhid: USB HID core driver
[ 1.582354] input: QEMU QEMU USB Tablet as /devices/pci0000:00/0000:00:02:1/0000:02:00.0/usb1/1-2/1-2:1.0/0003:0627:0001.0001/input/input4
=====
[ 1.582656] hid-generic 0003:0627:0001.0001: input,hidraw0: USB HID v0.01 Mouse [QEMU QEMU USB Tablet] on usb-0000:02:00.0-2/input0
INSERT HotWalletOS
=====
[ 1.689784] usb 2-5: new SuperSpeed USB device number 2 using xhci_hcd
[ 1.713248] usb 2-5: New USB device found, idVendor=0781, idProduct=55b1, bcdDevice= 1.10
[ 1.713503] usb 2-5: New USB device strings: Mfr=1, Product=2, SerialNumber=3
[ 1.713739] usb 2-5: Product: SanDisk 3.2 Gen1
[ 1.713970] usb 2-5: Manufacturer: SanDisk
[ 1.714196] usb 2-5: SerialNumber: A200366342093036
[ 1.718394] usb-storage 2-5:1.0: USB Mass Storage device detected
[ 1.719788] scsi host6: usb-storage 2-5:1.0
[ 1.720165] usbcore: registered new interface driver usb-storage
[ 1.721727] usbcore: registered new interface driver uas
[ 1.863900] input: InExPS/2 Generic Explorer Mouse as /devices/platform/i8042/serio1/input/input3
[ 2.735682] scsi 6:0:0:0: Direct-access   SanDisk   SanDisk 3.2 Gen1 DL17 PQ: 0 ANSI: 6
[ 2.738732] sd 6:0:0:0: [sdb] 977829888 512-byte logical blocks: (501 GB/466 GiB)
[ 2.740163] sd 6:0:0:0: [sdb] Write Protect is off
[ 2.741657] sd 6:0:0:0: [sdb] Write cache: disabled, read cache: enabled, doesn't support DPO or FUA
[ 2.746063] sd 6:0:0:0: [sdb] Attached SCSI removable disk
=====
INSERT HotWalletOS
=====
```


A-2) Select 'Create Vault'



A-3) Create a STRONG password to be used throughout MonerOS




A-4) Confirm said password




A-5) Go into 'Manage Wallets'




A-6) Select 'Create Wallet'




A-7) Enter the current date (This tells your wallet how far to go back when syncing)




A-8) Your full wallet address will be shown, along with a notice to write down your recovery seed




A-9) Write this recovery seed down and save it in a VERY safe place. This seed will allow you to regain access to your wallet in the event of catastrophic data loss, either from this operating system or virtually any monero wallet software.




A-10) Select 'Manage Wallets' again




A-11) Select 'Delete Wallet' (We're going to restore it)




A-12) If you have multiple wallets, make sure you select the right one




A-13) Confirm deletion




A-14) Select 'Manage Wallets' again




A-15) Select 'Restore Wallet' (so we can confirm the restore seed was copied down correctly)



A-16) Enter words 1-24




A-17) Enter restore date



A screenshot of a terminal window showing a dialog box titled "Set Restore Date". The dialog box has a black background with white text. It prompts the user to "Enter restore date (YYYY-MM-DD):" followed by a dashed line for input. Below the input line are two buttons: "Ok" and "Cancel".

```
Set Restore Date  
Enter restore date (YYYY-MM-DD):  
-----  
Ok Cancel
```


A-18) If everything was copied down and entered correctly, you will see a success message



A screenshot of a terminal window showing a success message titled "Monero Wallet Restored". The message states "Your Monero wallet has been restored." and displays a long alphanumeric address. At the bottom, there is a button labeled "<Ok>".

```
Monero Wallet Restored  
Your Monero wallet has been restored.  
Address:  
4AFJ1ZT6GpjAK16j9ybQvJfmN266EppoJXppjGecv2XUKXiKyXEgk2PKvuU9aQ2ZtFesoGQrjtme  
cYKyZ7ZFHjZ8B7F8M4z  
<Ok>
```


A-19) You can now safely shutdown the system and remove ColdWalletOS disk




B-1) Ensure ColdWalletOS is not plugged in, boot HotWalletOS and enter your password




B-2) You will be asked on every boot whether you want to use a remote node or self-sync. If you do not have HotWalletOS installed on a disk with at least 250GB, it will not allow you to self-sync. Also, if the disk is not an SSD, do not select self-sync. Flash drives and HDD disks do not have the speed required to keep up with blockchain syncing.



B-3) If choosing a remote node, you will need to enter an address (without http:// or https://). Visiting <https://monero.fail> is the best place to look for nodes. You can search for clearnet or onion nodes and view other information about them..




B-4) You will be required to enter your password 2 more times as the system finishes setting up. While inconvenient, this is necessary for security purposes



Enter Master Password

Ok

B-5) If everything was successful you will see this screen, along with your wallet(s) and balance(s)



HotWalletOS

BALANCE UPDATED EVERY 10-20 MINUTES

CURRENT NET BALANCE

\$0.00

ASSET	ADDRESS	BALANCE	VALUE
Monero (XMR)	4AFJ...8M4z	0.0000000	\$0.00

REMOTE VIEWING LINK

SHUTDOWN SYSTEM

C-1) With the system booted, you can access it from any TOR Browser if desired. This option is the most convenient. To get your Tor Address, click on 'Remote Viewing Link'

HotWalletOS

BALANCE UPDATED EVERY 10-20 MINUTES

CURRENT NET BALANCE


\$0.00

ASSET	ADDRESS	BALANCE	VALUE
Monero (XMR)	4AFJ...8M4z	0.0000000	\$0.00

REMOTE VIEWING LINK

SHUTDOWN SYSTEM

C-2) You can copy down the onion address, or if using a mobile device (covered in section F), you can simply scan the QR Code.



C-3) To get your full Monero Address, simply click on the desired wallet from the main screen

HotWalletOS

BALANCE UPDATED EVERY 10-20 MINUTES

CURRENT NET BALANCE

\$0.00

ASSET	ADDRESS	BALANCE	VALUE
Monero (XMR)	4AFJ...8M4z	0.0000000	\$0.00

REMOTE VIEWING LINK

SHUTDOWN SYSTEM

C-4) Double click on the 'Transfer From Address' to copy it. Now you can use that to receive funds to your wallet.

HotWalletOS

MONERO TRANSFER

TRANSFER FROM ADDRESS (READ-ONLY)

4AFJ1ZT6GpjAK16j9ybQvJfmN266EppojXppjGecv2XUKXiKyXEgk2PKv

TRANSFER TO ADDRESS

UNLOCKED XMR BALANCE (READ-ONLY)

0.000000000000

TRANSFER AMOUNT IN XMR (OR SWEEP_ALL)

DEVELOPMENT CONTRIBUTION

0.40% (Recommended)

WALLET PASSWORD

CREATE UNSIGNED TRANSACTION

CANCEL AND GO BACK

C-

C-5) When funds first come in, you will see the locked symbol next to the address. Monero transactions take about 20 minutes to unlock

HotWalletOS

BALANCE UPDATED EVERY 10-20 MINUTES

CURRENT NET BALANCE

\$1.88

ASSET	ADDRESS	BALANCE	VALUE
Monero (XMR)	4AFJ...8M4z	 0.0060000	\$1.88

REMOTE VIEWING LINK

SHUTDOWN SYSTEM

C-6) When you click on the address you will see your unlocked balance. In this case it's 0, but if you had a previously unlocked balance, that balance would still be unlocked. Only the pending transaction is locked.

HotWalletOS

MONERO TRANSFER

TRANSFER FROM ADDRESS (READ-ONLY)

4AFJ1ZT6GpjAK16j9ybQvJfmN266EppojXppjGecv2XUKX1KyXEgk2PKvi

TRANSFER TO ADDRESS

UNLOCKED XMR BALANCE (READ-ONLY)

0.000000000000

TRANSFER AMOUNT IN XMR (OR SWEEP_ALL)

DEVELOPMENT CONTRIBUTION

0.40% (Recommended)

WALLET PASSWORD

CREATE UNSIGNED TRANSACTION

CANCEL AND GO BACK

C-7) Once the transaction is unlocked, the padlock icon will go away

HotWalletOS

BALANCE UPDATED EVERY 10-20 MINUTES

CURRENT NET BALANCE

\$1.89

ASSET	ADDRESS	BALANCE	VALUE
Monero (XMR)	4AFJ...8M4z	0.0060000	\$1.89

REMOTE VIEWING LINK

SHUTDOWN SYSTEM

C-8) You can also see this when clicking on the wallet

HotWalletOS

MONERO TRANSFER

TRANSFER FROM ADDRESS (READ-ONLY)

4AFJ1ZT6GpjAK16j9ybQvJfmN266EppojXppjGecv2XUKXiKyXEgk2PKvi

TRANSFER TO ADDRESS

UNLOCKED XMR BALANCE (READ-ONLY)

0.006000000000

TRANSFER AMOUNT IN XMR (OR SWEEP_ALL)

DEVELOPMENT CONTRIBUTION

0.40% (Recommended)

WALLET PASSWORD

CREATE UNSIGNED TRANSACTION

CANCEL AND GO BACK

C-9a) You can enter an amount to transfer...

HotWalletOS

MONERO TRANSFER

TRANSFER FROM ADDRESS (READ-ONLY)

4AFJ1ZT6GpjAK16j9ybQvJfmN266EppojXppjGecv2XUKXiKyXEgk2PKvi

TRANSFER TO ADDRESS

UNLOCKED XMR BALANCE (READ-ONLY)

0.006000000000

TRANSFER AMOUNT IN XMR (OR SWEEP_ALL)

0.0051

DEVELOPMENT CONTRIBUTION

0.40% (Recommended)

WALLET PASSWORD

CREATE UNSIGNED TRANSACTION

CANCEL AND GO BACK

C-9b) Or you can enter the command 'sweep_all' to transfer the entire wallet balance to another address (fees automatically calculated)

HotWalletOS

MONERO TRANSFER

TRANSFER FROM ADDRESS (READ-ONLY)

4AFJ1ZT6GpjAK16j9ybQvJfmN266EppojXppjGecv2XUKXiKyXEgk2PKvi

TRANSFER TO ADDRESS

UNLOCKED XMR BALANCE (READ-ONLY)

0.006000000000

TRANSFER AMOUNT IN XMR (OR SWEEP_ALL)

sweep_all

DEVELOPMENT CONTRIBUTION


0.40% (Recommended)

WALLET PASSWORD


CREATE UNSIGNED TRANSACTION

CANCEL AND GO BACK

C-10) Once you properly fill out all the boxes and click 'Create Unsigned Transaction', you should receive a success message



C-11) Cold wallets can only process one transaction at a time. If you try to create another one before the previous is signed and submitted, it will ask you if you want to overwrite the previous one.



C-12) Return to the dashboard and lick ‘Shutdown System’ So that you can sign the transaction with ColdWalletOS

HotWalletOS

BALANCE UPDATED EVERY 10-20 MINUTES

CURRENT NET BALANCE



\$1.90

ASSET	ADDRESS	BALANCE	VALUE
Monero (XMR)	4AFJ...8M4z	0.0060000	\$1.90

REMOTE VIEWING LINK

SHUTDOWN SYSTEM


C-13) Confirm shutdown




D-1) Insert and boot from ColdWalletOS, then enter your password




D-2) Select 'Manage Wallets'




D-3) Select 'Sign Transactions'



D-4) Return to menu after signing is complete




D-5) Shutdown so we can submit the transaction with HotWalletOS




E-1) Remove ColdWalletOS, boot HotWalletOS and enter password



E-2) Select node option again



E-3) Enter password 2 more times as they come up



Enter Master Password

=====

Ok

E-4) Your transaction will be automatically submitted. Some or all of your balance will remain locked for about 20 minutes

HotWalletOS

BALANCE UPDATED EVERY 10-20 MINUTES

CURRENT NET BALANCE

\$0.27

ASSET	ADDRESS	BALANCE	VALUE
Monero (XMR)	4AFJ...8M4z	 0.0008372	\$0.27

REMOTE VIEWING LINK

SHUTDOWN SYSTEM

E-5) After transactions are unlocked, the padlock will be removed

HotWalletOS

BALANCE UPDATED EVERY 10-20 MINUTES

CURRENT NET BALANCE


\$0.26

ASSET	ADDRESS	BALANCE	VALUE
Monero (XMR)	4AFJ...8M4z	0.0008372	\$0.26


REMOTE VIEWING LINK

SHUTDOWN SYSTEM

F-1) Open Tor Browser on mobile and connect.



F-2) Click on the address bar and then the QR Code icon at the far right



F-3) The QR Code scanner will pop up



F-4) Just like earlier, click 'Remote Viewing Link' on the running system

HotWalletOS

BALANCE UPDATED EVERY 10-20 MINUTES

CURRENT NET BALANCE


\$0.00

ASSET	ADDRESS	BALANCE	VALUE
Monero (XMR)	4AFJ...8M4z	0.0000000	\$0.00


REMOTE VIEWING LINK

SHUTDOWN SYSTEM

F-5) Scan the QR Code with the mobile app



F-6) Confirm you want the app to open tis link



F-7) You can now use Tor Browser to interact with HotWalletOS, just like you can on the system itself.

