

MonerOS

Update Manual

Updating HotWalletOS & ColdWalletOS Systems with UpdateOS

Contents

Overview.....	3
Part 1: Download and extract MonerOS	3
Part 2: Flash UpdateOS	3
Part 4: Update HotWalletOS & ColdWalletOS	4

Overview

UpdateOS is used to update the actual system partitions on HotWalletOS and ColdWalletOS disks. Updates are done frequently and this allows your systems to stay up to date without replacing your vaults, wallets, system settings, etc. Simply download the newest UpdateOS.img file, write it to a disk, and boot into it. You can then plug in HotWalletOS and ColdWalletOS disks and select "Update Systems". That's it! It will overwrite the current system partitions with the newest versions. UpdateOS is based on ColdWalletOS so it too is air-gapped.

Part 1: Download and extract MonerOS

1. Download the newest MonerOS.zip file
2. Extract the files using your operating system's built-in tools:
 - Windows: Right-click the .zip file, select Extract All..., choose your destination folder, and click Extract.
 - macOS: Double-click the .zip file (or right-click and select Open). macOS will automatically extract the contents into the same folder.
 - Linux: Right-click the .zip file, select Extract Here (or Extract To... to choose a specific destination).

Part 2: Flash UpdateOS

Flash UpdateOS.img using balenaEtcher or your preferred flashing tool


Important: Flashing erases all existing data on the target drive. Back up anything you need before you continue, and double-check that you select the correct drive.

1. Open balenaEtcher and select **Flash from file**, then choose the UpdateOS.img file.
2. Select **Select target** and choose your target drive.
3. Select **Flash!** and wait for balenaEtcher to finish writing and validating the drive.

Part 4: Update HotWalletOS & ColdWalletOS

Complete these steps to update the system partitions

1. Boot into UpdateOS
2. Plug in HotWalletOS & ColdWalletOS system disks
3. Select Update Systems (Can be done separately if you only have one available USB Port)



4. Wait for system updates to complete

MonerOS Update Utility
Updating HotWalletOS...



MonerOS Update Utility
Updating ColdWalletOS...



Update Complete
Successfully updated HotWalletOS & ColdWalletOS.

<Ok>

5. Shutdown when complete and you're all up to date!

MonerOS Update Utility

Main Menu

Update Systems
Safe Shutdown
Terminal

Select