

Merchant Resource Center

User Manual

v1.0.0 (Canada)



About this documentation

Documentation Date: October 24, 2017

Created by: Moneris Product Documentation

[®]MONERIS and MONERIS BE PAYMENT READY & Design are registered trade-mark of Moneris Solutions Corporation. All other marks or registered trade-marks are the property of their respective owners.

© 2017 Moneris Solutions Corporation, 3300 Bloor Street West, Toronto, Ontario, M8X 2X2. All Rights Reserved. This manual shall not wholly or in part, in any form or by any means, electronic, mechanical, including photocopying, be reproduced or transmitted without the authorized consent of Moneris Solutions Corporation ("Moneris").

This guide is for informational purposes only. Neither Moneris nor any of its affiliates shall be liable for any direct, indirect, incidental, consequential or punitive damages arising out of use of any of the information contained in this guide. Neither Moneris or any of its affiliates nor any of our or their respective licensors, licensees, service providers or suppliers warrant or make any representation regarding the use or the results of the use of the information, content and materials contained in this guide in terms of their correctness, accuracy, reliability or otherwise.

Your Gift card processing is governed by your Moneris Gift Program Agreement with Moneris. Your Loyalty card processing is governed by your Moneris Loyalty Program Agreement with Moneris. Your credit and/or debit card processing is governed by the terms and conditions of the Moneris Merchant Agreement (the "Merchant Agreement") with Moneris. It is your responsibility to ensure that proper card processing procedures are followed at all times. Please refer to your Merchant manuals and the Merchant Agreement for details. The Moneris Merchant Operating Manual is available at moneris.com/support.

Contents

1	INTRO	DUCTION	1
	1.1	Introduction	1
	1.2	Before you get started	1
		1.2.1 Store administrator user: before you get started	2
		1.2.2 Non-administrator user: before you get started	2
	1.3	Activating your Merchant Resource Center store	3
	1.4	Ready to use the Merchant Resource Center?	4
2	MERCH	IANT RESOURCE CENTER BASICS	5
	2.1	Logging into the Merchant Resource Center	5
		2.1.1 The Merchant Resource Center main page	6
		2.1.2 The menu bar	7
		2.1.3 Available store features	8
	2.2	Accessing context-sensitive help	8
	2.3	Using the search fields	8
	2.4	Logging out of the Merchant Resource Center	9
	2.5	Need to reset your login password?	9
	2.6	Configuring your security questions and answers	10
	2.7	Switching between Canadian/U.S. Merchant Resource Center	11
	2.8	General guidelines for performing transactions	12
3	POS HA	ARDWARE	13
	3.1	Moneris iPP320 PINpad	13
	3.2	Setting up the iPP320 PINpad	15
		3.2.1 Configuring the iPP320 PINpad	18
		3.2.2 Initializing the iPP320 PINpad for the first time	19
	3.3	Card entry options	20
		3.3.1 Insert (chip cards)	20
		3.3.2 Swipe (magnetic stripe cards)	20

		3.3.3	Wave/tap: contactless cards	21
		3.3.4	Manual card entry	22
4	VIRTUA	L TERMIN	AL	23
	4.1	Purchas	se with debit/credit card	24
		4.1.1	Purchase with debit/credit card: iPP320 PINpad	25
		4.1.2	Purchase with debit/credit card: iPP320 (manual card entry)	26
		4.1.3	Purchase with debit/credit card: unencrypted MSR	28
		4.1.4	Purchase with debit/credit card: Vault profile	29
		4.1.5	Purchase with debit/credit card: keyed entry	30
	4.2	Purchas	se with cash	31
	4.3	Group I	Purchase with debit/credit card	32
	4.4	Preauth	norization with debit/credit card	33
		4.4.1	Preauthorization with debit/credit card: iPP320 PINpad	34
		4.4.2	Preauthorization with debit/credit card: iPP320 PINpad (mar card entry)	nual 35
		4.4.3	Preauthorization with debit/credit card: unencrypted MSR	37
		4.4.4	Preauthorization with debit/credit card: Vault profile	38
		4.4.5	Preauthorization with debit/credit card: keyed entry	40
	4.5	Reauth	orization with debit/credit card	42
	4.6	Capturi	ing a debit/credit Preauthorization	43
	4.7	Capturi	ing a debit/credit Reauthorization	45
	4.8 Voice Authorization-Advice with debit/credit card		uthorization-Advice with debit/credit card	47
		4.8.1	Voice Authorization-Advice with debit/credit card: unencryp MSR	ted 48
		4.8.2	Voice Authorization-Advice with debit/credit card: keyed ent	ry 49
	4.9	Void wi	ith debit/credit card	50
	4.10	Refund	with debit/credit card	51
	4.11	Refund	with cash	53
	4.12	Indepe	ndent Refund with debit/credit card	54
		4.12.1	Independent Refund with debit/credit card: iPP320 PINpad	55
		4.12.2	Independent Refund with debit/credit card: iPP320 PINpad (manual card entry)	56
		4.12.3	Independent Refund with debit/credit card: unencrypted MS	R 57

		4.12.4 4.12.5	Independent Refund with debit/credit card: Vault profile Independent Refund with debit/credit card: keyed entry	58 59
	4.13	Card Ve 4.13.1 4.13.2	erification with debit/credit card Card Verification with debit/credit card: unencrypted MSR Card Verification with debit/credit card: keyed entry	60 61 62
	4.14	Chip Ini	itialization	63
	4.15	•	al procedures: debit/credit cards	64
		4.15.1 4.15.2	Adding order details to a transaction When a purchasing (corporate) card is detected	64 65
		4.15.3	Adding level 2/3 details: capturing a debit/credit Preauthorization	66
		4.15.4	Adding level 2/3 details: capturing a debit/credit Reauthorization	70
		4.15.5	Adding level 2/3 details: Refund	74
		4.15.6	Cardholder prompts: iPP320 PINpad	78
		4.15.7	Cardholder prompts: iPP320 PINpad (manual card entry)	81
5	PRINTIN	IG/E-MAII	LING A RECEIPT	83
6	ORDER	HISTORY.		84
	6.1	Areas o	n the "Order History" page	84
		6.1.1	Transaction type details: "Order History" page	85
		6.1.2	Tip information details: "Order History" page	86
		6.1.3	eFraud details: "Order History" page	86
		6.1.4	Action items: "Order History" page	87
	6.2	Accessi	ng a transaction's "Order History" page	88
7	MONER	IS GIFT/LO	DYALTY CARD PROGRAMS	89
	7.1	Purchas	se with gift card	91
		7.1.1	Purchase with gift card: unencrypted MSR	92
		7.1.2	Purchase with gift card: keyed entry	93
	7.2	Void wi	th gift card	94
	7.3	Refund	with gift card	95
	7.4	Indeper	ndent Refund with gift card	96
		7.4.1	Independent Refund with gift card: unencrypted MSR	97
		7.4.2	Independent Refund with gift card: keyed entry	98

7.5	Loyalty F	Purchase: awarding loyalty points	99
	7.5.1	Loyalty Purchase: awarding loyalty points for associated debit/credit Purchase	100
	7.5.2	Loyalty Purchase: awarding loyalty points for associated debit/credit Purchase (gift/loyalty card Activation)	101
	7.5.3	Loyalty Purchase: awarding loyalty points for associated debit/credit Voice Authorization-Advice	102
	7.5.4	Loyalty Purchase: awarding loyalty points for associated cash Purchase	h 103
	7.5.5	Loyalty Purchase: awarding loyalty points for associated gift Purchase	104
	7.5.6	Loyalty Preauthorization: allocating points for associated debit/credit Preauthorization	105
	7.5.7	Loyalty Capture: awarding loyalty points for associated debit/credit Capture	106
7.6	Manual	Redemption (dollars) with loyalty card	107
	7.6.1	Manual Redemption (dollars) with loyalty card: unencrypted MSR	l 108
	7.6.2	Manual Redemption (dollars) with loyalty card: keyed entry	109
7.7	Manual	Redemption (points) with loyalty card	110
	7.7.1	Manual Redemption (points) with loyalty card: unencrypted MSR	111
	7.7.2	Manual Redemption (points) with loyalty card: keyed entry	112
7.8	Loyalty \	/oid	113
	7.8.1	Loyalty Void: removing loyalty points for associated debit/cr Void	edit 114
	7.8.2	Loyalty Void: reversing an associated gift card Purchase	114
	7.8.3	Loyalty Void: reversing a loyalty Redemption	115
7.9	Loyalty F	Refund	116
	7.9.1	Loyalty Refund: removing loyalty points for associated debit/credit Refund	117
	7.9.2	Loyalty Refund: removing loyalty points for associated cash Refund	117
	7.9.3	Loyalty Refund: removing loyalty points for associated gift Refund	118
	7.9.4	Loyalty Refund: reversing a loyalty Redemption	118
7.10	Redeem	ing coupon/voucher with gift/loyalty card	119
	7.10.1	Redeeming coupon/voucher with gift/loyalty card: MSR	120
	7.10.2	Redeeming coupon/voucher with gift/loyalty card: keyed en	try 121
7.11	Activatir	ng and loading a gift/loyalty card	122

		7.11.1 7.11.2	Activating and loading a gift/loyalty card: MSR Activating and loading a gift/loyalty card: keyed entry	123 124
	7.12	Deactiva	ating a gift/loyalty card	125
		7.12.1	Deactivating a gift/loyalty card: MSR	126
		7.12.2	Deactivating a gift/loyalty card: keyed entry	127
	7.13	Balance	Inquiry for gift/loyalty card: initiating from menu bar	128
		7.13.1	Balance Inquiry for gift/loyalty card: MSR	129
		7.13.2	Balance Inquiry for gift/loyalty card: keyed entry	130
	7.14	Balance	Inquiry for gift card: initiating during gift Purchase	131
	7.15	Balance	Inquiry for loyalty card: initiating during loyalty Redemption	132
	7.16	Optiona	l procedures: gift/loyalty cards	133
		7.16.1	Activating a gift/loyalty card - payment with debit/credit car iPP320 PINpad	rd: 133
		7.16.2	Activating a gift/loyalty card - payment with debit/credit car MSR	rd: 134
		7.16.3	Activating a gift/loyalty card - payment with debit/credit carkeyed entry	rd: 135
		7.16.4	Activating a gift/loyalty card - payment with cash	136
		7.16.5	Balance due for gift dollars transaction	137
		7.16.6	Balance due for loyalty dollars transaction	138
		7.16.7	Balance due for loyalty points Redemption	139
8	RECURR	ING BILLIN	IG	. 140
	8.1	Register	ing a recurring transaction: keyed entry	141
	8.2	Managir	ng a recurring transaction	143
	8.3	Recurrin	g transactions report	145
9	VAULT	••••••		. 147
	9.1	Register	ing a Vault profile	148
		9.1.1	Registering a Vault profile: unencrypted MSR	149
		9.1.2	Registering a Vault profile: keyed entry	150
	9.2	Managir	ng a Vault profile	151
	9.3	Vault re	port	160
	9.4	Hosted \	/ault configuration	162

10	REPORT	S		163
	10.1	Transac	tions report: debit/credit cards and cash	164
	10.2	Transac	tions report: grouped transactions	166
	10.3	Transac	tions report: gift/loyalty cards	167
	10.4	Transac	tions report: cash	168
	10.5	Manage	ed account updater report	169
	10.6	Batches	report: all card transactions	171
	10.7	Exporti	ng a report (transaction list) to a file	173
11	END-OF	-DAY PRO	CEDURE	174
12	MANAG	ING YOUI	R OWN USER PROFILE	175
	12.1	Modifyi	ng your user profile's login information	176
		12.1.1	Modifying your login password	176
		12.1.2	Modifying your security questions/answers	177
		12.1.3	Modifying your registered e-mail address	177
	12.2	Modifyi	ng your user profile's default transaction settings	178
		12.2.1	Setting your Merchant Resource Center default page	178
		12.2.2	Setting your default card entry method	179
		12.2.3	Setting your default electronic commerce indicator	180
		12.2.4	Setting your default display language	180
		12.2.5	Setting your default PINpad com port number	181
		12.2.6	Setting the default headers/fields to include a report's transaction list	182
		12.2.7	Setting the headers/fields to include in an exported report	184
	12.3	Viewing	your login history	185
13	ADMIN:	MANAGI	NG STORE SETTINGS/OTHER USER PROFILES	186
	13.1	Adding	a new user profile	188
	13.2	Modifyi	ng a user profile	189
		13.2.1	Modifying a user profile's first name/last name data	189
		13.2.2	Modifying a user profile's password	190
		13.2.3	Modifying a user profile's user permissions	191
		13.2.4	Modifying a user profile's admin access level	192

13.3	Deactivating a user profile		
13.4	Notifica	tion settings	194
	13.4.1	Adding an e-mail address to the notification list	194
	13.4.2	Removing an e-mail address from the notification list	194
13.5	Store se	ttings	195
	13.5.1	Automated logout setting	195
	13.5.2	Batch close time setting	195
	13.5.3	Cash payments setting	196
	13.5.4	PCI mode setting	196
	13.5.5	Receipt details setting	197
	13.5.6	Tip setting: iPP320 PINpad	197
	13.5.7	API token: viewing/regenerating the token	198
	13.5.8	Asynchronous transaction response setting	199
	13.5.9	Multi-store login status	199
	13.5.10	Managed account updater setting	200
13.6	Masterc	ard MasterPass configuration	201
13.7	Visa Checkout configuration		
13.8	Apple Pay in-app configuration		206
13.9	Android	Pay in-app configuration	208
13.10	Multi-st	ore login configuration	209
	13.10.1	Linking a child store to the master store	210
	13.10.2	Unlinking a child store from the master store	211
	13.10.3	<i>3</i>	ugh
		multi-store login	211
13.11	Audit lo	gs	212
	13.11.1	Access violations log: viewing	212
	13.11.2	Admin changes log	213
	13.11.3	User changes log	213
	13.11.4	Login history	214
13.12	IP access		
	13.12.1	Restricting store access to specific IP address(es)	215
	13.12.2	Blocking an IP address when IP restrictions enforced	216
13.13		egration options	217
		DirectPost configuration	218
		Hosted Paypage configuration	219
	13.13.3	Hosted tokenization	220

14	APPEND	PIX	221
	14.1	Payment/transaction fields	221
	14.2	Electronic commerce indicator (ECI)	223
	14.3	Permissions	224
		14.3.1 Admin access level	224
		14.3.2 User permissions	226
	14.4	Managed account updater service	231
	14.5	Level 2/3 reporting	232
		14.5.1 Level 2/3 details fields	233
	14.6	Address verification service (AVS)	235
	14.7	Card Validation Digits (CVD)	235
	14.8	Using the Merchant Resource Center store in a test environment 14.8.1 Test card numbers	236 237
	149	Assistance and resources	238

1 Introduction

1.1 Introduction

Powered by the Moneris Gateway, the Moneris Merchant Resource Center™ is a Webbased point-of-sale (POS) solution that enables you to process financial transactions securely in real time and/or a batch environment. Through the Merchant Resource Center you can also monitor transactions, pull reports, and reconcile batches.

1.2 Before you get started

Before you can process financial transactions on the Merchant Resource Center, there are several steps that you need to follow, particularly if you intend to function as a store administrator (see below).

Administrator users versus non-administrator users

Administrators have special responsibilities and access to functions that should be available to regular users. For example, as an administrator, you would normally perform duties such as adding and deleting user profiles and configuring optional settings that affect all users logging into your Merchant Resource Center store.

- If you intend to use the Merchant Resource Center as an administrator, see Store administrator user: before you get started (page 2).
- If you intend to use the Merchant Resource Center as a non-administrator user, see Non-administrator user: before you get started (page 2).

1.2.1 Store administrator user: before you get started

- 1. Ensure that your hardware meets or exceeds the following requirements:
 - Internet-accessible computer.
 - Web browser: Internet Explorer 8 or higher with cookies enabled.
 - Internet connection (high speed recommended).
 - If you are connecting an iPP320 PINpad and/or magnetic stripe reader:
 - On the computer to which you will connect the iPP320 PINpad and process transactions, you will need full admin permissions for your user account and the Java platform installed and enabled (free download available from java.com).
- 2. If you are activating a Merchant Resource Center store, ensure that you have your Moneris Merchant ID and Store ID (refer to your Moneris Welcome e-mail for these IDs).
- 3. Do one of the following:
 - If you have all the required elements, go to step 4.
 - If you do not have the required elements, please at **1-866-319-7450** or e-mail onlinepayments@moneris.com.
- 4. Determine your setup requirements:
 - If your store is not yet activated, proceed to Activating your Merchant Resource Center store (page 3).
 - If your store is already activated, proceed to *Ready to use the Merchant Resource Center?* (page 4).

1.2.2 Non-administrator user: before you get started

- 1. Obtain your login credentials (store ID and password) from your store administrator.
- 2. Proceed to Ready to use the Merchant Resource Center? (page 4).

1.3 Activating your Merchant Resource Center store

Follow the steps below to activate your Merchant Resource Center store.

Note: If your store is already activated, go to step 11.

- 1. Visit moneris.com/activate.
- 2. In the Moneris Merchant ID and Moneris Store ID fields, enter your Merchant ID and Store ID (refer to your Moneris Welcome e-mail for these IDs).
- 3. Click on the **Next** button.
- 4. In the **First Name** and **Last Name** fields, enter your first name and last name.
- 5. In the **Username** and **Password/Password Confirm** fields, enter the username and password under which you want to log into your store.

Note: The password must adhere to these restrictions (password fields are case sensitive): include 7-16 characters; start with a letter; and contain a number.

You must change your password periodically. If your password expires, you will be prompted to create a new password.

- 6. Click on the **Next** button.
- 7. From each of the three **Question/Answer** # drop-down lists, select a question and enter an answer in the corresponding field.

Note: Periodically you will be prompted to answer one of the questions when logging in.

8. In the **Email Address** field, enter your e-mail address.

Note: Should you ever need to have your password reset, a temporary password will be sent to this address.

- 9. Click on the **Complete Activation** button.
- 10. When a "Congratulations!" page displays, it means your Merchant Resource Center store is activated.

Important! Passwords should be kept confidential and not shared with any one. Change your password immediately if you have any reason to believe that someone else has access to it or has tried to log into your account (see page 176).

11. Proceed to Ready to use the Merchant Resource Center? (page 4).

1.4 Ready to use the Merchant Resource Center?

- 1. Do any of the following depending on your requirements:
 - If you need to set up a new iPP320 PINpad, proceed to page 15.
 - If you do not need to set up any POS hardware (e.g., iPP320 PINpad), go to step 2.
- 2. Learn more about some of the Merchant Resource Center features by reading through the sections listed below:

Note: Some of the features referenced in this manual will not necessarily be visible or accessible on your own Merchant Resource Center store. The features that are visible/accessible to you during your login session are dependent on the setup of your merchant account, the permissions for which your store administrator has configured your user profile, and the store settings as configured by your administrator.

- To log in/log out from the Merchant Resource Center and learn about some of the basic features, see page 5.
- To perform financial transactions with debit/credit cards and cash, see page 23.
- To perform financial transactions with gift/loyalty cards, including activating/deactivating cards, see page 89.
- To set up/manage recurring transactions, see page 140.
- To set up/manage Vault profiles, see page 147.
- To generate financial transaction reports, see page 163.
- To configure the settings/preferences for your own user profile, see page 174.
- To use the Merchant Resource Center in a test environment, see page 236.
- 3. If you are acting as the store administrator, configure the appropriate store settings as desired (see page 186).


Important! As a security precaution, you should configure the auto-logout setting so that any user is automatically logged out after a specified period of inactivity (see page 195).

2 Merchant Resource Center basics

2.1 Logging into the Merchant Resource Center

Follow the steps below to log in/start a new session on the Merchant Resource Center.

- 1. Visit https://www3.moneris.com/mpg/.
- 2. Wait for the "Merchant Resource Center" login page (shown below) to display:



3. In the "Logon" area, enter your credentials in the fields (**Username**, **Store ID**, and **Password**).

Note: You must have a valid user ID (username) and password to access the Merchant Resource Center.

Important! Passwords should be kept confidential and not shared with any one. Change your password immediately if you have any reason to believe that someone else has access to it or has tried to log into your account (see page 176).

4. Click on the **Submit** button.

Note: You must change your password periodically. If your password expires, you will be prompted to create a new password.

- If prompted to select/answer three security questions, see page 10.
- If prompted to change your password, enter the new password, and click on the **Submit** button.


Note: The password (password fields are case sensitive) must include 7-16 characters; start with a letter; contain a number; and cannot be the same as the previous 4 passwords.

- If prompted to answer a security question, answer it, and click on the **Submit** button (or **Change Password** button).
- 5. When the "Merchant Resource Center" main page displays (see page 6), you have successfully logged in.

2.1.1 The Merchant Resource Center main page

When you log in for the first time, the Merchant Resource Center main page (shown below) will display.

Note: The main page will always display unless you change your default page (see page 178).



2.1.2 The menu bar

Once you are logged into the Merchant Resource Center, you will see the menu bar (shown here) displayed near the top of the screen.



2

• The menu bar lists the features for which your store has been enabled (for a list of menu bar-accessible features, see page 8).

Using the menu bar

To access the functions/transactions associated with a menu-accessible feature, do the following:

- 1. Click on the feature that you want to use (e.g., to use the virtual terminal feature, click on **Terminal** on the menu bar).
- 2. Once the associated sub-menu bar displays (shown here), click on the function/transaction that you want to access (e.g., to do a debit/credit Purchase, click on **Purchase**).



3. When the "Purchase" page is displayed, you may perform the transaction.

2.1.3 Available store features

The table below lists the Merchant Resource Center features that accessible from the menu bar (see page 7).

Note: Only the features for which your Merchant Resource Center store has been enabled will be accessible and/or visible.

Feature	Description
Admin	Administrative functions (see page 186).
Reports	Transaction and batch reports (see page 163).
Terminal	Virtual terminal (see page 23).
Recurring	Recurring billing (see page 140).
Gift/Loyalty	Moneris Gift/Loyalty (see page 89).
Vault	Vault (see page 147).
Help	Context-sensitive online help (see page 8).
Firstname_Lastname	Managing your own user profile (see page 175).

2.2 Accessing context-sensitive help

Context-sensitive onscreen help may be accessed from any Merchant Resource Center page.

1. To access the help, click on **Help** on the menu bar.

2.3 Using the search fields

When entering data in a Merchant Resource Center search field, please note:

Search fields are not case sensitive.

Note: Password fields are case sensitive.

You may enter just a portion of a name (e.g., if you enter "mon" or "eris" or "Neri," the system retrieves "Moneris" in all instances).

2.4 Logging out of the Merchant Resource Center

Follow the steps below to end your session and log out of the Merchant Resource Center.

- 1. On the menu bar, click on Firstname Lastname > Logout.
- 2. When the Merchant Resource Center login page displays (see page 5), it means you have successfully logged out.

2.5 Need to reset your login password?

- 1. Start on the Merchant Resource Center login page (visit https://www3.moneris.com/mpg/).
- 2. Click on the Forgot Password? button.
- 3. On the "Password Reset" page, enter your credentials in the **Username** and **Store** ID fields.
- 4. Click on the **Submit** button.
- 5. Answer the security question (enter the answer in the field), and click on the **Submit** button.

Note: If you cannot remember the answer to your security question, contact your store administrator and request that they reset your password. If you are the store administrator and you cannot remember your security question, contact onlinepayments@moneris.com).

- 6. Click on the Close Window button.
- 7. Wait for the temporary password to be e-mailed to you.
- 8. Log into the Merchant Resource Center (enter your username and the temporary password that was e-mailed to you).

Note: You will be prompted to change the temporary password.

2.6 Configuring your security questions and answers

The questions and answers that you configure will be used to identify you in the event that you forget your password. (Periodically you may be prompted to answer a question when logging in.)

1. Select a question from each of the three **Security Question** # drop-down lists, and enter an answer in the corresponding **Security Answer** field.

Note: Each question and answer must be between 6 and 90 characters long, and each question and answer must be different from the other questions/answers.

2. In the Email Address field, enter your e-mail address.

Note: In the event that you need to have your login password reset, a temporary password will be sent to this address.

- 3. Click on the Save Reset Password Data button.
- 4. When the "Merchant Resource Center" main page displays (see page 6), you have successfully logged in.

2.7 Switching between Canadian/U.S. Merchant Resource Center

Follow the steps below to switch between the Canadian Merchant Resource Center and U.S. Merchant Resource Center.

2

Note: You may switch between the Merchant Resource Centers regardless of whether you are logged into one or both (to access a Merchant Resource Center store, you must always login using the credentials for your store).

To switch to the "Canada English" login page:

- 1. On the menu bar, click on the Canada English icon.
- 2. Wait for the "Merchant Resource Center" page to display.
- 3. Confirm that the ^{□ EN ▽} icon is displayed on the menu bar.

To switch to the Canada French login page:

- 1. On the menu bar, click on the Canada French icon.
- 2. Wait for the "Centre de ressources aux commerçants" page to display.
- 3. Confirm that the \square icon is displayed on the menu bar.

To switch to the U.S. English login page:

- 1. On the menu bar, click on the **USA Website** icon.
- 2. Wait for the "Merchant Resource Center" page to display.
- 3. Confirm that the Susa icon is displayed on the menu bar...

2.8 General guidelines for performing transactions

A financial transaction involves the transfer of funds between a cardholder's account and your own business account.

- Select the transaction to be processed (e.g., Terminal > Purchase or Terminal > Refund).
- 2. Select a payment method/card entry method.
- 3. Capture the card data (e.g., manually enter the data in Merchant Resource Center fields, or use an iPP320 PINpad or other supported POS device to capture the data).
 - If an iPP320 PINpad is connected, ensure that the cardholder follows any prompts that are displayed.
- 4. Wait for the Merchant Resource Center to display an "APPROVED" or "DECLINED" response.
- 5. Print/e-mail a transaction receipt.

3 POS hardware

3.1 Moneris iPP320 PINpad

The Moneris iPP320 PINpad can be used to process card-present transactions from your Merchant Resource Center store.

• To set up an iPP320 PINpad to work with your Merchant Resource Center store, see *Setting up the iPP320 PINpad* (page 15).



For names and descriptions of the labelled areas on the iPP320 PINpad, see page 14.

To see the labelled areas on the iPP320 PINpad, see page 13.

Label	Description
	Function keys (F1, F2, F3, and F4)
	 Select the option displayed above the key.
2	Alpha-Numeric keys
	Cancel key (red)
3	 Clear message displayed on the iPP320 PINpad.
	Cancel transaction.
	Correct key (yellow)
4	 Clear data entered on the iPP320 PINpad.
	OK / Enter key (green)
	 Submit data, or acknowledge a message on the iPP320 PINpad.
6	Chip Reader (slot at the bottom of the iPP320 PINpad)
•	■ See page 20.
	Contactless Reader Indicator (green flashing light)
7	 Four lights flash: The reader is capturing card data (see page 21).
	No lights flash: The reader is idle.
Q	Display Screen/Contactless Reader
	"WELCOME/BONJOUR" screen displays when the iPP320 PINpad is idle.
	Magnetic Stripe Reader (slot along the side of iPP320 PINpad)
9	■ See page 20.

3.2 Setting up the iPP320 PINpad

- 1. Please confirm that you received the following from Moneris:
 - iPP320 PINpad (see page 13).
 - PINpad cable: 1 x USB cable and/or 1 x serial cable and power cable.
- 2. Do one of the following:
 - If any of the above required elements are missing, contact us at 1-866-319-7450 or e-mail onlinepayments@moneris.com.
 - If you have all the required elements, go to step 3.
- 3. Do one of the following:
 - If your Merchant Resource Center store is activated and you have your store's login credentials, go to step 4.
 - If your store is not yet activated, proceed to *Before you get started* (page 1).
- 4. On the computer to which you will connect the iPP320 PINpad, ensure that you have:
 - Full admin permissions for your user account.
 - Internet connection (high speed recommended).
 - Java platform installed and enabled (free download available from java.com).
- 5. Do one of the following depending on how you intend to connect the iPP320 PINpad to your computer:
 - If you want to use a USB cable to connect the iPP320 to your computer, proceed to *Using a USB cable* (page 16).
 - If you want to use a serial cable to connect the iPP320 to your computer, proceed to *Using a serial cable* (page 17).


Using a USB cable

Download and install the iPP320 USB driver

- a. Visit https://github.com/moneris/.
- b. When the "Moneris" page displays, locate the IPP320-PINpad-USB-driver link, and click on it.
- c. When the "Moneris/IPP320-PINpad-USB-driver" page displays, locate the **TeliumUSBJungoDriverforWindows-v280.zip** listing, and then save the zip file to your computer.
- d. Unzip the **TeliumUSBJungoDriverforWindows-v280.zip** file, and click on the bundled executable (.exe) file to begin the installation process.
- e. When the installation dialog boxes display, continue clicking the **Next** button as prompted, and then click on the **Install** button.
- f. Once the driver is installed, proceed to step 2 (Connect the USB cable to the iPP320 PINpad and your computer) below.

2. Connect the USB cable to the iPP320 PINpad and your computer

- Plug the USB cable into the empty port on the underside of the iPP320 PINpad.
- b. Fold the latch down and press to secure the cable connection to the iPP320 PINpad.
- c. Plug the USB cable connector into a USB port on your computer.
- d. Wait while the iPP320 PINpad powers on.
- e. When the "INIT REQUIRED" screen displays on the iPP320 PINpad, proceed to *Configuring the iPP320 PINpad* (page 18).






•


Using a serial cable

1. Connect the serial cable to the iPP320 PINpad and your computer


- a. Plug the serial cable into the empty port on the underside of the iPP320 PINpad.
- b. Fold the latch down and press to secure the cable connection.




c. Plug the power cable connector into the port at the back of the serial cable connector.



d. Plug the serial cable connector into a serial port on your computer.



- e. Plug the power cable into a working power outlet.
- f. Wait while the iPP320 PINpad powers on.



g. When the "INIT REQUIRED" screen displays on the iPP320 PINpad, proceed to *Configuring the iPP320 PINpad* (page 18).



3.2.1 Configuring the iPP320 PINpad

1. Access the iPP320 PINpad's "MENU" screen

- a. Ensure that the "INIT REQUIRED" screen is displayed.
- b. Quickly press the function keys in the following sequence: **F2**, **F1**, **F3**, and **F4**.
- c. Do one of the following:
 - If the "MENU" screen (shown here) is displayed, proceed to step 2 (Configure the iPP320 PINpad's optional settings) below.
 - If the "INIT REQUIRED" screen is displayed, repeat steps 1a-b of this procedure.






2. Configure the iPP320 PINpad's optional settings

- a. When the "MENU" screen displays, press **F2** to scroll to **CONFIGURATION**.
- b. Press the green key to continue.
- c. When the "CONFIGURATION" screen displays, press **F4** (YES).
- d. Press the green key to continue.
- e. When the "LANGUAGE/LANGUE" menu displays, select a language type:
 - For English, press F1 (ENGL).
 - For French, press F4 (FRAN).
- g. When the "CABLE TYPE" menu displays, select a cable type:
 - If you are using a USB cable, simply press the green key to select USB.
 - If you are using a serial cable, press F2 to scroll to RS232, and then press the green key to select it.









h.	When the "QR-CODE" screen displays, press F4 (OFF).	QR-CODE ON OFF
i.	When the "BEEP" screen displays, press F1 (ON).	ON OFF
j.	When the "PED SERIAL NUMBER 61012345" screen displays, press the key to continue.	PED SERIAL NUMBER 61012345
k.	Wait while the IPP320 PINpad reboots.	PINPAD WILL REBOOT IN FEW SECONDS, PLEASE WAIT
1.	When the "INIT REQUIRED" screen displays, proceed to <i>Initializing the iPP320 PINpad for the first time</i> below.	INIT REQUIRED

3.2.2 Initializing the iPP320 PINpad for the first time

1. Identify the com port that the iPP320 PINpad is using while it is connected to your computer (this com port will be named "SAGEM TELIUM").

Note: If you are unsure about how to identify the com ports used by peripheral devices connected to your computer, refer to the documentation for your computer's operating system.

2. Identify the "SAGEM TELIUM" com port number.

Note: If you are unsure about how to identify com port numbers on your computer, refer to the documentation for your computer's operating system.

- 3. If you are not already logged into the Merchant Resource Center, log in now (see page 5).
- 4. Configure your Merchant Resource Center com port setting (see page 181).
- 5. Initialize the iPP320 PINpad (see page 63).
 - If you want to enable tip prompting on the iPP320, see page 197.

3.3 Card entry options

3.3.1 Insert (chip cards)

- 1. Wait for the iPP320 PINpad to display "SWIPE OR INSERT CARD" or "SWIPE, TAP OR INSERT CARD".
- 2. The cardholder inserts their card into the iPP320 PINpad's chip reader.

Note: Unless the iPP320 PINpad prompts otherwise, the card should not be swiped even if it has a magnetic stripe.



- 3. The cardholder may be prompted to enter data, including a PIN.
- 4. The cardholder leaves the chip card inserted until "REMOVE CARD" displays on the iPP320 PINpad.

Tip for proper card insertion:

Hold the iPP320 PINpad with one hand, and insert the card in the chip reader with the other hand (this will prevent the iPP320 PINpad's contactless reader from inadvertently reading the card data as a contactless transaction.

3.3.2 Swipe (magnetic stripe cards)

Note: If the card has a chip, it must be inserted (see above).

- 1. Wait for the iPP320 PINpad to display "SWIPE OR INSERT CARD" or "SWIPE. TAP OR INSERT CARD".
- 2. You or the cardholder swipes their card on the iPP320 PINpad's magnetic stripe reader.

Note: If the card is a credit card, you should swipe the




If the card is a debit card, the cardholder will be prompted to enter a PIN.

Tip for proper card swipe:

Hold the iPP320 PINpad with one hand, and swipe the card in the magnetic stripe reader with the other hand (this will prevent the iPP320 PINpad's internal contactless reader from inadvertently reading the card data).

3.3.3 Wave/tap: contactless cards

- Wait for the iPP320 PINpad to display "SWIPE, TAP OR INSERT CARD".
- 2. The cardholder taps/waves their card over the iPP320 PINpad's display screen:
 - Only Purchases and Refunds can be performed as contactless transactions.
 - The cardholder will not be prompted for a PIN.
 - The transaction amount must be equal to or less than the card's maximum Contactless Dollar Value (see below).



* In this manual, the term "contactless card" refers to a contactless-enabled card (supported brands include Visa®, Mastercard®, American Express®, Discover®, and Interac®) or other items such as a key fob, mobile tag, or mobile device (e.g., a smartphone, tablet, or smartwatch; the cardholder is responsible for any related software on their mobile device including downloading any required apps and loading their card information into their digital wallet).

Maximum Contactless Dollar Value (CDV)

To determine the maximum CDV for a card type, contact Moneris.

- Credit cards: If a credit card is tapped for an amount that exceeds its maximum CDV, the iPP320 PINpad will display "TAP FAILED PLEASE RETRY".
- Debit cards: If a debit card is tapped for an amount that exceeds its maximum CDV, the iPP320 PINpad will display "MUST INSERT CARD".

Tips for proper card tap/wave:

- The card must be within 0.5 in. (1.3 cm) of the iPP320 PINpad's display screen, but it does not have to touch it.
- The card must be tapped or waved by itself. It should not be waved while in a wallet with other cards.



3.3.4 Manual card entry

You may manually enter the card number for credit cards and some chip debit cards.

- 1. Initiate the debit/credit transaction (e.g., Terminal > Purchase).
- 2. As the payment method, select **Debit/credit Pinpad**.
- 3. Checkmark the **Enable manual card input** box.
- 4. For detailed instructions, see page 26 (Purchase), 35 (Preauthorization), and page 56 (Independent Refund).

4 Virtual terminal

Using the virtual terminal feature, you may perform debit/credit transactions such as Purchases, Preauthorizations, and Refunds (for full listing of available transactions, refer to the table below).

Transaction type	card type /tender	See procedure on:
Purchase ¹	debit/credit	page 24
Purchase	cash	page 31
Group Purchase	debit²/credit	page 32
Preauthorization ³	debit²/credit	page 33
Capture (Preauthorization) ⁴	debit²/credit	page 43
Voice Authorization	debit²/credit	page 47
Void	debit/credit	page 50
Refund	debit/credit	page 51
Independent Refund	debit/credit	page 54
Card Verification	debit²/credit	page 60
Chip Initialization ⁵	debit/credit	page 63

¹ To set up a recurring Purchase, see page 140.

² Applies only to some chip debit cards.

³ For Reauthorization, see page 42.

⁴ For Reauthorization Capture, see page 45.

 $^{^{\}scriptscriptstyle 5}$ Initializes the iPP320 PINpad (This is not a financial transaction.)

4.1 Purchase with debit/credit card

Debit/credit card sale of goods and services.

• For a listing of supported card entry methods, including the associated procedures describing how to use them to perform this transaction, refer to the table below:

Card entry method	See procedure on:
iPP320 PINpad	page 25
iPP320 PINpad (manual)	page 26
unencrypted MSR	page 28
Vault profile	page 29
keyed entry	page 30

4.1.1 Purchase with debit/credit card: iPP320 PINpad

Follow the steps below to perform a debit/credit Purchase by capturing debit/credit card data (insert, tap, or swipe) with an iPP320 PINpad.

- 1. On the menu bar, click on Terminal > Purchase.
- 2. Wait for the "Purchase" page to display.
- 3. In the "Payment Method" area, select **Debit/Credit Pinpad** from the drop-down list.
- 4. In the "Payment Details" area, do the following:

Note: For information about fields referred to in the steps below, see page 221.

- a. Ensure that the **Enable manual card input** box is unmarked.
- b. In the Order ID field, optionally enter an Order ID.
- c. In the **Customer ID** field, optionally enter a Customer ID.
- d. In the **Amount** field, enter the Purchase amount (#.##).
- 5. Click on the **Process Transaction** button.
- 6. When "Establishing communication with pinpad" displays on the "Purchase" page, wait.
- 7. When "Please follow prompts on pinpad" displays on the "Purchase" page, see page 78.
- 8. When the "APPROVED or "DECLINED" response displays on the "Purchase" page, the transaction is complete:
 - If Moneris Loyalty is enabled and you want to award loyalty points, see page 100.
 - If Moneris Loyalty is not enabled or it is but you want to bypass awarding points, print/e-mail the transaction receipt now (see page 83).

4.1.2 Purchase with debit/credit card: iPP320 (manual card entry)

Follow the steps below to perform a credit Purchase by manually entering (keying) credit card data on an iPP320 PINpad.

Note: Some chip debit cards may be used for this transaction.

- 1. On the menu bar, click on Terminal > Purchase.
- 2. Wait for the "Purchase" page to display.
- 3. In the "Payment Method" area, select **Debit/Credit Pinpad** from the drop-down list.
- 4. In the "Payment Details" area, do the following:

Note: For information about fields referred to in the steps below, see page 221.

- a. Checkmark the **Enable manual card input** box.
- b. In the Order ID field, optionally enter an Order ID.
- c. In the **Customer ID** field, optionally enter a Customer ID.
- d. In the **Amount** field, enter the Purchase amount (#.##).
- 5. Click on the **Process Transaction** button.
- 6. When "Establishing communication with pinpad" displays on the "Purchase" page, wait.
- 7. When "Please follow prompts on pinpad" displays on the "Purchase" page, do the following:
 - a. When "SWIPE, TAP OR INSERT CARD" (or "SWIPE OR INSERT CARD") displays on the iPP320 PINpad, key in the card account number, and press the green key.
 - b. When "EXPIRY DATE MMYY" displays on the iPP320 PINpad, key in the card expiry date (MMYY), and press the green key.
 - If "PURCHASE \$#.##-OK?" displays on the iPP320 PINpad, see page 81.
 - c. When "PLEASE WAIT" displays on the iPP320 PINpad, wait.
 - d. When "APPROVED THANK YOU OBTAIN CARD" displays on the iPP320 PINpad, press the green key (return the card to the cardholder).
- 8. When the "APPROVED or "DECLINED" response displays on the "Purchase" page, the transaction is complete:

4

- If Moneris Loyalty is enabled and you want to award loyalty points, see page 100.
- If Moneris Loyalty is not enabled or it is but you want to bypass awarding points, print/e-mail the transaction receipt now (see page 83).

4.1.3 Purchase with debit/credit card: unencrypted MSR

Follow the steps below to perform a credit Purchase by using an unencrypted magnetic stripe reader to capture the credit card data.

Note: Some chip debit cards may be used for this transaction.

- 1. On the menu bar, click on Terminal > Purchase.
- 2. Wait for the "Purchase" page to display.
- 3. In the "Payment Method" area, select Credit Card MSR from the drop-down list.
- 4. In the "Payment Details" area, do the following:

- a. In the **Order ID** field, optionally enter an Order ID.
- b. In the Customer ID field, optionally enter a Customer ID.
- c. In the **Statement Descriptor** field, enter a descriptor for the card statement.
 - If the Customer Code field displays, optionally enter a customer code.
 - If the Invoice Number field displays, optionally enter an invoice number.
- d. In the **Amount** field, enter the Purchase amount (#.##).
- e. In the Card Verification Digits field, enter the card verification digits.
 - If the "Address Verification" area displays, enter the billing address data in the Street Number, Street Name (use also to enter PO box data), and Zip/Postal Code fields (for a post office box, checkmark PO Box).
 - To add order details (shipping/billing and product details), see page 64.
- 5. Click on the **Swipe Card** button.
- 6. When "Please swipe credit card now" displays on the "Purchase" page, swipe the card on the unencrypted magnetic stripe reader.
 - If the Proceed with Level 2/3 button and the Proceed with Purchase button display on the "Purchase" page, see page 65.
- 7. When the "APPROVED" or "DECLINED" response displays on the "Purchase" page, the transaction is complete:
 - If Moneris Loyalty is enabled and you want to award loyalty points, see page 100.
 - If Moneris Loyalty is not enabled or it is but you want to bypass awarding points, print/e-mail the transaction receipt now (see page 83).

4.1.4 Purchase with debit/credit card: Vault profile

Follow the steps below to perform a credit Purchase by sourcing credit card data from a Vault profile.

Note: Some chip debit cards may be used for this transaction.

- 1. On the menu bar, click on Terminal > Purchase.
- 2. Wait for the "Purchase" page to display.
- 3. In the "Payment Method" area, select **Vault Profile Keyed Entry** from the drop-down list.
- 4. In the "Payment Details" area, do the following:
 - a. In the **Data Key** field, enter the data key of the Vault profile from which you want to source the card data.
 - b. Click on the Verify Data Key button.
 - c. Confirm that the **Credit Card Number** and **Expiry Date** fields are populated with the correct card data.
 - d. In the Card Verification Digits field, enter the card verification digits.
 - If the "Address Verification" area displays, confirm that the Street
 Number, Street Name, and Zip/Postal Code fields are populated with the correct billing address data.
- 5. In the "Payment Details" area, fill in the remaining fields:

- a. In the Order ID field, optionally enter an Order ID.
- b. In the **Customer ID** field, optionally enter a Customer ID.
- c. In the **Statement Descriptor** field, enter a descriptor for the card statement.
- d. In the Amount field, enter the Purchase amount (#.##).
- e. From the "ECI Indicator" drop-down list, select an e-commerce descriptor.
 - To add order details (shipping/billing and product details), see page 64.
- 6. Click on the **Process Transaction** button.
- 7. When the "APPROVED" or "DECLINED" response displays on the "Purchase" page, the transaction is complete:
 - If Moneris Loyalty is enabled and you want to award loyalty points, see page 100.
 - If Moneris Loyalty is not enabled or it is but you want to bypass awarding points, print/e-mail the transaction receipt now (see page 83).

4.1.5 Purchase with debit/credit card: keyed entry

Follow the steps below to perform a credit Purchase by manually entering (keying) credit card data on an iPP320 PINpad.

Note: Some chip debit cards may be used for this transaction.

- 1. On the menu bar, click on Terminal > Purchase.
- 2. Wait for the "Purchase" page to display.
- 3. In the "Payment Method" area, select **Credit Card Keyed Entry** from the drop-down list.
- 4. In the "Payment Details" area, do the following:

- a. In the Order ID field, optionally enter an Order ID.
- b. In the **Customer ID** field, optionally enter a Customer ID.
- c. In the **Statement Descriptor** field, enter a descriptor for the card statement.
 - If the **Customer Code** field displays, optionally enter a customer code.
 - If the Invoice Number field displays, optionally enter an invoice number.
- d. In the **Amount** field, enter the Purchase amount (#.##).
- e. In the Credit Card Number field, enter the card account number.
- f. In the **Expiry Date** field, enter the card expiry date (MMYY).
- g. In the Card Verification Digits field, enter the card verification digits.
- h. From the "ECI Indicator" drop-down list, select an e-commerce descriptor.
 - If the "Address Verification" area displays, enter the billing address data in the Street Number, Street Name (use also to enter PO box data), and Zip/Postal Code fields (for a post office box, checkmark PO Box).
 - To add order details (shipping/billing and product details), see page 64.
- 5. Click on the **Process Transaction** button.
 - If the **Proceed with Level 2/3** button and **Proceed with Purchase** button display on the "Purchase" page, see page 65.
- 6. When the "APPROVED" or "DECLINED" response displays on the "Purchase" page, the transaction is complete:
 - If Moneris Loyalty is enabled and you want to award loyalty points, see page 100.
 - If Moneris Loyalty is not enabled or it is but you want to bypass awarding points, print/e-mail the transaction receipt now (see page 83).

4.2 Purchase with cash

Cash sale of goods and services. Follow the steps below to perform a cash Purchase by manually entering (keying) the transaction data in the Merchant Resource Center fields.

- 1. On the menu bar, click on Terminal > Purchase.
- 2. Wait for the "Purchase" page to display.
- 3. In the "Payment Method" area, select Cash from the drop-down list.
- 4. In the "Payment Details" area, do the following:

Note: For information about fields referred to in the steps below, see page 221.

- a. In the Order ID field, optionally enter an Order ID.
- b. In the Customer ID field, optionally enter a Customer ID.
- c. In the **Amount** field, enter the Purchase amount (#.##).
- d. In the **Amount Tendered** field, optionally enter the dollar amount tendered by the customer.

Note: The **Change Due** field will automatically display the dollar amount owed to the customer.

- 5. Click on the **Complete** button.
- 6. When the "APPROVED" response displays on the "Purchase" page, the transaction is complete:
 - If Moneris Loyalty is enabled and you want to award loyalty points, see page 103.
 - If Moneris Loyalty is not enabled or it is but you want to bypass awarding points, print/e-mail the transaction receipt now (see page 83).

4.3 Group Purchase with debit/credit card

Follow the steps below to perform two or more credit Purchases simultaneously by manually entering (keying) credit card data in the Merchant Resource Center fields.

Note: Some chip debit cards may be used for any transaction(s) in the group.

- 1. On the menu bar, click on Terminal > Group Purchase.
- 2. Wait for the "Group Purchase" page to display.
- 3. Enter the payment details for the Purchase that you want to add to the group:

- a. In the Order ID field, optionally enter an Order ID.
- b. In the Customer ID field, optionally enter a Customer ID.
- c. In the **Amount** field, enter the Purchase amount (#.##).
- d. In the **Credit Card Number** field, enter the card account number.
- e. In the Expiry Date field, enter the card expiry date (MMYY).
- f. In the Card Verification Digits field, enter the card verification digits.
- g. From the ECI drop-down list, select an e-commerce descriptor.
- h. Click on the Add Transaction to Group button.
- 4. When the new transaction displays on the "Group Purchase" page, do one of the following:
 - To add another Purchase to the group, repeat step 3.
 - To continue without adding another Purchase to the group, go to step 5.
- 5. Click on the **Process Transactions** button.
- 6. When the group ticket number (e.g., "Group Ticket # : 12345678123456") displays on the page, click on the **View Results** button.
- 7. When the "Group Transaction Reports" page displays, refer to the "Transaction List" and confirm that each Purchase was "APPROVED" or "DECLINED".
- 8. Do the following:
 - a. In the "Transaction List" area, click on the Order ID (see "ORDER ID" column) of one of the Purchase transactions.
 - b. When the transaction's "Order History" page displays, print/e-mail the transaction receipt (see page 83).
 - c. Repeat step 8 for any remaining Purchase listed in the "Transaction List" area.

4.4 Preauthorization with debit/credit card

Preauthorizes an amount on a credit card.

Note: Some chip debit cards may be used for this transaction.

• For a listing of supported card entry methods, including the associated procedures describing how to use them to perform this transaction, refer to the table below:

Card entry method	See procedure on:
iPP320 PINpad	page 34
iPP320 PINpad (manual)	page 35
unencrypted MSR	page 37
Vault profile	page 38
keyed entry	page 40

4.4.1 Preauthorization with debit/credit card: iPP320 PINpad

Preauthorizes an amount on a credit card. Follow the steps below to perform a credit Preauthorization by capturing credit card data (insert or swipe) with an iPP320 PINpad.

Note: Some chip debit cards may be used for this transaction.

Important! To receive the funds for this transaction, you must perform a debit/credit Capture at a later time (see *Capturing a debit/credit Preauthorization* on page 43).

- 1. On the menu bar, click on Terminal > Preauth.
- 2. Wait for the "Preauth" page to display.
- 3. In the "Payment Method" area, select **Debit/Credit Pinpad** from the drop-down list
- 4. In the "Payment Details" area, do the following:

- a. In the Order ID field, optionally enter an Order ID.
- b. In the **Customer ID** field, optionally enter a Customer ID.
- c. In the **Amount** field, enter the Preauthorization amount (#.##).
- 5. Click on the Process Transaction button.
- 6. When "Establishing communication with pinpad" displays on the "Preauth" page, wait.
- 7. When "Please follow prompts on pinpad" displays on the "Preauth" page, see page 78.
- 8. When the "APPROVED or "DECLINED" response displays on the "Preauth" page, the transaction is complete:
 - If Moneris Loyalty is enabled and you want to allocate loyalty points, see page 105.
 - If Moneris Loyalty is not enabled or it is but you want to bypass allocating points, print/e-mail the transaction receipt now (see page 83).

4.4.2 Preauthorization with debit/credit card: iPP320 PINpad (manual card entry)

Preauthorizes an amount on a credit card. Follow the steps below to perform a credit Preauthorization by manually entering (keying) the credit card data on an iPP320 PINpad.

Note: Some chip debit cards may be used for this transaction.

Important! To receive the funds for this transaction, you must perform a debit/credit Capture at a later time (see page 43).

- 1. On the menu bar, click on **Terminal** > **Preauth**.
- 2. Wait for the "Preauth" page to display.
- 3. In the "Payment Method" area, select **Debit/Credit Pinpad** from the drop-down list.
- 4. In the "Payment Details" area, do the following:

- a. Checkmark the **Enable manual card input** box.
- b. In the Order ID field, optionally enter an Order ID.
- c. In the **Customer ID** field, optionally enter a Customer ID.
- d. In the **Amount** field, enter the Preauthorization amount (#.##).
- 5. Click on the **Process Transaction** button.
- 6. When "Establishing communication with pinpad" displays on the "Preauth" page, wait.
- 7. When "Please follow prompts on pinpad" displays on the "Preauth" page, do the following:
 - a. When "SWIPE OR INSERT CARD" displays on the iPP320 PINpad, key in the card account number, and press the green key.
 - b. When "EXPIRY DATE MMYY" displays on the iPP320 PINpad, key in the card expiry date (MMYY), and press the green key.
 - c. When "PLEASE WAIT" displays on the iPP320 PINpad, wait.
 - d. When "APPROVED THANK YOU OBTAIN CARD" displays on the iPP320 PINpad, press the green key.
- 8. When the "APPROVED or "DECLINED" response displays on the "Preauth" page, the transaction is complete:

4 Virtual terminal

- If Moneris Loyalty is enabled and you want to allocate loyalty points, see page 105.
- If Moneris Loyalty is not enabled or it is but you want to bypass allocating points, print/e-mail the transaction receipt now (see page 83).

4.4.3 Preauthorization with debit/credit card: unencrypted MSR

Preauthorizes an amount on a credit card. Follow the steps below to perform a credit Preauthorization by using an unencrypted magnetic stripe reader to capture credit card data.

Important! To receive the funds for this transaction, you must perform a debit/credit Capture at a later time (see page 43).

Note: Some chip debit cards may be used for this transaction. If your store is enabled for level 2/3 reporting (see page 232) and you swipe a purchasing card, you may be prompted to add level 2/3 details during the Capture.

- 1. On the menu bar, click on Terminal > Preauth.
- 2. Wait for the "Preauth" page to display.
- 3. In the "Payment Method" area, select Credit Card MSR from the drop-down list.
- 4. In the "Payment Details" area, do the following:

- a. In the Order ID field, optionally enter an Order ID.
- b. In the **Customer ID** field, optionally enter a Customer ID.
- c. In the **Statement Descriptor** field, enter a descriptor for the card statement.
 - If the **Customer Code** field displays, optionally enter a customer code.
 - If the Invoice Number field displays, optionally enter an invoice number.
- d. In the **Amount** field, enter the Preauthorization amount (#.##).
- e. In the **Card Verification Digits** field, enter the card verification digits.
 - If the "Address Verification" area displays, enter the billing address data in the Street Number, Street Name (use also to enter PO box data), and Zip/Postal Code fields (for a post office box, checkmark PO Box).
 - To add order details (shipping/billing and product details), see page 64.
- 5. Click on the **Swipe Card** button.
- 6. When "Please swipe credit card now" displays on the "Preauth" page, swipe the card on the unencrypted magnetic stripe reader.
- 7. When the "APPROVED" or "DECLINED" response displays on the "Preauth" page, the transaction is complete:
 - If Moneris Loyalty is enabled and you want to allocate loyalty points, see page 105.
 - If Moneris Loyalty is not enabled or it is but you want to bypass allocating points, print/e-mail the transaction receipt now (see page 83).

4.4.4 Preauthorization with debit/credit card: Vault profile

Preauthorizes an amount on a credit card. Follow the steps below to perform a credit Preauthorization by sourcing credit card data from a Vault profile.

Important! To receive the funds for this transaction, you must perform a debit/credit Capture at a later time (see page 43).

Note: Some chip debit cards may be used for this transaction. If a purchasing card is registered to the Vault profile and your store is enabled for level 2/3 reporting (see page 232), you may be prompted to add level 2/3 details during the Capture.

- 1. On the menu bar, click on **Terminal** > **Preauth**.
- 2. Wait for the "Preauth" page to display.
- 3. In the "Payment Method" area, select **Vault Profile Keyed Entry** from the drop-down list.
- 4. In the "Payment Details" area, do the following:
 - a. In the **Data Key** field, enter the data key of the Vault profile from which you want to source the card data.
 - b. Click on the **Verify Data Key** button.
 - c. Confirm that the **Credit Card Number** and **Expiry Date** fields are populated with the correct card data.
 - d. In the Card Verification Digits field, enter the card verification digits.
 - If the "Address Verification" area displays, confirm that the Street
 Number, Street Name (use also to enter PO box data), and Zip/Postal Code fields are populated with the correct address data.
- 5. In the "Payment Details" area, fill in the remaining fields:

- a. In the **Order ID** field, optionally enter an Order ID.
- b. In the **Customer ID** field, optionally enter a Customer ID.
- c. In the **Statement Descriptor** field, enter a descriptor for the card statement.
- d. In the Amount field, enter the Preauthorization amount (#.##).
- e. From the "ECI Indicator" drop-down list, select an e-commerce descriptor.
 - To add order details (shipping/billing and product details), see page 64.
- 6. Click on the Process Transaction button.
- 7. When the "APPROVED" or "DECLINED" response displays on the "Preauth" page, the transaction is complete:

4

- If Moneris Loyalty is enabled and you want to allocate loyalty points, see page 105.
- If Moneris Loyalty is not enabled or it is but you want to bypass allocating points, print/e-mail the transaction receipt now (see page 83).

4.4.5 Preauthorization with debit/credit card: keyed entry

Preauthorizes an amount on a credit card. Follow the steps below to perform a credit Preauthorization by manually entering (keying) credit card data in the Merchant Resource Center fields.

Important! To receive the funds for this transaction, you must perform a debit/credit Capture at a later time (see page 43).

Note: Some chip debit cards may be used for this transaction. If your store is enabled for level 2/3 reporting (see page 232) and you enter a purchasing card, you may be prompted to add level 2/3 details during the Capture.

- 1. On the menu bar, click on **Terminal** > **Preauth**.
- 2. Wait for the "Preauth" page to display.
- 3. In the "Payment Method" area, select **Credit Card Keyed Entry** from the drop-down list.
- 4. In the "Payment Details" area, do the following:

- a. In the **Order ID** field, optionally enter an Order ID.
- b. In the **Customer ID** field, optionally enter a Customer ID.
- c. In the **Statement Descriptor** field, enter a descriptor for the card statement.
 - If the **Customer Code** field displays, optionally enter a customer code.
 - If the Invoice Number field displays, optionally enter an invoice number.
- d. In the **Amount** field, enter the Preauthorization amount (#.##).
- e. In the Credit Card Number field, enter the card account number.
- f. In the **Expiry Date** field, enter the card expiry date (MMYY).
- g. In the **Card Verification Digits** field, enter the card verification digits.
- h. From the "ECI Indicator" drop-down list, select an e-commerce descriptor.
 - If the "Address Verification" area displays, enter the billing address in the Street Number, Street Name (use also to enter PO box data), and Zip/Postal Code fields (for a post office box, checkmark PO Box).
 - To add order details (shipping/billing and product details), see page 64.
- 5. Click on the **Process Transaction** button.
- 6. When the "APPROVED" or "DECLINED" response displays on the "Preauth" page, the transaction is complete:

4

- If Moneris Loyalty is enabled and you want to allocate loyalty points, see page 105.
- If Moneris Loyalty is not enabled or it is but you want to bypass allocating points, process the transaction receipt now (see page 83).

4.5 Reauthorization with debit/credit card

Follow the steps below to re-authorize another hold on the unused funds of a debit/credit Preauthorization that has already been partially captured.

Important! To receive the funds for this transaction, you must perform a debit/credit Capture at a later time (see page 45).

Note: If your store is enabled for level 2/3 reporting (see page 232) and the original Preauthorization was performed with a purchasing card, you may be prompted to add level 2/3 details during the Capture.

- 1. Retrieve the original debit/credit Preauthorization that you want to reauthorize (see page 164).
- 2. When the Transaction report is generated, locate the original debit/credit Preauthorization that you want to reauthorize, and then click on its corresponding **Reauth** button.
- 3. Wait for the "Reauth" page to display, and then do the following:

Note: For information about fields referred to in the steps below, see page 221.

- a. In the Reauth Order Id field, optionally enter a Reauth Order ID.
- b. In the **Statement Descriptor** field, enter a descriptor for the card statement.
 - If the **Customer Code** field displays, optionally enter a customer code.
 - If the Invoice Number field displays, optionally enter an invoice number.
- c. In the **Amount** field, enter the Reauthorization amount (#.##).
- 4. Click on the **Process Transaction** button.
- 5. When the "APPROVED" or DECLINED response displays on the Reauth page, the transaction is complete.
- 6. Print/e-mail the debit/credit Reauthorization receipt now (see page 83).

Note: Moneris loyalty points cannot be allocated (awarded) for a Reauthorization transaction.

4.6 Capturing a debit/credit Preauthorization

Follow the steps below to capture a debit/credit Preauthorization (see page 33) so that the authorized funds are transferred to your account at settlement.

Note: If you are capturing a Preauthorization that was originally performed on an iPP320 PINpad (insert or swipe), ensure that the same iPP320 PINpad is connected to your computer while you are performing the Capture.

- 1. On the menu bar, click on **Terminal** > **Capture**.
- 2. Wait for the "Capture/Preauth Completion" page to display.
- 3. In the **Order ID** field, enter the Order ID of the original debit/credit Preauthorization that you want to capture.

Note: If you only have a partial Order ID, mark the **begins with** or the **ends with** radio button.

- 4. Click on the Locate Transaction button.
- 5. In the "Transaction List" area, locate the Preauthorization that you want to capture, and then click on its corresponding **Capture** button.
- 6. Wait for the "Transaction Details" area to display, and then do the following:

Note: For information about fields referred to in the steps below, see page 221.

- a. In the **Statement Descriptor** field, enter a descriptor for the card statement.
 - If the Customer Code field displays, optionally enter a customer code.
 - If the Invoice Number field displays, optionally enter an invoice number.
- b. In the **Amount** field, do one of the following:
 - To capture the Preauthorization, enter the amount (#.##) that you want to capture.

Note: If the Preauthorization is captured for an amount that is less than the original Preauthorization amount, the un-captured amount will for a period of time remain available for a subsequent Reauthorization (see page 42).

- To cancel the Preauthorization and release the funds, enter a zero-dollar amount (0.00).
- c. If the **Add Level 2/3 Details** button displays, do one of the following:
 - To add level 2/3 details to the Capture, see page 66.
 - To proceed without adding level 2/3 details to the capture, go to step 7.
- 7. Click on the **Process Transaction** button.

- If "Establishing communication with pinpad" displays on the "Capture" page, wait while the Merchant Resource Center communicates with the iPP320 PINpad (you will not need to pass the iPP320 PINpad back and forth to the cardholder).
- 8. When the "APPROVED" or "DECLINED" response displays on the "Capture" page, the transaction is complete:
 - If you allocated loyalty points for the original debit/credit Preauthorization and you now want to award the points, seepage 106.
 - If did not award loyalty points for the original transaction, print/e-mail the debit/credit Capture receipt now (see page 83).

4.7 Capturing a debit/credit Reauthorization

Follow the steps below to capture a debit/credit Reauthorization (see page 42) so that the authorized funds are transferred to your account at settlement.

Note: If you are capturing a Reauthorization that was originally a Preauthorization performed on an iPP320 PINpad (insert or swipe), ensure that the same iPP320 PINpad is connected to your computer while you are performing the Capture.

- 1. On the menu bar, click on **Terminal** > **Capture**.
- 2. Wait for the "Capture/Preauth Completion" page to display.
- 3. In the **Order ID** field, enter the Order ID of the original debit/credit Reauthorization that you want to capture.

Note: If you only have a partial Order ID, mark the **begins with** or the **ends with** radio button.

- 4. Click on the Locate Transaction button.
- 5. In the "Transaction List" area, locate the Reauthorization that you want to capture, and then click on its corresponding **Capture** button.
- 6. Wait for the "Transaction Details" area to display, and then do the following:

Note: For information about fields referred to in the steps below, see page 221.

- a. In the **Statement Descriptor** field, enter a descriptor for the card statement.
 - If the **Customer Code** field displays, optionally enter a customer code.
 - If the Invoice Number field displays, optionally enter an invoice number.
- b. In the **Amount** field, do one of the following:
 - To capture the Reauthorization, enter the amount (#.##) that you want to capture.

Note: If the Reauthorization is captured for an amount that is less than the original Reauthorization amount, the un-captured amount will for a period of time remain available for a subsequent Reauthorization.

- To cancel the Reauthorization and release the funds, enter a zero-dollar amount (0.00).
- c. If the **Add Level 2/3 Details** button displays, do one of the following:
 - To add level 2/3 details to the Capture, see page 70.
 - To proceed without adding level 2/3 details to the Capture, go to step 7.
- 7. Click on the **Process Transaction** button.

- If "Establishing communication with pinpad" displays on the "Capture" page, wait while the Merchant Resource Center communicates with the iPP320 PINpad (you will not need to pass the iPP320 PINpad back and forth to the cardholder).
- 8. When the "APPROVED" or "DECLINED" response displays on the "Capture" page, the transaction is complete.
- 9. Print/e-mail the debit/credit Capture receipt now (see page 83).

Note: Moneris loyalty points cannot be awarded for the capture of a Reauthorization transaction.

4.8 Voice Authorization-Advice with debit/credit card

Credit card sale of goods and services using authorization code obtained from an IVR system.

Note: Some chip debit cards may be used for this transaction. UnionPay cards cannot be used for this transaction.

• For a listing of supported card entry methods, including the associated procedures describing how to use them to perform this transaction, refer to the table below:

Card entry method	See procedure on:
unencrypted MSR	page 48
keyed entry	page 49

4.8.1 Voice Authorization-Advice with debit/credit card: unencrypted MSR

Credit card sale of goods and services using authorization code obtained from an IVR system. Follow the steps below to perform a credit Voice Authorization-Advice using an unencrypted magnetic stripe reader to capture the credit card data.

Note: Some chip debit cards may be used for this transaction. UnionPay cards cannot be used for this transaction.

- 1. On the menu bar, click on **Terminal** > **Voice Auth**.
- 2. Wait for the "Voice Authorization/Advice" page to display.
- 3. In the "Payment Method" area, select Credit Card MSR from the drop-down list.
- 4. In the "Payment Details" area, do the following:

- a. In the Order ID field, optionally enter an Order ID.
- b. In the **Customer ID** field, optionally enter a Customer ID.
- c. In the **Statement Descriptor** field, enter a descriptor for the card statement.
- d. In the **Auth Code** field, enter the authorization code that you obtained when you called to authorize this transaction.
- e. In the **Amount** field, enter the Voice Authorization/Advice transaction amount (#.##).
- 5. Click on the **Swipe Card** button.
- 6. When "Please swipe credit card now" displays on the "Authorization/Advice" page, swipe the card on the unencrypted magnetic stripe reader.
- 7. When the "APPROVED" or "DECLINED" response displays on the "Voice Authorization/Advice" page, the transaction is complete:
 - If Moneris Loyalty is enabled and you want to award loyalty points, see page 102.
 - If Moneris Loyalty is not enabled or it is but you want to bypass awarding points, print/e-mail the Voice Authorization-Advice receipt now (see page 83).

4.8.2 Voice Authorization-Advice with debit/credit card: keyed entry

Credit card sale of goods and services using authorization code obtained from an IVR system. Follow the steps below to perform a credit Voice Authorization-Advice by manually entering (keying) credit card data in the Merchant Resource Center fields.

Note: Some chip debit cards may be used for this transaction. UnionPay cards cannot be used for this transaction.

- 1. On the menu bar, click on **Terminal** > **Voice Auth**.
- 2. Wait for the "Voice Authorization/Advice" page to display.
- 3. In the "Payment Method" area, select **Credit Card Keyed Entry** from the drop-down list.
- 4. In the "Payment Details" area, do the following:

- a. In the Order ID field, optionally enter an Order ID.
- b. In the **Customer ID** field, optionally enter a Customer ID.
- c. In the **Statement Descriptor** field, enter a descriptor for the card statement.
- d. In the **Auth Code** field, enter the authorization code that you obtained when you called to authorize this transaction.
- e. In the **Amount** field, enter the Voice Authorization/Advice transaction amount (#.##).
- f. In the **Credit Card Number** field, enter the card account number.
- g. In the **Expiry Date** field, enter the card expiry date (MMYY).
- h. From the "ECI Indicator" drop-down list, select an e-commerce descriptor.
- 5. Click on the Process Transaction button.
- 6. When the "APPROVED" or "DECLINED" response displays on the "Voice Authorization/Advice" page, the transaction is complete:
 - If Moneris Loyalty is enabled and you want to award loyalty points, see page 102.
 - If Moneris Loyalty is not enabled or it is but you want to bypass awarding points, print/e-mail the Voice Authorization-Advice receipt now (see page 83).

4.9 Void with debit/credit card

Follow the steps below to reverse (cancel) a Merchant Resource Center-referenced debit/credit card Purchase, Capture, or Voice Authorization-Advice in an open batch.

Note: To reverse a Merchant Resource Center-referenced credit transaction in a closed batch, you must perform a credit Refund (see page 51).

To reverse any debit/credit transaction that is unreferenced on the Merchant Resource Center, you must perform an Independent Refund (see page 54).

If you are reversing a transaction that was originally performed on an iPP320 PINpad (insert or swipe), ensure that the same iPP320 PINpad is connected to your computer while you are performing the Void.

- 1. On the menu bar, click on Terminal > Void.
- 2. Wait for the "Void" page to display.
- 3. In the **Order ID** field, enter the Order ID of the original transaction that you want to reverse.

Note: If you only have a partial Order ID, mark the **begins with** or the **ends with** radio button.

- 4. Click on the Locate Transaction button.
- 5. Wait for the "Void" page to display.
- 6. In the "Transaction List" area, click on the **Void** button beside the transaction that you want to reverse.
- 7. In the "Transaction Details" area, do the following:

- If the Customer Code field displays, optionally enter a customer code.
- If the Invoice Number field displays, optionally enter an invoice number.
- 8. Click on the Process Transaction button.
 - If "Establishing communication with pinpad" displays on the "Void" page, wait until "Please follow prompts on pinpad" displays (see page 78).
- 9. When the "APPROVED" or "DECLINED" response displays on the "Void" page, the transaction is complete:
 - If you want to remove any Moneris loyalty points awarded for the original transaction, see page 114.
 - If you did not award loyalty points for the original transaction, print/e-mail the Purchase-Correction (Void) receipt now (see page 83).

4.10 Refund with debit/credit card

Follow the steps below to fully or partially reverse (refund) a Merchant Resource Centerreferenced credit card Purchase, Capture, or Voice Authorization-Advice in a closed batch.

Note: If you are reversing a transaction that was originally performed on an iPP320 PINpad (insert or swipe), ensure that the same iPP320 PINpad is connected to your computer while you are performing the Refund.

To reverse a Merchant Resource Center-referenced debit card transaction, you must do a Void (see page 50). If you cannot retrieve the transaction using the Void function, try doing a Refund by following the steps below.

To reverse any debit/credit card transaction that is unreferenced on the Merchant Resource Center, you must do an Independent Refund (see page 54).

- 1. On the menu bar, click on **Terminal** > **Refund**.
- 2. Wait for the "Refund" page to display.
- 3. In the **Order ID** field, enter the Order ID of the original transaction that you want to reverse.

Note: If you only have a partial Order ID, mark the **begins with** or the **ends with** radio button.

- 4. Click on the Locate Transaction button.
- 5. Wait for the "Refund" page to display.
- 6. In the "Transaction List" area, click on the **Refund** button beside the transaction that you want to reverse.
- 7. In the "Transaction Details" area, do the following:

- a. In the **Amount** field, enter the amount to be refunded (#.##); otherwise, leave the displayed amount as is to refund the full amount of the original transaction.
 - If the **Customer Code** field displays, optionally enter a customer code.
 - If the Invoice Number field displays, optionally enter an invoice number.
- b. If the Add Level 2/3 Details button displays, do one of the following:
 - To add level 2/3 details to the Refund, see page 74.
 - To proceed without adding level 2/3 details to the Refund, go to step 8.
- 8. Click on the Process Transaction button.
 - If "Establishing communication with pinpad" displays on the "Refund" page, wait until "Please follow prompts on pinpad" displays (see page 78).

Virtual terminal

- 9. When the "APPROVED" or "DECLINED" response displays on the "Refund" page, the transaction is complete:
 - If you want to remove any Moneris loyalty points awarded for the original
 - transaction, see page 117.

 If did not award loyalty points for the original transaction, print/e-mail the Refund receipt now (see page 83).

4.11 Refund with cash

Follow the steps below to fully or partially reverse (refund) a cash transaction. You will manually enter (key) all transaction data in the Merchant Resource Center fields.

- 1. On the menu bar, click on **Terminal** > **Refund**.
- 2. Wait for the "Refund" page to display.
- 3. In the **Order ID** field, enter the Order ID of the original transaction that you want to reverse.

Note: If you only have a partial Order ID, mark the **begins with** or the **ends with** radio button.

- 4. Click on the Locate Transaction button.
- 5. Wait for the "Refund" page to display.
- 6. In the "Transaction List" area, click on the **Refund** button beside the transaction that you want to reverse.
- 7. In the **Amount** field, enter the amount to be refunded (#.##); otherwise, leave the displayed amount as is to refund the full amount of the original transaction.
- 8. Click on the **Process Transaction** button.
- 9. When the "APPROVED" response displays on the "Refund" page, the transaction is complete:
 - If you want to remove any Moneris loyalty points awarded for the original transaction, see page 117.
 - If did not award loyalty points for the original transaction, print/e-mail the Refund receipt now (see page 83).

4.12 Independent Refund with debit/credit card

Reverse (refund) a debit/credit card transaction that is unreferenced on the Merchant Resource Center.

• For a listing of supported card entry methods, including the associated procedures describing how to use them to perform this transaction, refer to the table below:

Card entry method	See procedure on:
iPP320 PINpad	page 55
iPP320 PINpad (manual)	page 56
unencrypted MSR	page 57
Vault profile	page 58
keyed entry	page 59

4.12.1 Independent Refund with debit/credit card: iPP320 PINpad

Follow the steps below to fully or partially reverse (refund) a debit/credit card transaction that is unreferenced on the Merchant Resource Center. You will use an iPP320 PINpad to capture the card data via insert, tap, or swipe.

- 1. On the menu bar, click on **Terminal** > **Independent Refund**.
- 2. Wait for the "Independent Refund" page to display.
- In the "Payment Method" area, select Debit/Credit Pinpad from the drop-down list.
- 4. In the "Payment Details" area, do the following:

- a. Ensure that the **Enable manual card input** box is unmarked.
- b. In the **Order ID** field, optionally enter an Order ID.
- c. In the **Customer ID** field, optionally enter a Customer ID.
- d. In the **Amount** field, enter the Independent Refund amount (#.##).
- 5. Click on the Process Transaction button.
- 6. When "Establishing communication with pinpad" displays on the "Independent Refund" page, wait.
- 7. When "Please follow prompts on pinpad" displays on the "Independent Refund" page, see page 78.
- 8. When the "APPROVED or "DECLINED" response displays on the "Independent Refund" page, the transaction is complete.
- 9. Print/e-mail the Independent Refund receipt now (see page 83).

4.12.2 Independent Refund with debit/credit card: iPP320 PINpad (manual card entry)

Follow the steps below to fully or partially reverse (refund) a debit/credit card transaction that is unreferenced on the Merchant Resource Center. You will manually enter (key) the card data on an iPP320 PINpad.

Note: Some chip debit cards may be used for this transaction.

- 1. On the menu bar, click on **Terminal** > **Independent Refund**.
- 2. Wait for the "Independent Refund" page to display.
- In the "Payment Method" area, select Debit/Credit Pinpad from the drop-down list.
- 4. In the "Payment Details" area, do the following:

- a. Checkmark the **Enable manual card input** box.
- b. In the Order ID field, optionally enter an Order ID.
- c. In the Customer ID field, optionally enter a Customer ID.
- d. In the Amount field, enter the Independent Refund amount (#.##).
- 5. Click on the Process Transaction button.
- 6. When "Establishing communication with pinpad" displays on the "Independent Refund" page, wait.
- 7. When "Please follow prompts on pinpad" displays on the "Independent Refund" page, do the following:
 - a. When "SWIPE, TAP OR INSERT CARD" (or "SWIPE OR INSERT CARD") displays on the iPP320 PINpad, key in the card account number, and press the green key.
 - b. When "EXPIRY DATE MMYY" displays on the iPP320 PINpad, key in the card expiry date (MMYY), and press the green key.
 - c. When "PLEASE WAIT" displays on the iPP320 PINpad, wait.
 - d. When "APPROVED THANK YOU OBTAIN CARD" displays on the iPP320 PINpad, press the green key (return the card to the cardholder).
- 8. When the "APPROVED or "DECLINED" response displays on the "Independent Refund" page, the transaction is complete.
- 9. Print/e-mail the Independent Refund receipt now (see page 83).

4.12.3 Independent Refund with debit/credit card: unencrypted MSR

Follow the steps below to fully or partially reverse (refund) a debit/credit card transaction that is unreferenced on the Merchant Resource Center. You will use an unencrypted magnetic stripe reader to capture the card data.

Note: Some chip debit cards may be used for this transaction.

- 1. On the menu bar, click on **Terminal** > **Independent Refund**.
- 2. Wait for the "Independent Refund" page to display.
- 3. In the "Payment Method" area, select Credit Card- MSR from the drop-down list.
- 4. In the "Payment Details" area, do the following:

- a. In the Order ID field, optionally enter an Order ID.
- b. In the **Customer ID** field, optionally enter a Customer ID.
- c. In the **Statement Descriptor** field, enter a descriptor for the card statement.
- d. In the Amount field, enter the Independent Refund amount (#.##).
- 5. Click on the **Swipe Card** button.
- 6. When "Please swipe credit card now" displays on the "Independent Refund" page, swipe the card on the unencrypted magnetic stripe reader.
- 7. When the "APPROVED" or "DECLINED" response displays on the "Independent Refund" page, the transaction is complete.
- 8. Print/e-mail the Independent Refund receipt now (see page 83).

4.12.4 Independent Refund with debit/credit card: Vault profile

Follow the steps below use credit card data sourced from a Vault profile to fully or partially reverse (refund) a debit/credit card transaction that is unreferenced on the Merchant Resource Center.

Note: Some chip debit cards may be used for this transaction.

- 1. On the menu bar, click on **Terminal** > **Independent Refund**.
- 2. Wait for the "Independent Refund" page to display.
- 3. In the "Payment Method" area, select **Vault Profile Keyed Entry** from the drop-down list.
- 4. In the "Payment Details" area, do the following:

- a. In the **Data Key** field, enter the data key of the Vault profile from which you want to source the card data.
- b. Click on the **Verify Data Key** button.
- c. Confirm that the **Credit Card Number** and **Expiry Date** fields are populated with the correct card data.
- d. In the **Card Verification Digits** field, enter the card verification digits.
- 5. In the "Payment Details" area, fill in the remaining fields:
 - a. In the **Order ID** field, optionally enter an Order ID.
 - b. In the **Customer ID** field, optionally enter a Customer ID.
 - c. In the **Amount** field, enter the Independent Refund amount (#.##).
 - d. In the **Statement Descriptor** field, enter a descriptor for the card statement.
- 6. Click on the Process Transaction button.
- 7. When the "APPROVED" or "DECLINED" response displays on the "Independent Refund" page, the transaction is complete.
- 8. Print/e-mail the Independent Refund receipt now (see page 83).

4.12.5 Independent Refund with debit/credit card: keyed entry

Follow the steps below to fully or partially reverse (refund) a debit/credit card transaction that is unreferenced on the Merchant Resource Center. You will manually enter (key) the card data in the Merchant Resource Center fields.

- 1. On the menu bar, click on **Terminal** > **Independent Refund**.
- 2. Wait for the "Independent Refund" page to display.
- 3. In the "Payment Method" area, select **Credit Card Keyed Entry** from the drop-down list.
- 4. In the "Payment Details" area, do the following:
 - a. In the **Statement Descriptor** field, enter a descriptor for the card statement.
 - b. In the Amount field, enter the Independent Refund amount (#.##).
 - c. In the Credit Card Number field, enter the card account number.
 - d. In the **Expiry Date** field, enter the card expiry date (MMYY).
 - e. In the **Card Verification Digits** field, enter the card verification digits.
 - f. From the "ECI Indicator" drop-down list, select an e-commerce descriptor.
- Click on the Process Transaction button.
- 6. When the "APPROVED" or "DECLINED" response displays on the "Independent Refund" page, the transaction is complete.
- 7. Print/e-mail the Independent Refund receipt now (see page 83).

4.13 Card Verification with debit/credit card

Obtain card and address verification without charging the cardholder's credit card (e.g.,, you may want to verify that a credit card is valid before storing the card number on file for future payments (e.g., recurring billing, registering the card in a Vault profile, etc.).

Note: Some chip debit cards may be used for this transaction. UnionPay cards cannot be used for this transaction.

• For a listing of supported card entry methods, including the associated procedures describing how to use them to perform this transaction, refer to the table below:

Card entry method	See procedure on:
unencrypted MSR	page 61
keyed entry	page 62

4.13.1 Card Verification with debit/credit card: unencrypted MSR

Follow the steps below to perform a Card Verification with a credit card by using an unencrypted magnetic stripe reader to capture the card data.

Note: Some chip debit cards may be used for this transaction. UnionPay cards cannot be used for this transaction.

- 1. On the menu bar, click on **Terminal** > **Verification**.
- 2. Wait for the "Card Verification" page to display.
- 3. In the "Payment Method" area, select Credit Card MSR from the drop-down list.
- 4. In the "Payment Details" area, do the following:

- a. In the Order ID field, optionally enter an Order ID.
- b. In the **Customer ID** field, optionally enter a Customer ID.
 - If the "Address Verification" area displays, enter the billing address data in the Street Number, Street Name (use also to enter PO box data), and Zip/Postal Code fields (for a post office box, checkmark PO Box).
- 5. Click on the **Swipe Card** button.
- 6. When "Please swipe credit card now" displays on the "Card Verification" page, swipe the card on the unencrypted magnetic stripe reader.
- 7. When the "APPROVED" or "DECLINED" response displays on the "Card Verification" page, the transaction is complete.
- 8. Print/e-mail the Card Verification receipt (see page 83).

4.13.2 Card Verification with debit/credit card: keyed entry

Follow the steps below to perform a Card Verification with a credit card by manually entering (keying) the card data in the Merchant Resource Center fields.

Note: Some chip debit cards may be used for this transaction. UnionPay cards cannot be used for this transaction.

- 1. On the menu bar, click on **Terminal** > **Verification**.
- 2. Wait for the "Card Verification" page to display.
- In the "Payment Method" area, select Credit Card Keyed Entry from the dropdown list.
- 4. In the "Payment Details" area, do the following:

- a. In the Order ID field, optionally enter an Order ID.
- b. In the **Customer ID** field, optionally enter a Customer ID.
- c. In the Credit Card Number field, enter the card account number.
- d. In the **Expiry Date** field, enter the card expiry date (MMYY).
- e. From the "ECI Indicator" drop-down list, select an e-commerce descriptor.
 - If the "Address Verification" area displays, enter the billing address data in the Street Number, Street Name (use also to enter PO box data), and Zip/Postal Code fields (for a post office box, checkmark PO Box).
- 5. Click on the Process Transaction button.
- 6. When the "APPROVED" or "DECLINED" response displays on the "Card Verification" page, the transaction is complete.
- 7. Print/e-mail the Card Verification receipt (see page 83).

4.14 Chip Initialization

Follow the steps below to initialize an iPP320 PINpad (see page 13) that is connected to your computer and registered to your Merchant Resource Center store.

- 1. On the menu bar, click on **Terminal** > **Chip Initialization**.
- 2. When "Establishing communication with pinpad" displays on the "Chip Initialization" page, wait.
- 3. When "Downloading pinpad parameters from the host" displays on the "Chip Initialization" page, wait.

Note: The iPP320 PINpad displays "PLEASE WAIT" during this process.

- If a Moneris "TerminalApplet" warning displays on your computer screen, select the option to always trust content from this publisher, and then allow the applet to run.
- If a "security warning" prompt displays on your computer screen prompting you for permission to allow the Moneris "TerminalApplet" to access a moneris.com Web site, select the option to always grant this access.
- 4. When the "Initialization Complete" response displays on the "Chip Initialization" page, the iPP320 PINpd is ready to be used to process transactions.
 - If the **Continue** button displays, click on it.
- 5. The operation is complete.

4.15 Optional procedures: debit/credit cards

4.15.1 Adding order details to a transaction

Follow the steps below to add order details to a transaction.

Note: Order details are for receipt purposes only (the Merchant Resource Center will not perform calculations based on data sent in the order details fields). Only e-mail receipts can include order details. If you subsequently add level 2/3 details to an eligible follow-on Capture or Refund (see page 232), the Merchant Resource Center will discard any order details data submitted in the original transaction.

- 1. On the transaction page, click on the **Add Order Details** button.
- 2. Wait for the "Order Details" area to display on the transaction page.
- 3. In the "Billing Details" area, enter billing data in the fields (First Name, Last Name, Company, Address, City, State/Prov, Postal Code, Country, Phone, Fax, Shipping Details, First Name, Last Name, Company, Address, City, State/Prov, Postal Code, Country, Phone, and Fax).
- 4. Do one of the following:
 - If the shipping address is not the same as billing address, go to step 5.
 - If the shipping address is the same as billing address, checkmark the **Check if**Shipping address is the same as Billing address box, and go to step 6.
- 5. In the "Shipping Details" area, enter the customer shipping data in the fields (First Name, Last Name, Company, Address, City, State/Prov, Postal Code, Country, Phone, and Fax).
- 6. In the **Email Address** field, optionally enter the customer's e-mail address.
- 7. In the **Special Instructions** field, optionally enter supplementary details.
- 8. In the "Line Items Click 'Add Item' to include item in order" area, create a line item listing for a specific product/service being shipped/rendered in the order:
 - a. Enter the product details in the line item fields (**Product Code**, **Description**, **Quantity**, and **Amount**).
 - b. Click on the **Add Item** button.
 - c. When the product is listed in the "The items listed below will be included in the order details" area, do one of the following:
 - To add another line item, repeat steps 8a-c.
 - If you want to continue without adding additional line items, go to step 9.
- 9. In the "Taxes & Shipping" area, enter tax/shipping data in the fields (Shipping/Freight, Tax 1, and Tax 2).
- 10. Refer back to the financial transaction procedure.

4.15.2 When a purchasing (corporate) card is detected

When both the **Proceed with Level 2/3** button and **Proceed with Purchase** button display on the "Purchase" page, it means the Merchant Resource Center has detected that the card you entered is a purchasing (corporate) card.

1. You may add level 2/3 details to the transaction or bypass adding level 2/3 details:

To add level 2/3 details:

a. Click on the Proceed with Level 2/3 button.

Note: The transaction will be processed as a debit/credit Preauthorization.

b. When the "APPROVED" or "DECLINED" response displays on the "Preauth" page, the transaction is complete:

Important! To receive funds, you must perform a debit/credit Capture at a later time (see page 43). You will be prompted to add the level 2/3 details during the Capture.

- If Moneris Loyalty is enabled and you want to allocate loyalty points, see page 105.
- If Moneris Loyalty is not enabled or it is but you want to bypass allocating points, print/e-mail the transaction receipt now (see page 83).

To bypass adding level 2/3 details:

a. Click on the Proceed with Purchase button.

Note: The transaction will be processed as a debit/credit Purchase.

- b. When the "APPROVED" or "DECLINED" response displays on the "Purchase" page, the transaction is complete:
 - If Moneris Loyalty is enabled and you want to award loyalty points, see page 100.
 - If Moneris Loyalty is not enabled or it is but you want to bypass awarding points, print/e-mail the transaction receipt now (see page 83).

4.15.3 Adding level 2/3 details: capturing a debit/credit Preauthorization

When the "Transaction Details" of the debit/credit Preauthorization that you want to capture are displayed on the "Capture" page, follow the steps below to add level 2/3 tax details to the transaction.

Note: For more information about the level 2/3 details feature, see page 232.

- 1. Click on the Add Level 2/3 Details button.
- 2. When the **Destination Postal Code** field displays, do one of the following:
 - If you are shipping/rendering the order within Canada, enter the destination postal code (exclude spaces or hyphens).
 - If you are shipping/rendering the order internationally, leave the field blank so that no taxes are added to the Capture total.
- 3. Click on the **Continue** button.
- 4. Depending on the card type used to process the original Preauthorization, do one of the following:
 - If a Visa card was used, see page 67.
 - If a Mastercard was used, see page 68.
 - If an Amex card was used, see page 69.

4.15.3.1 Entering level 2/3 details: Visa cards (capturing a Preauthorization)

Follow the steps below to add Visa-specific level 2/3 details on the "Capture" page.

Note: For more information about the fields referred to in the steps below, see page 233.

- In the "Addendum 1 Details" area, enter shipping data in the fields (Buyer Name, Customer Ref. Identifier, Destination Country, Destination Postal Code, Freight Amount (inc taxes), Duty Amount, and VAT Reference Num).
 - If the "Tax Details" area displays (Canadian postal codes only) and the order is tax exempt, mark the "Invoice Tax Exempt" **Yes** radio button; otherwise, mark the **No** radio button, and enter the tax amount in the **HST Amount** field (must be less than 30% of original amount).
- 2. In the "Line Items" area, create a line item listing for a specific product/service being shipped/rendered in the order:
 - a. Enter the product details in the line item fields (Commodity Code, Product Code, Description, Quantity, Unit Meas., and Unit Cost).
 - If the "Tax Exempt for Line Item" HST box displays, checkmark it if the product is tax exempt.
 - If there is a discount on the product unit cost, enter the discount amount in the **Discount on unit cost** field (#.##).
 - b. Click on the **Add Line** button.
 - c. When the product is listed in "Line Items included in order" area, do one of the following:
 - To add another line item, repeat steps 2a-c.
 - To continue without adding additional line items, go to step 3.
- 3. Click on the **Calculate Totals** button, and confirm that each line item total is correct.

- 4. Click on the Process Transaction button.
- 5. When the "APPROVED" or "DECLINED" response displays on the "Capture" page, the transaction is complete:
 - If you allocated loyalty points for the original debit/credit Preauthorization and you want to award the points, see page 106.
 - If did not award loyalty points for the original transaction, print/e-mail the Capture receipt now (see page 83).

4.15.3.2 Entering level 2/3 details: Mastercard cards (capturing a Preauthorization)

Follow the steps below to enter Mastercard-specific level 2/3 details on the "Capture" page.

Note: For information about fields referred to in the steps below, see page 233.

- 1. In the "Addendum 1 Details" area, enter shipping data in the fields (**Destination Country**, **Destination Postal Code**, **Freight Amount (inc taxes)**, **Duty Amount**, and **Supplemental Data**).
 - If the "Tax Details" area displays(Canadian postal codes only) and the order is tax exempt, mark the "Invoice Tax Exempt" Yes radio button; otherwise, mark the No radio button, and enter the tax amount in the HST Amount field (must be less than 30% of original amount).
- 2. In the "Line Items" area, create a line item listing for a specific product/service being shipped/rendered in the order:
 - a. Enter product details in the line item fields (**Product Code**, **Description**, **Quantity**, **Unit Meas.**, and **Unit Cost**).
 - If the "Tax Exempt for Line Item" HST box displays, checkmark it if the product is tax exempt.
 - If there is a discount on the product unit cost, enter the discount amount in the **Discount on unit cost** field (#.##).
 - b. Click on the **Add Line** button.
 - c. When the product is now listed in the "Line Items included in order" area, do one of the following:
 - To add another line item, repeat steps 2a-c.
 - To continue without adding additional line items, go to step 3.
- 3. Click on the **Calculate Totals** button, and confirm that each line item total is correct.

- 4. Click on the Process Transaction button.
- 5. When the "APPROVED" or "DECLINED" response displays on the "Capture" page, the transaction is complete:
 - If you allocated loyalty points for the original debit/credit Preauthorization and you want to award the points, see page 106.
 - If did not award loyalty points for the original transaction, print/e-mail the Capture receipt now (see page 83).

4.15.3.3 Entering level 2/3 details: Amex cards (capturing a Preauthorization)

Follow the steps below to enter Amex -specific level 2/3 details on the "Capture" page:

- 1. In the "Customer Details" area, enter customer data in the fields (Customer Name, Street Address 1, Street Address 2, City, Province/State, Postal/Zip Code, Invoice Number, PO Number, Customer Reference ID).
 - If the "Tax Details" area displays (Canadian postal codes only) and the order is tax exempt, mark the "Invoice Tax Exempt" **Yes** radio button; otherwise, mark the **No** radio button.
- 2. In the "Line Items" area, create a line item listing for a specific product/service being shipped/rendered in the order:

Note: For information about fields referred to in the steps below, see page 233.

- a. Select the product code type (e.g., PART #) from the drop-down list.
- b. Enter the product details in the other line item fields (**Description**, **Quantity**, **Unit Meas.**, and **Unit Cost**).
 - If the "Tax Exempt for Line Item" **HST** box displays, checkmark it if the product is tax exempt.
 - If there is a discount on the product unit cost, enter the discount amount in the **Discount on unit cost** field.
- c. Click on the **Add Line** button.
- d. When the product is listed in "Line Items included in order" area, do one of the following:
 - To add another line item, repeat steps 2a-d.
 - To continue without adding additional line items, go to step 3.
- 3. Click on the **Calculate Totals** button, and confirm that each line item total is correct.

- 4. Click on the Process Transaction button.
- 5. When the "APPROVED" or "DECLINED" response displays on the "Capture" page, the transaction is complete:
 - If you allocated loyalty points for the original debit/credit Preauthorization and you want to award the points, see page 106.
 - If did not award loyalty points for the original transaction, print/e-mail the Capture receipt now (see page 83).

4.15.4 Adding level 2/3 details: capturing a debit/credit Reauthorization

When the "Transaction Details" of a debit/credit Reauthorization are displayed on the "Capture" page, follow the steps below to add level 2/3 details to the Capture transaction.

Note: For more information about the level 2/3 details feature, see page 232.

- 1. Click on the Add Level 2/3 Details button.
- 2. When the **Destination Postal Code** field displays, do one of the following:
 - If you are shipping/rendering the order within Canada, enter the destination postal code (exclude spaces or hyphens).
 - If you are shipping/rendering the order internationally, leave the field blank so that no taxes are added to the Capture total.
- 3. Click on the **Continue** button.
- 4. Depending on the card type used to process the original Preauthorization, do one of the following:
 - If a Visa card was used, see page 71.
 - If a Mastercard was used, see page 72.
 - If an Amex card was used, see page 73.

4.15.4.1 Entering level 2/3 details: Visa cards (capturing a Reauthorization)

Follow the steps below to add Visa-specific level 2/3 details on the "Capture" page.

Note: For more information about the fields referred to in the steps below, see page 233.

- In the "Addendum 1 Details" area, enter shipping data in the fields (Buyer Name, Customer Ref. Identifier, Destination Country, Destination Postal Code, Freight Amount (inc taxes), Duty Amount, and VAT Reference Num).
 - If the "Tax Details" area displays (Canadian postal codes only) and the order is tax exempt, mark the "Invoice Tax Exempt" Yes radio button; otherwise, mark the No radio button, and enter the tax amount in the HST Amount field (must be less than 30% of original amount).
- 2. In the "Line Items" area, create a line item listing for a specific product/service being shipped/rendered in the order:
 - a. Enter the product details in the line item fields (Commodity Code, Product Code, Description, Quantity, Unit Meas., and Unit Cost).
 - If the "Tax Exempt for Line Item" HST box displays, checkmark it if the product is tax exempt.
 - If there is a discount on the product unit cost, enter the discount amount in the **Discount on unit cost** field (#.##).
 - b. Click on the **Add Line** button.
 - c. When the product is listed in "Line Items included in order" area, do one of the following:
 - To add another line item, repeat steps 2a-c.
 - To continue without adding additional line items, go to step 3.
- 3. Click on the **Calculate Totals** button, and confirm that each line item total is correct.

Note: The **Amount** field ("Transaction Details" area) should now reflect the combined amount of all line item totals, including taxes and discounts applied against the order.

- 4. Click on the Process Transaction button.
- 5. When the "APPROVED" or "DECLINED" response displays on the "Capture" page, the transaction is complete.
- 6. Print/e-mail the Capture receipt now (see page 83).

Note: Moneris Loyalty points cannot be awarded for the capture of a Reauthorization transaction.

4.15.4.2 Entering level 2/3 details: Mastercard cards (capturing a Reauthorization)

Follow the steps below to enter Mastercard-specific level 2/3 details on the "Capture" page.

Note: For information about fields referred to in the steps below, see page 233.

- 1. In the "Addendum 1 Details" area, enter shipping data in the fields (**Destination Country**, **Destination Postal Code**, **Freight Amount (inc taxes)**, **Duty Amount**, and **Supplemental Data**).
 - If the "Tax Details" area displays (Canadian postal codes only) and the order is tax exempt, mark the "Invoice Tax Exempt" **Yes** radio button; otherwise, mark the **No** radio button, and enter the tax amount in the **HST Amount** field (must be less than 30% of original amount).
- 2. In the "Line Items" area, create a line item listing for a specific product/service being shipped/rendered in the order:
 - a. Enter the product details in the line item fields (**Product Code**, **Description**, **Quantity**, **Unit Meas.**, and **Unit Cost**).
 - If the "Tax Exempt for Line Item" **HST** box displays, checkmark it if the product is tax exempt.
 - If there is a discount on the product unit cost, enter the discount amount in the **Discount on unit cost** field (#.##).
 - b. Click on the **Add Line** button.
 - c. When the product is now listed in the "Line Items included in order" area, do one of the following:
 - To add another line item, repeat steps 2a-c.
 - To continue without adding additional line items, go to step 3.
- 3. Click on the **Calculate Totals** button, and confirm that each line item total is correct.

Note: The **Amount** field ("Transaction Details" area) should now reflect the combined amount of all line item totals, including taxes and discounts applied against the order.

- 4. Click on the Process Transaction button.
- 5. When the "APPROVED" or "DECLINED" response displays on the "Capture" page, the transaction is complete.
- 6. Print/e-mail the Capture receipt now (see page 83).

Note: Moneris Loyalty points cannot be awarded for the capture of a Reauthorization transaction.

4.15.4.3 Entering level 2/3 details: Amex cards (capturing a Reauthorization)

Follow the steps below to enter Amex card-specific level 2/3 details on the "Capture" page:

- 1. In the "Customer Details" area, enter customer data in the fields (Customer Name, Street Address 1, Street Address 2, City, Province/State, Postal/Zip Code, Invoice Number, PO Number, and Customer Reference ID).
 - If the "Tax Details" area displays (Canadian postal codes only) and the order is tax exempt, mark the "Invoice Tax Exempt" **Yes** radio button; otherwise, mark the **No** radio button.
- 2. In the "Line Items" area, create a line item listing for a specific product/service being shipped/rendered in the order:

Note: For information about fields referred to in the steps below, see page 233.

- a. Select the product code type (e.g., PART #) from the drop-down list.
- b. Enter the product details in the other line item fields (**Description**, **Quantity**, **Unit Meas.**, and **Unit Cost**).
 - If the "Tax Exempt for Line Item" **HST** box displays, checkmark it if the product is tax exempt.
 - If there is a discount on the product unit cost, enter the discount amount in the **Discount on unit cost** field (#.##).
- c. Click on the **Add Line** button.
- d. When the product is listed in "Line Items included in order" area, do one of the following:
 - To add another line item, repeat steps 2a-d.
 - To continue without adding additional line items, go to step 3.
- 3. Click on the **Calculate Totals** button, and confirm that each line item total is correct.

Note: The **Amount** field ("Transaction Details" area) should now reflect the combined amount of all line item totals, including taxes and discounts applied against the order.

- 4. When the "APPROVED" or "DECLINED" response displays on the "Capture" page, the transaction is complete.
- 5. Print/e-mail the Capture receipt now (see page 83).

Note: Moneris Loyalty points cannot be awarded for the capture of a Reauthorization transaction.

4.15.5 Adding level 2/3 details: Refund

When the "Transaction Details" of the debit/credit transaction to be reversed (refunded) are displayed on the "Refund" page, follow the steps below to add level 2/3 details (product and taxes) to the Refund transaction.

Note: For more information about the level 2/3 details feature, see page 232.

- 1. Click on the Add Level 2/3 Details button.
- 2. When the **Destination Postal Code** field displays, do one of the following:
 - If you are refunding an order that was originally shipped/rendered within Canada, enter the original destination postal code (exclude spaces or hyphens).
 - If you are refunding an order that was originally shipped/rendered internationally, leave the field blank so that no taxes are added to the Refund total.
- 3. Click on the **Continue** button.
- 4. Depending on the card type used to process the original Capture, do one of the following:
 - If a Visa card was used, see page 75.
 - If a Mastercard was used, see page 76.
 - If an Amex card was used, see page 77.

4.15.5.1 Entering level 2/3 details: Visa cards (Refund)

Follow the steps below to add Visa-specific level 2/3 details on the "Refund" page.

Note: For more information about the fields referred to in the steps below, see page 233.

- 1. In the "Addendum 1 Details" area, enter the original order's shipping data in the fields (Buyer Name, Customer Ref. Identifier, Destination Country, Destination Postal Code, Freight Amount (inc taxes), Duty Amount, and VAT Reference Num).
 - If the "Tax Details" area displays (Canadian postal codes only) and the original order was tax exempt, mark the "Invoice Tax Exempt" Yes radio button; otherwise, mark the No radio button, and enter the original order's tax amount in the HST Amount field (must be less than 30% of original amount).
- 2. In the "Line Items" area, create a line item listing for a specific product/service being refunded from the original order:
 - a. Enter the product details in the line item fields (Commodity Code, Product Code, Description, Quantity, Unit Meas., and Unit Cost).
 - If the "Tax Exempt for Line Item" **HST** box displays, checkmark it if the product was tax exempt in the original order.
 - If there was a discount on the original order's product unit cost, enter the discount amount in the **Discount on unit cost** field (#.##).
 - b. Click on the **Add Line** button.
 - c. When the product is listed in "Line Items included in order" area, do one of the following:
 - To add another line item, repeat steps 2a-c.
 - To continue without adding additional line items, go to step 3.
- 3. Click on the **Calculate Totals** button, and confirm that each line item total is correct.

- 4. Click on the Process Transaction button.
- 5. When the "APPROVED" or "DECLINED" response displays on the "Refund" page, the transaction is complete:
 - If you want to remove any Moneris loyalty points awarded for the original transaction, see page 117.
 - If did not award loyalty points for the original transaction, print/e-mail the Refund receipt now (see page 83).

4.15.5.2 Entering level 2/3 details: Mastercard cards (Refund)

Follow the steps below to enter Mastercard-specific level 2/3 details on the "Refund" page.

Note: For information about fields referred to in the steps below, see page 233.

- 1. In the "Addendum 1 Details" area, enter the original order's shipping data in the fields (Destination Country, Destination Postal Code, Freight Amount (inc taxes), Duty Amount, and Supplemental Data).
 - If the "Tax Details" area displays (Canadian postal codes only) and the original order was tax exempt, mark the "Invoice Tax Exempt" Yes radio button; otherwise, mark the No radio button, and enter the original order's tax amount in the HST Amount field (must be less than 30% of original amount).
- 2. In the "Line Items" area, create a line item listing for a specific product/service being refunded from the original order:
 - a. Enter the product details in the line item fields (**Product Code**, **Description**, **Quantity**, **Unit Meas.**, and **Unit Cost**).
 - If the "Tax Exempt for Line Item" **HST** box displays, checkmark it if the product was tax exempt in the original order.
 - If there was a discount on the original order's product unit cost, enter the discount amount in the **Discount on unit cost** field (#.##).
 - b. Click on the Add Line button.
 - c. When the product is now listed in the "Line Items included in order" area, do one of the following:
 - To add another line item, repeat steps 2a-c.
 - To continue without adding additional line items, go to step 3.
- 3. Click on the **Calculate Totals** button, and confirm that each line item total is correct.

- 4. Click on the Process Transaction button.
- 5. When the "APPROVED" or "DECLINED" response displays on the "Refund" page, the transaction is complete:
 - If you want to remove any Moneris loyalty points awarded for the original transaction, see page 117.
 - If did not award loyalty points for the original transaction, print/e-mail the Refund receipt now (see page 83).

4.15.5.3 Entering level 2/3 details: Amex cards (Refund)

Follow the steps below to enter Amex-specific level 2/3 details on the "Refund" page:

- 1. In the "Customer Details" area, enter customer data in the fields (Customer Name, Street Address 1, Street Address 2, City, Province/State, Postal/Zip Code, Invoice Number, PO Number, and Customer Reference ID).
 - If the "Tax Details" area displays (Canadian postal codes only) and the order is tax exempt, mark the "Invoice Tax Exempt" **Yes** radio button; otherwise, mark the **No** radio button.
- 2. In the "Line Items" area, create a line item listing for a specific product/service being refunded from the original order:

Note: For information about fields referred to in the steps below, see page 233.

- a. Select the product code type (e.g., PART #) from the drop-down list.
- b. Enter the product details in the other line item fields (**Description**, **Quantity**, **Unit Meas.**, and **Unit Cost**).
 - If the "Tax Exempt for Line Item" **HST** box displays, checkmark it if the product was tax exempt in the original order.
 - If there was a discount on the original order's product unit cost, enter the discount amount in the **Discount on unit cost** field (#.##).
- c. Click on the **Add Line** button.
- d. When the product is listed in "Line Items included in order" area, do one of the following:
 - To add another line item, repeat steps 2a-d.
 - To continue without adding additional line items, go to step 3.
- 3. Click on the **Calculate Totals** button, and confirm that each line item total is correct.

- 4. Click on the Process Transaction button.
- 5. When the "APPROVED" or "DECLINED" response displays on the "Refund" page, the transaction is complete:
 - If you want to remove any Moneris loyalty points awarded for the original transaction, see page 117.
 - If did not award loyalty points for the original transaction, print/e-mail the Refund receipt now (see page 83).

4.15.6 Cardholder prompts: iPP320 PINpad

When "Please follow prompts on pinpad" displays on the transaction page, do the following:

- 1. Hand the iPP320 PINpad to the cardholder.
- 2. The cardholder responds to any prompt that displays on the iPP320 PINpad.

Note: Potential prompts (and the actions to take for each) are listed in order of appearance in the table below. Only some of the listed prompts will appear for any one transaction.

Cardholder prompt	Cardholder action
SWIPE, TAP OR INSERT CARD OT SWIPE OR INSERT CARD OT SWIPE CARD	Enters their card on the iPP320 PINpad (for options, see pages 20 to 21).
SELECT LANGUAGE	Selects the display language:
ENGL FRAN	To select English, presses F1 (ENG).
	To select French, presses F4 (FRAN).
SELECT <application name=""> YES NO</application>	 Selects the card application: To select the displayed application, presses F1 (YES). To view the next available application, presses F4 (NO).
<application name=""> -OK? YES NO</application>	Presses F1 (YES) to use the displayed application.
<transaction NAME> \$#.##-OK?</transaction 	Presses the green key to confirm the displayed amount.
I PRE-AUTHORIZE UP TO \$#.##-OK?	Presses the green key to confirm the displayed amount.

This table continues on the next page.

Cardholder prompt	Cardholder action	
TIP OPTIONS	Selects a tip type:	
\$ % NONE	To enter a dollar amount, presses F1(\$).	
	To enter a percentage, presses F2 (%)	
	To bypass entering a tip, presses F4 (NONE).	
ENTER TIP AMOUNT \$0.00	Keys in an amount, and presses the green Ney.	
TIP PERCENTAGE	Selects a percentage type:	
%AA %BB OTHR	 To add a preset tip percentage, presses F1 (AA%) or F2 (BB%). 	
	 To add a different precentage, presses F4 (OTHR). 	
ENTER TIP %	Enters a tip percentage, and presses the green key.	
<transaction NAME> \$#.##-OK?</transaction 	Presses the green key to confirm the displayed transaction amount.	
ун.нн ОК:	Note: If the cardholder wants to change the tip amount, they press the yellow key, and re-enter the tip when prompted.	
SELECT ACCOUNT	Selects a debit account:	
CHQ SAV	To select "chequing", presses F1 (CHQ).	
	To select "savings", presses F4 (SAV).	
ENTER PIN & OK	Keys in their Personal Identification Number (PIN) and presses the green key.	
PLEASE WAIT	Waits while the transaction is processed.	
APPROVED	Removes their card from chip reader.	
THANK YOU REMOVE CARD	Note: The iPP320 PINpad beeps until the card is removed.	
APPROVED THANK YOU OBTAIN CARD	Retrieves their card.	
WELCOME/BONJOUR	Returns the iPP320 PINpad to you (go to step 3).	

4 Virtual terminal

- 3. Accept the iPP320 from the cardholder.
 - If "WELCOME/BONJOUR" is not currently displayed on the iPP320 PINpad, press the green key until "WELCOME/BONJOUR" displays.
- 4. Refer back to the financial transaction procedure (continue at the step "When the "APPROVED" or "DECLINED" response displays...").

4.15.7 Cardholder prompts: iPP320 PINpad (manual card entry)

When "PURCHASE \$#.##-OK?" displays on the iPP320 PINpad, do the following:

- 1. Hand the iPP320 PINpad to the cardholder.
- 2. The cardholder responds to any prompt that displays on the iPP320 PINpad.

Note: Potential prompts (and the actions to take for each) are listed in order of appearance in the table below. Only some of the listed prompts will display for any one transaction.

Cardholder prompt	Cardholder action
PURCHASE \$#.##-OK?	Presses the green key to confirm the displayed amount.
TIP OPTIONS	Selects a tip type:
\$ % NONE	To enter a dollar amount, presses F1(\$).
	To enter a percentage, presses F2 (%)
	To bypass entering a tip, presses F4 (NONE).
ENTER TIP AMOUNT \$0.00	Keys in an amount, and presses the green lesses.
TIP PERCENTAGE	Selects a percentage type:
%AA %BB OTHR	 To add a preset tip percentage, presses F1 (AA%) or F2 (BB%).
	 To add a different precentage, presses F4 (OTHR).
ENTER TIP %	Enters a tip percentage, and presses the green 🔲 key.
PURCHASE \$#.##-OK?	Presses the green key to confirm the displayed transaction amount.
	Note: If the cardholder wants to change the tip amount, they press the yellow key, and re-enter the tip when prompted.
PLEASE WAIT	Waits while the transaction is processed.
APPROVED THANK YOU OBTAIN CARD	Retrieves their card.
WELCOME/BONJOUR	Returns the iPP320 PINpad to you (go to step 3).

- 3. Accept the iPP320 from the cardholder.
 - If "WELCOME/BONJOUR" is not currently displayed on the iPP320 PINpad, press the green key until "WELCOME/BONJOUR" displays.
- 4. When the "APPROVED" or "DECLINED" response displays on the "Purchase" page, the transaction is complete:
 - If Moneris Loyalty is enabled and you want to award loyalty points, see page 100.
 - If Moneris Loyalty is not enabled or it is but you want to bypass awarding points, print/e-mail the transaction receipt now (see page 83).

5 Printing/e-mailing a receipt

Once you submit a transaction and the Merchant Resource Center displays the host response "APPROVED" or "DECLINED" (or "APPROVED"/"DECLINED") indicating the transaction has been processed, follow the steps below to print and/or e-mail the transaction receipt.

Note: If you ever want to view, print, or e-mail a receipt after you have closed the transaction page, access the transaction's "Order History" (see page 88).

To print the transaction receipt:

- 1. In the "Action Items" area on the host response page, click on a **Print Receipt #x#** (or **Receipt #x#**) button.
- 2. When the print dialog box opens, select the printer from which you want to print the transaction receipt.
- 3. Click on the **Print** button.
- 4. The operation is complete. (To print another receipt, repeat steps 1-3.)
- 5. If the receipt includes any of these cardholder validation method (CVM) statements, take the appropriate action depending on the context:

CVM statement	Action required
"SIGNATURE Cardholder will pay issuer above amount pursuant to Cardholder Agreement"	Cardholder signature is required.
"NO SIGNATURE TRANSACTION"	No cardholder signature is required.
"VERIFIED BY PIN"	No cardholder signature is required.

To e-mail the transaction receipt:

- 1. In the "Action Items" area on the host response page, click on the **Send Email Receipt** (or **Email Receipt**) button.
- 2. When the e-mail window opens, do the following:
 - a. In the **Email Address** field, enter the e-mail address to which you want to send the transaction receipt.
 - b. Click on the **Send Receipt & Close** button.
- 3. The operation is complete. (To send another receipt, repeat steps 1-2.)

6 Order history

The Merchant Resource Center assigns an "Order History" page to every financial transaction for which the host response is "APPROVED" or "DECLINED".

This "Order History" page displays detailed information (e.g., amount, date, time, etc.) about the transaction, including information about any follow-on transaction or associated transaction that has been performed subsequently (see *Areas on the "Order History" page* below).

To access a transaction's "Order History" page, see page 88.

6.1 Areas on the "Order History" page

The "Order History" page may be divided into several areas depending on the transaction and payment type:

- Transaction type details (see page 85).
- Tip information details (see page 86).
- eFraud details (see page 86).
- Action items details (see page 87).

6.1.1 Transaction type details: "Order History" page

The "Transaction type" area on a transaction's "Order History" page displays details about the transaction (refer to the table below for descriptions about data in specific fields).

To access a transaction's "Order History" page, see page 88.

Field	Description	
Amount	Transaction amount including any tip.	
Approval Code	Authorization code.	
Card Number	Card account number.	
Card Type	Card brand (or "Cash").	
Clerk	Username of the user who performed the transaction.	
Crypt Type	Electronic commerce indicator.	
Customer Code	User-entered value. Optional.	
Customer ID	User-entered value. Optional.	
Date/Time	Date/time of the transaction (Month DD YYYY HH:MM).	
Expiry Date	Card expiry date (MMYY).	
Foreign Currency Amount	The non-CAD amount for which the transaction was processed.	
Invoice Number	User-entered value. Optional.	
Message	Host response (e.g., "APPROVED" or "DECLINED").	
Order ID	Unique Merchant Resource Center transaction identifier.	
Response	Transaction response code.	
Sequence Number	Moneris host identifier (e.g., If "610123450010690030" is the number, then "61012345" is the ID of the iPP320 PINpad used to capture the card data. If the number starts with "66", it means the card data were captured via keyed entry on the Merchant Resource Center.	
Transaction Type	Transaction type (e.g., Purchase, Refund, Void, etc.).	
Wallet Type	Cloud wallet (see page 186) or Vault (see page 147) transaction identifier.	

6.1.2 Tip information details: "Order History" page

The "Tip Information" area on a transaction's "Order History" page displays tip details about the transaction (refer to the table below for descriptions about data in specific fields).

To access a transaction's "Order History" page, see page 88.

Field	Description	
Pre-Tip Amount	Transaction amount excluding the tip.	
Tip Amount	Tip amount.	

6.1.3 eFraud details: "Order History" page

The "eFraud details" area on a transaction's "Order History" page displays validation responses to any anti-fraud data submitted in the transaction (refer to the table below for descriptions about data in specific fields).

To access a transaction's "Order History" page, see page 88.

Field	Description
AVS Result	Indicates address verification service (AVS) validation result if verification is performed at the time the transaction is processed. The result indicates whether the street number, street name, or zip code data match the data that the issuer has on file (see page 235).
CVD Result	Indicates card verification digits(CVD) validation result if verification is performed at the time the transaction is processed. This result indicates whether the 3 or 4-digit CVD code (usually printed on the back of the card on the signature line) matches the code that the issuer has on file.
CVV Result	(Verified by Visa) - Indicates the issuer's response regarding whether the CAVV value that you provide is fully authenticated and valid. The CAVV value may be indicative of the data (e.g., a password) entered by the cardholder during an e-commerce transaction. The authentication data are sent to the card issuer independent of the Merchant Resource Center.

6.1.4 Action items: "Order History" page

Buttons displaying in the "Action Items" area of a transaction's "Order History" page indicate potential follow-on transactions and/or access to other transaction details.

- To initiate a follow-on transaction or access other transaction details (e.g., Refund, Reauth, or Void), click on the appropriate button (refer to the table below for descriptions about activities that are initiated when you click on a button).
- To access a transaction's "Order History" page, see page 88.

7 1 - 9 - 7 1 - 9		
Button	Description	
Add Loyalty	Award loyalty points for a preceding gift/loyalty or cash transaction.	
Associated	Display the "Order History" page listing a gift/loyalty transaction and one or more other transactions (e.g., debit/credit, gift/loyalty, or cash).	
Capture	Initiate a debit/credit or loyalty Capture transaction.	
Email Receipt	E-mail a transaction receipt.	
Level 2/3 Details	Display level 2/3 transaction details (tax and product data) if they were submitted in the transaction.	
Loyalty	Award, allocate, or remove loyalty points depending on the preceding (associated) debit/credit transaction.	
Print Receipt - #x#	Print a transaction receipt.	
Reauth	Initiate a debit/credit Reauthorization transaction.	
Receipt - #x#	Print a transaction receipt.	
Refund	Initiate a debit/credit Refund or gift Refund transaction.	
Send Email Receipt	E-mail a transaction receipt.	
Void	Initiate a Void transaction (debit/credit or gift/loyalty).	

6.2 Accessing a transaction's "Order History" page

Follow the steps below to access a transaction's "Order History" page.

Note: For more information about the "Order History" page, see page 84.

- 1. Retrieve the transaction by generating the appropriate report (see page 163).
- 2. When the desired transaction is listed in the "Transactions List" area, click on the transaction's **Order ID** hyperlink.
- 3. When the transaction's "Order History" page displays, the operation is complete.
- 4. If you want to print/e-mail a transaction receipt, do the following:

To print a transaction receipt:

- a. In the "Action Items" area, click on a **Print Receipt #x#** button.
- b. When the print dialog box opens, select the printer from which you want to print the transaction receipt.
- c. Click on the **Print** button.
- d. The operation is complete. (To print another receipt, repeat steps a-c.)

To e-mail the transaction receipt:

- a. In the "Action Items" area, click on the **Send Email Receipt** button.
- b. Wait for the e-mail window to open.
- c. In the **Email Address** field, enter the e-mail address to which you want to send the transaction receipt.
- d. Click on the **Send Receipt & Close** button.
- e. The operation is complete. (To send another receipt, repeat steps a-d.)

7 Moneris Gift/Loyalty card programs

The Moneris Gift/Loyalty program allows you to offer your customers card-based programs that are processed through the Merchant Resource Center.

Gift card program

The gift card program allows you to offer your customers stored-value gift cards for predefined dollar values as well as variable-value cards and rechargeable cards. This program is available for small businesses and can be customized for national chains.

• For full listing of gift card transactions that you can initiate directly from the Merchant Resource Center menu bar (see page 7), refer to the table below.

Transaction type	See procedure on:
Purchase	page 91
Void	page 94
Refund	page 95
Independent Refund	page 96
Coupon/Voucher Redemption	page 119
Activate card	page 122
Deactivate card	page 125
Balance Inquiry	page 128

Loyalty card program

Loyalty card program: allows you to reward customer loyalty by awarding points based on the dollar value of the purchases a cardholder makes. This program is available for small businesses and can be customized for national chains.

• For full listing of loyalty card transactions that you can process from the Merchant Resource Center, refer to the table below:

Transaction type	See procedure on:
Purchase	page 99
Preauthorization	page 105
Capture	page 106
Redemption (dollars)	page 107
Redemption (points)	page 110
Void	page 113
Refund	page 116
Coupon/Voucher Redemption	page 119
Activate card	page 122
Deactivate card	page 125
Balance Inquiry	page 128

7.1 Purchase with gift card

Gift card sale of goods and services.

• For a listing of supported card entry methods, including the associated procedures describing how to use them to perform this transaction, refer to the table below:

7

Card entry method	See procedure on:
unencrypted MSR	page 92
keyed entry	page 93

/

7.1.1 Purchase with gift card: unencrypted MSR

Follow the steps below to perform a Purchase with a gift card by using an unencrypted magnetic stripe reader to capture the card data.

- 1. On the menu bar, click on **Gift/Loyalty** > **Purchase**.
- 2. Wait for the "Purchase" page to display.
- 3. From the "Transaction Type" drop-down list, select **Dollar Value Purchase/Redemption**.
- 4. In the **Total Amount** field, enter the Purchase amount (#.##).
- 5. In the **Customer ID** field, optionally enter a Customer ID.
- 6. Click on the **Next** button.
- 7. In the "Payment Method" area, select Gift Card MSR from the drop-down list.
- 8. In the "Gift Card Payment Step 1" area, do the following:

Note: For information about fields referred to in the steps below, see page 221.

- a. In Order ID field, optionally enter an Order ID.
- b. In the **Customer ID** field, optionally enter a Customer ID.
- c. Do one of the following:
 - To view the available funds/status of the gift card, see page 131.
 - To proceed with the gift Purchase, go to step d.
- d. Click on the Swipe Gift Card button.
- 9. When "Please swipe gift card now" displays on the "Purchase" page, swipe the gift card on the unencrypted magnetic stripe reader.
- 10. When the CVC field displays, enter the card validation code.
 - If any other data field displays, enter the required data (consult your manager if you are unsure about what to enter).
- 11. When the "APPROVED" or "DECLINED" response displays on the "Purchase" page, the transaction is complete:
 - If a "Balance Due: \$#.##" is indicated, see page 137.
 - If a "Balance Due: \$0.00" (zero dollars) is indicated, do one of the following:
 - If Moneris Loyalty is enabled and you want to award loyalty points, see page 104.
 - If Moneris Loyalty is not enabled or it is but you want to bypass awarding points, print/e-mail the transaction receipt now (see page 83).

7.1.2 Purchase with gift card: keyed entry

Follow the steps below to perform a Purchase with a gift card by manually entering (keying) the card data in the Merchant Resource Center fields.

7

- 1. On the menu bar, click on Gift/Loyalty > Purchase.
- 2. Wait for the "Purchase" page to display.
- 3. From the "Transaction Type" drop-down list, select **Dollar Value Purchase/Redemption**.
- 4. In the Total Amount field, enter the Purchase amount (#.##).
- 5. In the **Customer ID** field, optionally enter a Customer ID.
- 6. Click on the **Next** button.
- 7. In the "Payment Method" area, select Gift Card Keyed from the drop-down list.
- 8. In the "Gift Card Payment Step 1" area, do the following:

Note: For information about fields referred to in the steps below, see page 221.

- a. In Order ID field, optionally enter an Order ID.
- b. In the Customer ID field, optionally enter a Customer ID.
- c. In the **Gift Card Number** field, enter the gift card number.
- d. Do one of the following:
 - To view the available funds/status of the gift card, see page 131.
 - To continue with the gift Purchase, go to step 9.
- 9. Click on the **Next** button.
- 10. When the CVC field displays, enter the card validation code.
 - If any other data field displays, enter the required data (consult your manager if you are unsure about what to enter).
- 11. Click on the Process button.
- 12. When the "APPROVED" or "DECLINED" response displays on the "Purchase" page, the transaction is complete:
 - If a "Balance Due: \$#.##" is indicated, see page 137.
 - If a "Balance Due: \$0.00" (zero dollars) is indicated, do one of the following:
 - If Moneris Loyalty is enabled and you want to award loyalty points, see page 104.
 - If Moneris Loyalty is not enabled or it is but you want to bypass awarding points, print/e-mail the transaction receipt now (see page 83).

7

7.2 Void with gift card

Follow the steps below to reverse (void) an open-batch gift card Purchase that is referenced on the Merchant Resource Center (restores gift dollars to the card).

- 1. On the menu bar, click on Gift/Loyalty > Void.
- 2. Wait for the "Void" page to display.
- 3. In the **Order ID** field, enter the Order ID of the original transaction that you want to reverse.

Note: If you only have a partial Order ID, mark the **begins with** or the **ends with** radio button.

- 4. Click on the Locate Transaction button.
- 5. Wait for the "Void" page to display.
- 6. In the "Transaction List" area, click on the **Void** button beside the transaction that you want to reverse.
- 7. When the "Transaction Details" area displays, click on the **Process** button.
- 8. When the "APPROVED" response displays, the transaction is complete.
- 9. Print/e-mail the transaction receipt now (see page 83).

Note: If you awarded loyalty points for the original gift Purchase that you have just voided, do a loyalty Void now to remove the awarded points (see page 114).

7.3 Refund with gift card

Follow the steps below to reverse a closed-batch gift card transaction that is referenced on the Merchant Resource Center (restores gift dollars to the card).

7

- 1. On the menu bar, click on Gift/Loyalty > Refund.
- 2. Wait for the "Refund" page to display.
- 3. In the **Order ID** field, enter the Order ID of the original transaction that you want to reverse.

Note: If you only have a partial Order ID, mark the **begins with** or the **ends with** radio button.

- 4. Click on the Locate Transaction button.
- 5. Wait for the "Refund" page to display.
- 6. In the "Transaction List" area, click on the **Refund** button beside the transaction that you want to reverse.
- 7. In the "Transaction Details" area, do the following:

Note: For information about fields referred to in the steps below, see page 221.

- a. In the CVC field, enter the card validation code.
 - If any other data field displays, enter the required data (consult your manager if you are unsure about what to enter).
- 8. Click on the **Process** button.
- 9. When the "APPROVED" response displays, the transaction is complete.
- 10. Print/e-mail the transaction receipt now (see page 83).

Note: If you awarded loyalty points on the original gift Purchase that you have just refunded, do a loyalty Refund now to remove the awarded points (see page 118).

7

7.4 Independent Refund with gift card

Reverse (refund) a gift card transaction that is unreferenced on the Merchant Resource Center.

For a listing of supported card entry methods, including the associated procedures describing how to use them to perform this transaction, refer to the table below:

Card entry method	See procedure on:
unencrypted MSR	page 97
keyed entry	page 98

7.4.1 Independent Refund with gift card: unencrypted MSR

Follow the steps below to reverse (refund) a gift card transaction that is unreferenced on the Merchant Resource Center. You will use an unencrypted magnetic stripe reader to capture the card data.

- 1. On the menu bar, click on Gift/Loyalty > Independent Refund.
- 2. Wait for the "Independent Refund" page to display.
- 3. In the "Read Card" area, select Mag Swipe Reader from the drop-down list.
- 4. In the "Independent Refund Details Step 1" area, do the following:

Note: For information about fields referred to in the steps below, see page 221.

- a. In the Order ID field, optionally enter an Order ID.
- b. In the **Customer ID** field, optionally enter a Customer ID.
- 5. Click on the **Swipe Card** button.
- 6. When "Please swipe card now" displays on the "Independent Refund" page, swipe the card on the unencrypted magnetic stripe reader.
- 7. When the "Payment Details Step 2" area displays, do the following:
 - a. In the CVC field, enter the card validation code.
 - b. In the **Reference Number** field, enter the reference number of the original gift Purchase transaction that you want to reverse.
 - c. In the **Refund Amount** field, enter the amount (#.##) of the original transaction that you want to reverse.
 - If any other data field displays, enter the required data (consult your manager if you are unsure about what to enter).
- 8. Click on the **Process** button.
- 9. When the "APPROVED" or "DECLINED" response displays, the transaction is complete.
- 10. Print/e-mail the transaction receipt now (see page 83).

7.4.2 Independent Refund with gift card: keyed entry

Follow the steps below to reverse (refund) a gift card transaction that is not referenced on the Merchant Resource Center. You will manually enter (key) the card data in the Merchant Resource Center fields.

- 1. On the menu bar, click on Gift/Loyalty > Independent Refund.
- 2. Wait for the "Independent Refund" page to display.
- 3. In the "Read Card" area, select **Keyed Entry** from the drop-down list.
- 4. In the "Independent Refund Details Step 1" area, do the following:

Note: For information about fields referred to in the steps below, see page 221.

- a. In the Order ID field, optionally enter an Order ID.
- b. In the Customer ID field, optionally enter a Customer ID.
- c. In the Card Number field, enter the gift card number.
- d. Click on the Next button.
- 5. When the "Payment Details Step 2" area displays, do the following:
 - a. In the CVC field, enter the card validation code.
 - b. In the **Reference Number** field, enter the reference number of the original gift Purchase transaction that you want to reverse.
 - c. In the **Refund Amount** field, enter the amount (#.##) of the original transaction that you want to reverse.
 - If any other data field displays, enter the required data (consult your manager if you are unsure about what to enter).
 - d. Click on the Process button.
- 6. When the "APPROVED" or "DECLINED" response displays, the transaction is complete.
- 7. Print/e-mail the transaction receipt now (see page 83).

7.5 Loyalty Purchase: awarding loyalty points

You award loyalty points by performing a loyalty Purchase as a follow-on transaction to an associated debit/credit, gift, or cash Purchase or equivalent transaction.

 For a full listing of loyalty Purchase types and associated procedures, refer to the table below.

7

Loyalty Purchase as follow-on to:	See procedure on:
debit/credit Purchase	page 100
debit/credit Purchase - used for gift/loyalty card activation	page 101
debit/credit Voice-Authorization Advice	page 102
cash Purchase	page 103
gift Purchase	page 104
debit/credit Preauthorization	page 105
Capture	page 106
Redemption (dollars)	page 107
Redemption (points)	page 110
Void	page 113
Refund	page 116
Coupon/Voucher Redemption	page 119
Activate card	page 122
Deactivate card	page 125
Balance Inquiry	page 128

7.5.1 Loyalty Purchase: awarding loyalty points for associated debit/credit Purchase

When the "APPROVED" response displays on the "Purchase" page of a debit/credit Purchase that you have just processed (see page 24), follow the steps below to do a loyalty Purchase and award loyalty points.

- 1. In the "Action Items" area, click on the Loyalty button.
- 2. Wait for the loyalty "Purchase" page to display.
- 3. In the "Read Loyalty Card" area, do the following:

Note: For information about fields referred to in the steps below, see page 221.

- a. In Order ID field, optionally enter an Order ID.
- b. In the Customer ID field, optionally enter a Customer ID.
- 4. Capture the loyalty card data:

To swipe the loyalty card on an unencrypted magnetic stripe reader:

- a. From the drop-down list, select Mag Swipe Reader.
- b. Click on the **Swipe Card** button.
- c. When "Please swipe loyalty card now" displays on the "Purchase" page, swipe the loyalty card on the unencrypted magnetic stripe reader.

- a. From the drop-down list, select **Keyed Entry**.
- b. In the **Loyalty Card Number** field, enter the loyalty card number.
- c. Click on the **Next** button.
 - If one or more amount fields display (e.g., **Benefit Amount** and/or **Pre-Tax Amount**), enter the appropriate amount (#.##) for which points should be awarded. Consult your manager if you are unsure about what to enter.
 - If any other data field displays (e.g., **Bonus Code**), enter the required data (e.g., you may be required to award bonus points). Consult your manager if you are unsure about what to enter.
- 5. Click on the **Process** button.
- 6. When the "APPROVED" response displays (in the "Loyalty Response" area on the "Purchase" page), the transaction is complete.
- 7. Print/e-mail the transaction receipt now (see page 83).

7.5.2 Loyalty Purchase: awarding loyalty points for associated debit/credit Purchase (gift/loyalty card Activation)

When the "APPROVED" response displays (in the "Payment Response" area) on the "Activate" page (see page 122), follow the steps below to do a loyalty Purchase and award loyalty points for the debit/credit Purchase that you processed to completed the gift card activation.

- 1. In the "Action Items" area, click on the Loyalty button.
- 2. Wait for the loyalty "Purchase" page to display.
- 3. In the "Read Loyalty Card" area, do the following:

Note: For information about fields referred to in the steps below, see page 221.

- a. In Order ID field, optionally enter an Order ID.
- b. In the **Customer ID** field, optionally enter a Customer ID.
- 4. Capture the loyalty card data:

To swipe the loyalty card on an unencrypted magnetic stripe reader:

- a. From the drop-down list, select Mag Swipe Reader.
- b. Click on the **Swipe Card** button.
- c. When "Please swipe loyalty card now" displays on the "Purchase" page, swipe the loyalty card on the unencrypted magnetic stripe reader.

- a. From the drop-down list, select Keyed Entry.
- b. In the Loyalty Card Number field, enter the loyalty card number.
- c. Click on the Next button.
 - If one or more amount fields display (e.g., **Benefit Amount** and/or **Pre-Tax Amount**), enter the appropriate amount (#.##) for which points should be awarded. Consult your manager if you are unsure about what to enter.
 - If any other data field displays (e.g., **Bonus Code**), enter the required data (e.g., you may be required to award bonus points). Consult your manager if you are unsure about what to enter.
- 5. Click on the **Process** button.
- 6. When the "APPROVED" response displays (in the "Loyalty Response" area on the "Purchase" page), the transaction is complete.
- 7. Print/e-mail the transaction receipt now (see page 83).

7

7.5.3 Loyalty Purchase: awarding loyalty points for associated debit/credit Voice Authorization-Advice

When the "APPROVED" response displays on the "Voice Authorization/Advice" page of a debit/credit Voice Authorization-Advice transaction that you have just processed (see page 47), follow the steps below to do a loyalty Purchase and award loyalty points.

- 1. In the "Action Items" area, click on the Loyalty button.
- 2. Wait for the loyalty "Purchase" page to display.
- 3. In the "Read Loyalty Card" area, do the following:

Note: For information about fields referred to in the steps below, see page 221.

- a. In Order ID field, optionally enter an Order ID.
- b. In the Customer ID field, optionally enter a Customer ID.
- 4. Capture the loyalty card data:

To swipe the loyalty card on an unencrypted magnetic stripe reader:

- a. From the drop-down list, select Mag Swipe Reader.
- b. Click on the **Swipe Card** button.
- c. When "Please swipe loyalty card now" displays on the "Purchase" page, swipe the loyalty card on the unencrypted magnetic stripe reader.

- a. From the drop-down list, select **Keyed Entry**.
- b. In the **Loyalty Card Number** field, enter the loyalty card number.
- c. Click on the **Next** button.
 - If one or more amount fields display (e.g., **Benefit Amount** and/or **Pre-Tax Amount**), enter the appropriate amount (#.##) for which points should be awarded. Consult your manager if you are unsure about what to enter.
 - If any other data field displays (e.g., **Bonus Code**), enter the required data (e.g., you may be required to award bonus points). Consult your manager if you are unsure about what to enter.
- 5. Click on the **Process** button.
- 6. When the "APPROVED" response displays (see the "Loyalty Response" area on the "Purchase" page), the transaction is complete.
- 7. Print/e-mail the transaction receipt now (see page 83).

7.5.4 Loyalty Purchase: awarding loyalty points for associated cash Purchase

When the "APPROVED" response displays on the "Purchase" page of a cash Purchase transaction that you have just processed (see page 31), follow the steps below to do a loyalty Purchase and award loyalty points.

- 1. In the "Action Items" area, click on the Loyalty button.
- 2. Wait for the loyalty "Purchase" page to display.
- 3. In the "Read Loyalty Card" area, do the following:

Note: For information about fields referred to in the steps below, see page 221.

- a. In Order ID field, optionally enter an Order ID.
- b. In the Customer ID field, optionally enter a Customer ID.
- 4. Capture the loyalty card data:

To swipe the loyalty card on an unencrypted magnetic stripe reader:

- a. From the drop-down list, select Mag Swipe Reader.
- b. Click on the **Swipe Card** button.
- c. When "Please swipe loyalty card now" displays on the "Purchase" page, swipe the loyalty card on the unencrypted magnetic stripe reader.

- a. From the drop-down list, select **Keyed Entry**.
- b. In the Loyalty Card Number field, enter the loyalty card number.
- c. Click on the **Next** button.
 - If one or more amount fields display (e.g., **Benefit Amount** and/or **Pre-Tax Amount**), enter the appropriate amount (#.##) for which points should be awarded. Consult your manager if you are unsure about what to enter.
 - If any other data field displays (e.g., Bonus Code), enter the required data (e.g., you may be required to award bonus points). Consult your manager if you are unsure about what to enter.
- 5. Click on the **Process** button.
- 6. When the "APPROVED" response displays (refer to the "Loyalty Response" area on the "Purchase" page), the transaction is complete.
- 7. Print/e-mail the transaction receipt now (see page 83).

7.5.5 Loyalty Purchase: awarding loyalty points for associated gift Purchase

When the "APPROVED" response displays on the "Purchase" page of a gift Purchase transaction that you have just processed, follow the steps below to do a loyalty Purchase and award loyalty points.

- 1. In the "Action Items" area, click on the **Add Loyalty** button.
- 2. Wait for the loyalty "Purchase" page to display.
- 3. In the "Read Loyalty Card" area, do the following:

Note: For information about fields referred to in the steps below, see page 221.

- a. In Order ID field, optionally enter an Order ID.
- b. In the **Customer ID** field, optionally enter a Customer ID.
- 4. Capture the loyalty card data:

To swipe the loyalty card on an unencrypted magnetic stripe reader:

- a. From the drop-down list, select Mag Swipe Reader.
- b. Click on the **Swipe Card** button.
- c. When "Please swipe loyalty card now" displays on the "Purchase" page, swipe the loyalty card on the unencrypted magnetic stripe reader.

- a. From the drop-down list, select **Keyed Entry**.
- b. In the **Loyalty Card Number** field, enter the loyalty card number.
- c. Click on the **Next** button.
 - If one or more amount fields display (e.g., **Benefit Amount** and/or **Pre-Tax Amount**), enter the appropriate amount (#.##) for which points should be awarded. Consult your manager if you are unsure about what to enter.
 - If any other data field displays (e.g., **Bonus Code**), enter the required data (e.g., you may be required to award bonus points). Consult your manager if you are unsure about what to enter.
- 5. Click on the **Process** button.
- 6. When the "APPROVED" response displays (refer to the "Loyalty Response" area on the "Purchase" page), the transaction is complete.
- 7. Print/e-mail the transaction receipt now (see page 83).

7.5.6 Loyalty Preauthorization: allocating points for associated debit/credit Preauthorization

When the "APPROVED" response displays on the "Preauth" page of a debit/credit Preauthorization transaction that you have just processed (see page 33), follow the steps below to do a loyalty Preauthorization and allocate loyalty points.

- 1. In the "Action Items" area, click on the Loyalty button.
- 2. Wait for the loyalty "Preauth" page to display.
- 3. In the "Read Loyalty Card" area, do the following:

Note: For information about fields referred to in the steps below, see page 221.

- a. In Order ID field, optionally enter an Order ID.
- b. In the Customer ID field, optionally enter a Customer ID.
- 4. Capture the loyalty card data:

To swipe the loyalty card on an unencrypted magnetic stripe reader:

- a. From the drop-down list, select Mag Swipe Reader.
- b. Click on the **Swipe Card** button.
- c. When "Please swipe loyalty card now" displays on the "Preauth" page, swipe the loyalty card on the unencrypted magnetic stripe reader.

To manually enter the loyalty card:

- a. From the drop-down list, select **Keyed Entry**.
- b. In the **Loyalty Card Number** field, enter the loyalty card number.
- c. Click on the **Next** button.
 - If one or more amount fields display (e.g., **Benefit Amount** and/or **Pre-Tax Amount**), enter the appropriate amount (#.##) for which points should be allocated. Consult your manager if you are unsure about what to enter.
 - If any other data field displays (e.g., **Bonus Code**), enter the required data (e.g., you may be required to allocate bonus points). Consult your manager if you are unsure about what to enter.
- 5. Click on the **Process** button.
- 6. When the "APPROVED" response displays (refer to the "Loyalty Response" area on the "Preauth" page), the transaction is complete.
- 7. Print/e-mail the transaction receipt now (see page 83).

Important! To award the allocated loyalty points, you must capture the debit credit Preauthorization and then capture the loyalty Preauthorization (see page 43).

7.5.7 Loyalty Capture: awarding loyalty points for associated debit/credit Capture

When the "APPROVED" response displays on the "Capture" page of a debit/credit Capture that you have just processed (see page 43), follow the steps below to award the loyalty points that were allocated for the original debit/credit Preauthorization.

- 1. In the "Action Items" area, click on the **Loyalty** button.
- 2. Wait for the loyalty "Capture" page to display.
 - If one or more amount fields display (e.g., **Benefit Amount** and/or **Pre-Tax Amount**), enter the appropriate amount (#.##) for which points should be awarded. Consult your manager if you are unsure about what to enter.
 - If any other data field displays (e.g., **Bonus Code**), enter the required data (e.g., you may be required to award bonus points). Consult your manager if you are unsure about what to enter.
- 3. Click on the Process button.
- 4. When the "APPROVED" response displays (refer to the "Loyalty Response" area on the "Capture" page), the transaction is complete.
- 5. Print/e-mail the transaction receipt now (see page 83).

7.6 Manual Redemption (dollars) with loyalty card

Redeem dollars from a loyalty card.

• For a listing of supported card entry methods, including the associated procedures describing how to use them to perform this transaction, refer to the table below:

7

Card entry method	See procedure on:
unencrypted MSR	page 108
keyed entry	page 109

7.6.1 Manual Redemption (dollars) with loyalty card: unencrypted MSR

Follow the steps below to redeem dollars from a loyalty card by using an unencrypted magnetic stripe reader to capture the card data.

- 1. On the menu bar, click on **Gift/Loyalty** > **Purchase**.
- 2. Wait for the "Purchase" page to display.
- 3. In the "Transaction Details" area, do the following:
 - a. From the drop-down list, select **Dollar Value Purchase/Redemption**.
 - b. In the **Total Amount** field, enter the number of dollars that you want to redeem from the loyalty card.
 - c. In the **Customer ID** field, optionally enter a Customer ID.
- 4. Click on the Next button.
- 5. In the "Payment Method" area, select Loyalty Card MSR from the drop-down list.
- 6. In the "Loyalty Card Redemption Step 1" area, do the following:

- a. In Order ID field, optionally enter an Order ID.
- b. In the **Customer ID** field, optionally enter a Customer ID.
- c. Do one of the following:
 - To view the available funds/status of the loyalty card, see page 132.
 - To proceed with the Redemption, go to step d.
- d. Click on the Swipe Loyalty Card button.
- 7. When "Please swipe loyalty card now" displays on the "Purchase" page, swipe the loyalty card on the unencrypted magnetic stripe reader.
 - If the "Payment Details Step 2" -area fields display (e.g., **Bonus Code**), enter the required data (if you are unsure about what to enter, consult your manager), and click on the **Process** button.
- 8. Wait for the "APPROVED" or "DECLINED" response to display on the "Purchase" page:
 - If a "Balance Due \$#.##" response is indicated, see page 137.
 - If a "Balance Due \$0.00" (zero dollars) response is indicated, the transaction is compete (go to step 9).
- 9. Print/e-mail the transaction receipt now (see page 83).

7.6.2 Manual Redemption (dollars) with loyalty card: keyed entry

Follow the steps below to redeem dollars from a loyalty card by manually entering (keying) the card data in the Merchant Resource Center fields.

- 1. On the menu bar, click on Gift/Loyalty > Purchase.
- 2. Wait for the "Purchase" page to display.
- 3. In the "Transaction Details" area, do the following:
 - a. From the drop-down list, select **Dollar Value Purchase/Redemption**.
 - b. In the **Total Amount** field, enter the number of dollars that you want to redeem from the loyalty card.
 - c. In the **Customer ID** field, optionally enter a Customer ID.
- 4. Click on the Next button.
- 5. In the "Payment Method" area, select **Loyalty Card Keyed** from the drop-down list.
- 6. In the "Loyalty Card Redemption Step 1" area, do the following:

- a. In Order ID field, optionally enter an Order ID.
- b. In the **Customer ID** field, optionally enter a Customer ID.
- c. Do one of the following:
 - To view the available funds/status of the loyalty card, see page 132.
 - To proceed with the Redemption, go to step d.
- d. In the **Loyalty Card Number** field, enter the loyalty card number.
- 7. Click on the **Next** button.
 - If the "Payment Details Step 2" -area fields display (e.g., **Bonus Code**), enter the required data (if you are unsure about what to enter, consult your manager), and click on the **Process** button.
- 8. Wait for the "APPROVED" or "DECLINED" response to display on the "Purchase" page:
 - If a "Balance Due \$#.##" response is indicated, see page 137.
 - If a "Balance Due \$0.00" (zero dollars) response is indicated, the transaction is compete (go to step 9).
- 9. Print/e-mail the transaction receipt now (see page 83).

7.7 Manual Redemption (points) with loyalty card

Redeem points from a loyalty card.

• For a listing of supported card entry methods, including the associated procedures describing how to use them to perform this transaction, refer to the table below:

Card entry method	See procedure on:
unencrypted MSR	page 111
keyed entry	page 112

7.7.1 Manual Redemption (points) with loyalty card: unencrypted MSR

Follow the steps below to redeem points from a loyalty card by using an unencrypted magnetic stripe reader to capture the card data.

- 1. On the menu bar, click on **Gift/Loyalty** > **Purchase**.
- 2. Wait for the "Purchase" page to display.
- 3. In the "Transaction Details" area, do the following:
 - a. From the drop-down list, select **Points Value Purchase/Redemption**.
 - b. In the **Points to Redeem** field, enter the number of points that you want to redeem from the loyalty card.
 - c. In the **Customer ID** field, optionally enter a Customer ID.
- 4. Click on the Next button.
- 5. In the "Payment Method" area, select Loyalty Card MSR from the drop-down list.
- 6. In the "Loyalty Card Redemption Step 1" area, do the following:

- a. In Order ID field, optionally enter an Order ID.
- b. In the **Customer ID** field, optionally enter a Customer ID.
- c. Do one of the following:
 - To view the available funds/status of the loyalty card, see page 132.
 - To proceed with the Redemption, go to step d.
- d. Click on the Swipe Loyalty Card button.
- 7. When "Please swipe loyalty card now" displays on the "Purchase" page, swipe the loyalty card on the unencrypted magnetic stripe reader.
 - If the "Payment Details Step 2" -area fields display (e.g., **Bonus Code**), enter the required data (if you are unsure about what to enter, consult your manager), and click on the **Process** button.
- 8. When the "APPROVED" or "DECLINED" response displays on the "Purchase" page, the transaction is complete, but note:
 - If a "Balance Due #### pts" response is indicated, see page 138.
 - If a "Balance Due 0 pts" (zero points) response is indicated, the transaction is complete (go to step 9).
- 9. Print/e-mail the transaction receipt now (see page 83).

7.7.2 Manual Redemption (points) with loyalty card: keyed entry

Follow the steps below to redeem points from a loyalty card by manually entering (keying) the card data in the Merchant Resource Center fields.

- 1. On the menu bar, click on Gift/Loyalty > Purchase.
- 2. Wait for the "Purchase" page to display.
- 3. In the "Transaction Details" area, do the following:
 - a. From the drop-down list, select **Points Value Purchase/Redemption**.
 - b. In the **Points to Redeem** field, enter the number of points that you want to redeem from the loyalty card.
 - c. In the Customer ID field, optionally enter a Customer ID.
- 4. Click on the Next button.
- 5. In the "Payment Method" area, select **Loyalty Card Keyed** from the drop-down list.
- 6. In the "Loyalty Card Redemption Step 1" area, do the following:

- a. In **Order ID** field, optionally enter an Order ID.
- b. In the **Customer ID** field, optionally enter a Customer ID.
- c. Do one of the following:
 - To view the available funds/status of the loyalty card, see page 132.
 - To proceed with the Redemption, go to step d.
- d. In the **Loyalty Card Number** field, enter the loyalty card number.
- 7. Click on the **Next** button.
 - If the "Payment Details Step 2" -area fields display (e.g., **Bonus Code**), enter the required data (if you are unsure about what to enter, consult your manager), and click on the **Process** button.
- 8. Wait for the "APPROVED" or "DECLINED" response to display on the "Purchase" page:
 - If a "Balance Due #### pts" response is indicated, see page 138.
 - If a "Balance Due 0 pts" (zero points) response is indicated, the transaction is complete (go to step 9).
- 9. Print/e-mail the transaction receipt now (see page 83).

7.8 Loyalty Void

To reverse a loyalty transaction that originally awarded points for an associated transaction that has since been voided, do the following:

To reverse a loyalty transaction for an associated debit/credit Void, see page 114.

7

- To reverse a loyalty transaction for an associated gift Void, see page 114.
- To reverse a loyalty transaction for an associated loyalty Redemption, see page 115.

7

7.8.1 Loyalty Void: removing loyalty points for associated debit/credit Void

When the "APPROVED" response displays on the "Void" page of a debit/credit transaction that you have just processed, follow the steps below to do a loyalty Void and remove the loyalty points awarded for the original Purchase, Capture, or Voice Authorization-Advice transaction.

- 1. In the "Action Items" area, click on the **Loyalty** button.
- 2. When the "APPROVED" response displays (see the "Loyalty Response" area on the "Void" page), the transaction is complete.
- 3. Print/e-mail the transaction receipts now (see page 83).

7.8.2 Loyalty Void: reversing an associated gift card Purchase

Follow the steps below to do a loyalty Void and remove the loyalty points awarded for the original gift card Purchase (see page 91).

- 1. On the menu bar, click on Gift/Loyalty > Void.
- 2. Wait for the "Void" page to display.
- 3. In the **Order ID** field, enter the Order ID of the original loyalty Purchase transaction that you want to reverse.

Note: If you only have a partial Order ID, mark the **begins with** or the **ends with** radio button.

- 4. Click on the Locate Transaction button.
- 5. Wait for the "Void" page to display.
- 6. In the "Transaction List" area, click on the **Void** button beside the transaction that you want to reverse.
- 7. When the "Transaction Details" area displays, click on the **Process** button.
- 8. When the "Approved" or "Declined" response displays on the "Void" page, the transaction is complete.
- 9. Print/e-mail the transaction receipt now (see page 83).

7.8.3 Loyalty Void: reversing a loyalty Redemption

Follow the steps below to reverse (void) an open-batch loyalty card Redemption for dollars (see page 107) or reverse an open-batch loyalty card Redemption for points (see page 110) for the full amount of the original transaction (restores loyalty points/dollars to the card).

- 1. On the menu bar, click on Gift/Loyalty > Void.
- 2. Wait for the "Void" page to display.
- 3. In the **Order ID** field, enter the Order ID of the original Redemption transaction that you want to reverse.

Note: If you only have a partial Order ID, mark the **begins with** or the **ends with** radio button.

- 4. Click on the Locate Transaction button.
- 5. Wait for the "Void" page to display.
- 6. In the "Transaction List" area, click on the **Void** button beside the transaction that you want to reverse.
- 7. When the "Transaction Details" area displays, click on the **Process** button.
- 8. When the "Approved" or "Declined" response displays on the "Void" page, the transaction is complete.
- 9. Print/e-mail the transaction receipt now (see page 83).

7

7.9 Loyalty Refund

To reverse a loyalty transaction that originally awarded points for an associated Purchase that has since been refunded, do the following:

- To reverse a loyalty transaction for an associated debit/credit Refund, see page 117.
- To reverse a loyalty transaction for an associated cash Refund, see page 117.
- To reverse a loyalty transaction for an associated gift Refund, see page 118.
- To reverse a loyalty transaction for an associated loyalty Redemption, see page 118.

7.9.1 Loyalty Refund: removing loyalty points for associated debit/credit Refund

When the "APPROVED" response displays on the "Refund" page of a debit/credit transaction that you just processed, follow the steps below to do a loyalty Refund and remove the loyalty points that were awarded for the original debit/credit Purchase, Capture, or Voice Authorization-Advice transaction.

Note: Some loyalty card programs do not allow loyalty Refunds.

- 1. In the "Action Items" area, click on the Loyalty button.
- 2. When the "APPROVED" or "DECLINED" response displays (see the "Loyalty Response" area on the "Refund" page), the transaction is complete.
- 3. Print/e-mail the transaction receipt now (see page 83).

7.9.2 Loyalty Refund: removing loyalty points for associated cash Refund

When the "APPROVED" response displays on the "Refund" page of a cash transaction that you just processed, follow the steps below to do a loyalty Refund and remove the loyalty points that were awarded for the original cash Purchase.

Note: Some loyalty card programs do not allow loyalty Refunds.

- 1. In the "Action Items" area, click on the Loyalty button.
- 2. When the "APPROVED" or "DECLINED" response displays (see the "Loyalty Response" area on the "Refund" page), the transaction is complete.
- 3. Print/e-mail the transaction receipt now (see page 83).

7.9.3 Loyalty Refund: removing loyalty points for associated gift Refund

Follow the steps below to do a loyalty Refund and remove points that were awarded for a gift card transaction (for which points were awarded) that you have since refunded (see page 95).

- 1. On the menu bar, click on Gift/Loyalty > Refund.
- 2. Wait for the "Refund" page to display.
- 3. In the **Order ID** field, enter the Order ID of the original loyalty Purchase that you want to reverse.

Note: If you only have a partial Order ID, mark the **begins with** or the **ends with** radio button.

- 4. Click on the Locate Transaction button.
- 5. Wait for the "Refund" page to display.
- 6. In the "Transaction List" area, click on the **Refund** button beside the transaction that you want to reverse.
- 7. When the "Transaction Details" area displays, click on the **Process** button.
- 8. When the "Approved" or "Declined" response displays on the "Refund" page, the transaction is complete.
- 9. Print/e-mail the transaction receipt now (see page 83).

7.9.4 Loyalty Refund: reversing a loyalty Redemption

A loyalty Redemption transaction in a closed batch cannot be reversed (refunded) from the Merchant Resource Center.

7.10 Redeeming coupon/voucher with gift/loyalty card

7

Redeem a coupon/voucher.

• For a listing of supported card entry methods, including the associated procedures describing how to use them to perform this transaction, refer to the table below:

Card entry method	See procedure on:
unencrypted MSR	page 120
keyed entry	page 121

7.10.1 Redeeming coupon/voucher with gift/loyalty card: MSR

Follow the steps below to redeem a coupon/voucher by using an unencrypted magnetic stripe reader to capture the card data.

Note: No dollars or points will be used from the card as a result of this transaction (i.e., it will result in a zero-dollar Purchase/Redemption).

- 1. On the menu bar, click on Gift/Loyalty > Redeem.
- 2. Wait for the "Redeem Coupon / Voucher" page to display.
- 3. In the "Read Card" area, select Mag Swipe Reader from the drop-down list.
- 4. In the "Redeem Details Step 1" area, do the following:

- a. In Order ID field, optionally enter an Order ID.
- b. In the **Customer ID** field, optionally enter a Customer ID.
- c. Click on the **Swipe Gift Card** button.
- d. When "Please swipe card now" displays on the "Redeem Coupon / Voucher" page, swipe the gift/loyalty card on the unencrypted magnetic stripe reader.
- 5. In the "Payment Details Step 2" area, do the following:
 - a. In the **Reference Number** field, enter the "REF NUM" from the gift/loyalty coupon/voucher receipt.
 - If the CVC field displays, enter the card validation code.
 - If any other data field displays, enter the required data (if you are unsure about what to enter, consult your manager).
 - b. Click on the Process button.
- 6. When the "APPROVED" or "DECLINED" response displays on the "Redeem Coupon/Voucher" page, the transaction is complete.
- 7. Print/e-mail the transaction receipt now (see page 83).

7.10.2 Redeeming coupon/voucher with gift/loyalty card: keyed entry

Follow the steps below to redeem a coupon/voucher by manually entering (keying) the gift/loyalty card data in the Merchant Resource Center fields.

Note: No dollars or points will be used from the card as a result of this transaction (i.e., it will result in a zero-dollar Purchase/Redemption).

- 1. On the menu bar, click on **Gift/Loyalty** > **Redeem**.
- 2. Wait for the "Redeem Coupon / Voucher" page to display.
- 3. In the "Read Card" area, select **Keyed** from the drop-down list.
- 4. In the "Redeem Details Step 1" area, do the following:

- a. In Order ID field, optionally enter an Order ID.
- b. In the **Customer ID** field, optionally enter a Customer ID.
- c. In the Gift Card Number field, enter the gift/loyalty card number.
- d. Click on the Next button.
- 5. In the "Payment Details Step 2" area, do the following:
 - a. In the **Reference Number** field, enter the "REF NUM" from the gift/loyalty coupon/voucher receipt.
 - If the CVC field displays, enter the card validation code.
 - If any other data field displays, enter the required data (if you are unsure about what to enter, consult your manager).
 - b. Click on the **Process** button.
- 6. When the "APPROVED" or "DECLINED" response displays on the "Redeem-Coupon/Voucher" page, the transaction is complete.
- 7. Print/e-mail the transaction receipt now (see page 83).

7.11 Activating and loading a gift/loyalty card

Activate and load a gift/loyalty card.

• For a listing of supported card entry methods, including the associated procedures describing how to use them to perform this transaction, refer to the table below:

Card entry method	See procedure on:
unencrypted MSR	page 123
keyed entry	page 124

7.11.1 Activating and loading a gift/loyalty card: MSR

Follow the steps below to activate a gift/loyalty card by using an unencrypted magnetic stripe reader to capture the card data.

7

- 1. On the menu bar, click on Gift/Loyalty > Activate.
- 2. Wait for the "Activate" page to display.
- 3. In the "Read Card" area, do the following:

- a. From the "Card Input Method" drop-down list, select Mag Swipe Reader.
- b. In the Order ID field, optionally enter an Order ID.
- c. In the **Customer ID** field, optionally enter a Customer ID.
- d. Click on the **Swipe Card** button.
- e. When "Please swipe card now" displays on the "Activate" page, swipe the gift/loyalty card on the unencrypted magnetic stripe reader.
- 4. Do one of the following:
 - If the ""Activation Details Step 2" area displays, go to step 5.
 - If the "APPROVED" response displays, go to step 6.
- 5. In the "Activation Details Step 2" area, do the following:
 - a. If the CVC field displays, enter the card validation code.
 - b. If the **Activation Amount** field displays (e.g., variable amount gift cards), enter the amount that you want to load on the card.
 - If any other data field displays, enter the required data (if you are unsure about what to enter, consult your manager).
 - c. Click on the **Process** button.
- 6. When the "APPROVED" response displays on the "Activate" page, click on the **Continue** button.
- 7. Select a payment method (refer to the appropriate procedure in the table below):

Payment method	card entry method	see procedure on:
debit/credit card	iPP320 PINpad	page 133
debit/credit card	unencrypted MSR	page 134
debit/credit card	keyed entry	page 135
cash	-	page 136

7.11.2 Activating and loading a gift/loyalty card: keyed entry

Follow the steps below to activate a gift/loyalty card by using an unencrypted magnetic stripe reader to capture the card data.

- 1. On the menu bar, click on Gift/Loyalty > Activate.
- 2. Wait for the "Activate" page to display.
- 3. In the "Read Card" area, do the following:

- a. From the "Card Input Method" drop-down list, select **Keyed Entry**.
- b. In the Order ID field, optionally enter an Order ID.
- c. In the **Customer ID** field, optionally enter a Customer ID.
- d. In the **Card Number** field, enter the gift/loyalty card number, and click on the **Next** button.
- 4. Do one of the following:
 - If the "Activation Details Step 2" area displays, to go step 5.
 - If the "APPROVED" response displays, go to step 6.
- 5. In the "Activation Details Step 2" area, do the following:
 - a. If the CVC field displays, enter the card validation code.
 - b. If the **Activation Amount** field displays (e.g., variable amount gift cards), enter the amount that you want to load on the card.
 - If any other data field displays, enter the required data (if you are unsure about what to enter, consult your manager).
 - c. Click on the **Process** button.
- 6. When the "APPROVED" response displays on the "Activate" page, click on the **Continue** button.
- 7. Select a payment method, and refer to the appropriate procedure in the table below:

Payment method	card entry method	see procedure on:
debit/credit card	iPP320 PINpad	page 133
debit/credit card	unencrypted MSR	page 134
debit/credit card	keyed entry	page 135
cash	-	page 136

7.12 Deactivating a gift/loyalty card

Deactivate a gift/loyalty card.

• For a listing of supported card entry methods, including the associated procedures describing how to use them to perform this transaction, refer to the table below:

7

Card entry method	See procedure on:
unencrypted MSR	page 126
keyed entry	page 127

7.12.1 Deactivating a gift/loyalty card: MSR

Follow the steps below to permanently deactivate a gift/loyalty card by using an unencrypted magnetic stripe reader to capture the card data.

- 1. On the menu bar, click on **Gift/Loyalty** > **Deactivate**.
- 2. Wait for the "Deactivate" page to display.
- 3. In the "Read Card" area, select Mag Swipe Reader from the drop-down list.

- 4. In the "Deactivation Details Step 1" area, do the following:
 - a. In the **Order ID** field, optionally enter an Order ID.
 - b. In the **Customer ID** field, optionally enter a Customer ID.
 - c. Click on the Swipe Card button.
 - d. When "Please swipe card now" displays on the "Deactivate" page, swipe the gift/loyalty card on the unencrypted magnetic stripe reader.
- 5. Do one of the following:
 - If the "Payment Details Step 2" area displays, go to step 6.
 - If the "APPROVED" response displays, go to step 7.
- 6. In the "Payment Details Step 2" area, do the following:
 - a. If the CVC field displays, enter the card validation code.
 - If any other data field displays, enter the required data (if you are unsure about what to enter, consult your manager).
- 7. When the "APPROVED" response displays on the "Deactivate" page, the transaction is complete (the card is deactivated).
- 8. Print/e-mail the transaction receipt now (see page 83).

7.12.2 Deactivating a gift/loyalty card: keyed entry

Follow the steps below to permanently deactivate a gift/loyalty card by manually entering (keying) the card data in the Merchant Resource Center fields.

- 1. On the menu bar, click on Gift/Loyalty > Deactivate.
- 2. Wait for the "Deactivate" page to display.
- 3. In the "Read Card" area, select **Keyed Entry** from the drop-down list.

Note: For information about fields referred to in the steps below, see page 221.

7

- 4. In the "Deactivation Details Step 1" area, do the following:
 - a. In the **Order ID** field, optionally enter an Order ID.
 - b. In the **Customer ID** field, optionally enter a Customer ID.
 - c. In the Card Number field, enter the gift/loyalty card number.
 - d. Click on the Next button.
- 5. Do one of the following:
 - If the "Payment Details Step 2" area displays, go to step 6.
 - If the "APPROVED" response displays, go to step 7.
- 6. In the "Payment Details Step 2" area, do the following:
 - a. If the CVC field displays, enter the card validation code.
 - If any other data field displays, enter the required data (if you are unsure about what to enter, consult your manager).
 - b. Click on the **Process** button.
- 7. When the "APPROVED" response displays on the "Deactivate" page, the transaction is complete (the card is deactivated).
- 8. Print/e-mail the transaction receipt now (see page 83).

7.13 Balance Inquiry for gift/loyalty card: initiating from menu bar

Obtain the points balance and status for a gift/loyalty card.

For a listing of supported card entry methods, including the associated procedures describing how to use them to perform this transaction, refer to the table below:

Card entry method	See procedure on:
unencrypted MSR	page 129
keyed entry	page 130

7.13.1 Balance Inquiry for gift/loyalty card: MSR

Follow the steps below to obtain the status and dollar or points balance on a gift/loyalty card by using an unencrypted magnetic stripe reader to capture the card data.

7

- 1. On the menu bar, click on Gift/Loyalty > Balance Inquiry.
- 2. Wait for the "Balance Inquiry" page to display.

- 3. In the "Read Card" area, do the following:
 - a. Select Mag Swipe Reader from the drop-down list.
 - b. Click on the **Swipe Card** button.
 - c. When "Please swipe card now" displays on the "Balance Inquiry" page, swipe the gift/loyalty card on the unencrypted magnetic stripe reader.
- 4. Do one of the following:
 - If the "Card Details Step 2" area displays, go to step 5.
 - In the "Inquiry Response"-area details display, go to step 6.
- 5. In the "Card Details Step 2" area, do the following:
 - a. In the CVC field, enter the card validation code.
 - If any other data field displays, enter the required data (if you are unsure about what to enter, consult your manager).
 - b. Click on the **Next** button.
- 6. When the "Inquiry Response"-area details display on the "Balance Inquiry" page, the operation is complete.

7

7.13.2 Balance Inquiry for gift/loyalty card: keyed entry

Follow the steps below to obtain the status and dollar or points balance on a gift/loyalty card by manually entering (keying) the card data in the Merchant Resource Center fields.

- 1. On the menu bar, click on Gift/Loyalty > Balance Inquiry.
- 2. Wait for the "Balance Inquiry" page to display.
- 3. In the "Read Card" area, do the following:

- a. From the drop-down list, select Keyed Entry.
- b. In the **Card Number** field, enter the gift/loyalty card number.
- c. Click on the **Next** button.
- 4. Do one of the following:
 - If the "Card Details Step 2" area displays, go to step 5.
 - If the "Inquiry Response"-area details display, go to step 6.
- 5. In the "Card Details Step 2" area, do the following:
 - a. In the CVC field, enter the card validation code.
 - If any other data field displays, enter the required data (if you are unsure about what to enter, consult your manager).
 - b. Click on the **Next** button.
- 6. When the "Inquiry Response"-area details display on the "Balance Inquiry" page, the operation is complete.

7.14 Balance Inquiry for gift card: initiating during gift Purchase

7

Follow the steps below to perform view the dollar balance and status of a gift card while you are performing a gift Purchase transaction.

- 1. In the "Gift Card Payment Step 1" area on the "Purchase" page, click on the **Gift Card Balance Inquiry** button.
- 2. When the "Balance Inquiry" page displays, capture the gift card data:

To swipe the gift card on an unencrypted magnetic stripe reader:

- a. From the "Card Input" drop-down list, select Mag Swipe Reader.
- b. Click on the **Swipe Card** button.
- c. When "Please swipe card now" displays on the "Balance Inquiry" page, swipe the gift card on the unencrypted magnetic stripe reader.

To manually enter the gift card:

- a. From the "Card Input" drop-down list, select Keyed Entry.
- b. In the **Card Number** field, enter the gift card number.
- c. Click on the **Next** button.
- 3. In the "Card Details Step 2" area, do the following:
 - a. In the CVC field, enter the card validation code.
 - If any other data field displays, enter the required data (consult your manager if you are unsure about what to enter).
 - b. Click on the **Next** button.
- 4. When the "Inquiry Response"-area details display on the "Balance Inquiry" page, the operation is complete.
- 5. Click on **Close Window** at the top of the page, and refer back to the gift Purchase procedure.

7.15 Balance Inquiry for loyalty card: initiating during loyalty Redemption

Follow the steps below to view the points balance and status of a loyalty card while you are performing a manual loyalty Redemption transaction.

- 1. In the "Loyalty Card Payment Step 1" area on the "Purchase" page, click on the Loyalty Card Balance Inquiry button.
- 2. When the "Balance Inquiry" page displays, capture the loyalty card data:

To swipe the loyalty card on an unencrypted magnetic stripe reader:

- a. From the "Card Input" drop-down list, select Mag Swipe Reader.
- b. Click on the **Swipe Card** button.
- c. When "Please swipe card now" displays on the "Balance Inquiry" page, swipe the loyalty card on the unencrypted magnetic stripe reader.

- a. From the "Card Input" drop-down list, select **Keyed Entry**.
- b. In the **Card Number** field, enter the loyalty card number.
- c. Click on the **Next** button.
- 3. Do one of the following:
 - If the "Card Details Step 2" area displays, enter the required data in any field that displays (consult your manager if you are unsure about what to enter), and click on the **Next** button.
 - If the "Inquiry Response"-area details display, go to step 4.
- 4. When the "Inquiry Response"-area details display on the "Balance Inquiry" page, the operation is complete.
- 5. Click on **Close Window** at the top of the page, and refer back to the loyalty Redemption procedure.

7.16.1 Activating a gift/loyalty card - payment with debit/credit card: iPP320 PINpad

7

Follow the steps below to complete a gift card Activate transaction by paying the balance due with a debit/credit card. You will use an iPP320 PINpad to capture the debit/credit card data (insert, tap, or swipe).

- 1. In the "Payment Method" area on the "Activate" page, select **Debit/Credit Pinpad** from the drop-down list.
- 2. In the "Payment Details" area, do the following:

Note: For information about fields referred to in the steps below, see page 221.

- a. If the **Enable manual card input** box displays, ensure that it is unmarked.
- b. In the Order ID field, optionally enter an Order ID.
- c. In the Customer ID field, optionally enter a Customer ID.
- d. In the **Amount** field, confirm that the displayed dollar amount (#.##) is the amount that you want to load on the gift card (i.e., the Purchase amount).

Note: If no amount data is displayed in the field, enter the amount now.

- 3. Click on the Swipe Card button.
- 4. When "Establishing communication with pinpad" displays on the "Activate" page, wait.
- 5. When "Please follow prompts on pinpad" displays on the "Activate" page, see *Cardholder prompts: iPP320 PINpad* (page 78).
- 6. When the "APPROVED or "DECLINED" response displays on the "Activate" page, the transaction is complete:
 - If Moneris Loyalty is enabled and you want to award loyalty points, see page 101.
 - If Moneris Loyalty is not enabled or it is but you want to bypass awarding points, print/e-mail the transaction receipt now (see page 83).

7.16.2 Activating a gift/loyalty card - payment with debit/credit card: MSR

Follow the steps below to complete a gift card Activate transaction by paying the balance due with a credit card. You will use an unencrypted magnetic stripe reader to capture the credit card data.

Note: Some chip debit cards may be used for this transaction.

- 1. In the "Payment Method" area on the "Activate" page, select **Credit Card MSR** from the drop-down list.
- 2. In the "Payment Details" area, do the following:

Note: For information about fields referred to in the steps below, see page 221.

- a. In the Order ID field, optionally enter an Order ID.
- b. In the **Customer ID** field, optionally enter a Customer ID.
- c. In the **Statement Descriptor** field, enter a descriptor for the card statement.
- d. In the **Amount** field, confirm that the displayed dollar amount (#.##) is the amount that you want to load on the gift card (i.e., the Purchase amount).

Note: If no amount data is displayed in the field, enter the amount now.

- e. In the Card Verification Digits field, enter the card verification digits.
 - If the "Address Verification" area displays, enter the billing address data in the Street Number, Street Name (use also to enter PO box data), and Zip/Postal Code fields (for a post office box, checkmark PO Box).
 - To add order details (shipping/billing and product details), see page 64.
- 3. Click on the **Swipe Card** button.
- 4. When "Please swipe credit card now" displays on the "Activate" page, swipe the credit card on the unencrypted magnetic stripe reader.
- 5. When the "APPROVED" or DECLINED" response displays on the "Activate" page, the transaction is complete:
 - If Moneris Loyalty is enabled and you want to award loyalty points, see page 101.
 - If Moneris Loyalty is not enabled or it is but you want to bypass awarding points, print/e-mail the transaction receipt now (see page 83).

7.16.3 Activating a gift/loyalty card - payment with debit/credit card: keyed entry

Follow the steps below to complete a gift card Activate transaction by paying the balance due with a credit card. You will manually enter (key) the card in the Merchant Resource Center fields.

Note: Some chip debit cards may be used for this transaction.

- 1. In the "Payment Method" area on the "Activate" page, select **Credit Card Keyed Entry** from the drop-down list.
- 2. In the "Payment Details" area, do the following:

Note: For information about fields referred to in the steps below, see page 221.

- a. In the Order ID field, optionally enter an Order ID.
- b. In the **Customer ID** field, optionally enter a Customer ID.
- c. In the **Statement Descriptor** field, enter a descriptor for the card statement.
- d. In the **Amount** field, confirm that the displayed dollar amount (#.##) is the amount that you want to load on the gift card (i.e., the Purchase amount).

Note: If no amount data is displayed in the field, enter the amount now.

- e. In the Credit Card Number field, enter the card account number.
- f. In the **Expiry Date** field, enter the card expiry date (MMYY).
- g. In the Card Verification Digits field, enter the card verification digits.
- h. From the "ECI Indicator" drop-down list, select an e-commerce descriptor.
 - If the "Address Verification" area displays, enter the billing address data in the Street Number, Street Name (use also to enter PO box data), and Zip/Postal Code fields (for a post office box, checkmark PO Box).
 - To add order details (shipping/billing and product details), see page 64.
- 3. Click on the Process Transaction button.
- 4. When the "APPROVED" or DECLINED" response displays on the "Activate" page, the transaction is complete:
 - If Moneris Loyalty is enabled and you want to award loyalty points, see page 101.
 - If Moneris Loyalty is not enabled or it is but you want to bypass awarding points, print/e-mail the transaction receipt now (see page 83).

7.16.4 Activating a gift/loyalty card - payment with cash

Follow the steps below to complete a gift card Activate transaction by paying the balance due with cash.

- 1. In the "Payment Method" area on the "Activate" page, select **Cash** from the drop-down list.
- 2. In the "Payment Details" area, do the following:

Note: For information about fields referred to in the steps below, see page 221.

- a. In the Order ID field, optionally enter an Order ID.
- b. In the **Customer ID** field, optionally enter a Customer ID.
- c. In the **Amount** field, confirm that the displayed dollar amount (#.##) is the amount that you want to load on the gift card (i.e., the Purchase amount).

Note: If no amount data is displayed in the field, enter the amount now.

d. In the **Amount Tendered** field, optionally enter the dollar amount tendered by the customer.

Note: The **Change Due** field will automatically display the dollar amount owed to the customer.

- 3. Click on the **Complete** button.
- 4. When the "APPROVED" response displays on the "Activate" page, the transaction is complete:
 - If Moneris Loyalty is enabled and you want to award loyalty points, see page 101.
 - If Moneris Loyalty is not enabled or it is but you want to bypass awarding points, print/e-mail the transaction receipt now (see page 83).

7.16.5 Balance due for gift dollars transaction

When a gift Purchase results in a "Balance Due \$#.##" response (because there are insufficient dollars on the gift card to cover the gift Purchase amount), follow the steps below to select another payment type to cover the outstanding balance.

7

- 1. In the "Action Items" area on the response page, click on the **Continue** button.
- 2. Wait for the "Purchase" page to display.
- 3. Based on the payment method/card entry method that you want to use to pay the outstanding balance, refer to the appropriate Purchase procedure below:

Gift card

Card entry method	See Purchase procedure on:
unencrypted MSR	page 92 (begin at step 7)
keyed entry	page 93 (begin at step 7)

Loyalty card (dollars redemption)

Card entry method	See Redemption procedure on:
unencrypted MSR	page 108 (begin at step 5)
keyed entry	page 109 (begin at step 5)

Debit/credit card

Card entry method	See Purchase procedure on:
iPP320 PINpad	page 25 (begin at step 3)
iPP320 PINpad (manual)	page 26 (begin at step 3)
unencrypted MSR	page 28 (begin at step 3)
keyed entry	page 30 (begin at step 3)

Cash

See page 31 (begin at step 3).

7.16.6 Balance due for loyalty dollars transaction

When a loyalty Redemption results in a "Balance Due \$#.##" response (because there are insufficient dollars/points on the loyalty card to cover the loyalty Redemption amount), follow the steps below to select another payment type to cover the outstanding balance.

- 1. In the "Action Items" area on the response page, click on the **Continue** button.
- 2. Wait for the "Purchase" page to display.
- 3. Based on the payment method/card entry method that you want to use to pay the outstanding balance, refer to the appropriate Purchase procedure below:

Gift card

Card entry method	See Purchase procedure on:
unencrypted MSR	page 92 (begin at step 7)
keyed entry	page 93 (begin at step 7)

Loyalty card (dollars redemption)

Card entry method	See Redemption procedure on:
unencrypted MSR	page 108 (begin at step 5)
keyed entry	page 109 (begin at step 5)

Debit/credit card

Card entry method	See Purchase procedure on:
iPP320 PINpad	page 25 (begin at step 3)
iPP320 PINpad (manual)	page 26 (begin at step 3)
unencrypted MSR	page 28 (begin at step 3)
keyed entry	page 30 (begin at step 3)

Cash

See page 31 (begin at step 3).

7.16.7 Balance due for loyalty points Redemption

When a manual loyalty card Redemption results in a "Balance Due #### pts" response (i.e., because there are insufficient points on the loyalty card to cover the Redemption amount), follow the steps below to select another payment type to cover the outstanding balance.

1. In the "Action Items" area on the response page, click on the **Continue** button.

7

- 2. Wait for the "Purchase" page to display.
- 3. Based on the card entry method that you want to use to pay the outstanding balance, refer to the appropriate Redemption procedure below:

Loyalty card (points redemption)

Card entry method	See Redemption procedure on:
unencrypted MSR	page 111 (begin at step 5)
keyed entry	page 112 (begin at step 5)

8 Recurring billing

If your Merchant Resource Center store is enabled for the recurring billing feature, you may initiate the automatic charging of customer credit cards (and some debit chip cards) at regular intervals, suspend payments, include one-time fees, and generate card expiration reports for transactions. You may also manage the setup of existing recurring transactions.

- To register a recurring transaction, see page 141.
- To manage (update or delete) a recurring transaction, see page 143.
- To generate a recurring transaction report, see page 145.

8.1 Registering a recurring transaction: keyed entry

Follow the steps below to register a transaction (Purchase) that is set to recur automatically at a frequency that you define. You manually enter (key) the card data in the Merchant Resource Center fields.

Note: Some debit chip cards may be used for this transaction.

- 1. On the menu bar, click on **Recurring > Add Recurring Transaction**.
- 2. Wait for the "Add Recurring Transaction" page to display.
- 3. Do the following:

Note: For information about fields referred to in the steps below, see page 221.

- a. In **Order ID** field, optionally enter an Order ID.
- b. In the **Customer ID** field, optionally enter a Customer ID.
- c. In the Credit Card Number field, enter the card account number.
- d. In the Expiry Date field, enter the card expiry date (MMYY).
- e. In the Card Verification Digits field, enter the card verification digits.
- f. From the "ECI Indicator" drop-down list, select an e-commerce descriptor.
 - If the "Address Verification" area displays, enter the billing address data in the Street Number, Street Name (use also to enter PO box data), and Zip/Postal Code fields (for a post office box, checkmark PO Box).
- 4. In the "Recurring Details" area, do the following:
 - a. Mark a "Bill Now" radio button:
 - To start billing when the transaction is registered, mark the YES radio button, and enter the first billing amount in the Bill Now Amount field.
 - To start billing some time after the transaction is registered, mark the NO radio button.

Note: If "NO" is selected but you want to obtain card verification results when the recurring transaction is registered, checkmark the **Perform** card verification box.

- b. In the **Recurring Amount** field, enter the amount to be billed at the specified recur start time.
- c. From the **Start Date** drop-down list, select the date on which billing is to commence.
- d. In the **Recur Every** field, enter a number that defines the interval of a single billing to the card (billing does not include the "BILL NOW" amount if this option was selected in step a).

- **Note:** If you enter **8** for example, billing will occur after eight undefined periods of time have elapsed. (You define the periods of time in step e.)
- e. From the **Recur Every** drop-down list, select the time frame (e.g., day(s), month(s), year(s)) to define the interval of a single billing.
 - **Note:** If **month(s)** is selected for example, the card will be billed once every "X" number of months. ("X" is defined by what you entered in step d.)
- f. In the Number of Recurs field, enter a number that defines how many times a card should be billed not including the "Bill Now" option.
 - **Note:** If you enter **5** for example, a single billing will occur five times at whatever interval you specified in steps d and e.
- g. Click on the Add Customer Details button, and enter data in the "Customer Details"-area fields (First Name, Last Name, Company, Address, State/Prov, **Zip Code**, **Country**, **Phone**, and **Fax**).
- 5. Click on the Process Transaction button.
- 6. When the "successfully registered" response displays on the "Add Recurring Transaction" page, the operation is complete.
- 7. While the "Add Recurring Transaction" page is displayed, do one of the following:
 - Update the recurring transaction details now (see page 143; begin at step 8).
 - Close the "Add Recurring Transaction" page, and update the recurring transaction details later (see page 143; begin at step 1).

8.2 Managing a recurring transaction

Follow the steps below to alter the characteristics of a recurring transaction.

- 1. On the menu bar, click on **Recurring** > **Manage Recurring**.
- 2. Wait for the "Manage Recurring Transactions" page to display.
- 3. You may narrow the search by using Customer ID, Order ID, last name, amount, managed account update status, and hold status ("other criteria"); and /or date:

To narrow the search by "other criteria":

- a. In the "Other Criteria" area, checkmark the box beside any of the other criteria (Customer ID, Last Name, Order ID, Amount, Managed Account Update Ignore Enabled, and Hold Status) that you want to include in the report.
- b. Enter the required data in the field beside any box that you checkmarked in the previous step.
 - If you checkmarked the Hold Status box, mark the On Hold or Active radio button

To narrow the search by date

- a. In the "Date" area, checkmark the Date box.
- b. Checkmark the box beside one or more of the following date criteria: **Create Date**, **Start Date**, **Next Recur Date**, and/or **End Date**.
- c. For each box that you checkmarked in the previous step, select a date (DD/MM/YYYY) from the corresponding **From** /**To** drop-down lists.
- 4. In the "Sort By" area, set your sort order preference for listing the results:
 - a. From the **Sort Transactions by** drop-down list, select the order (**Create Date**, **Start Date**, **Next Recur Date**, etc.) in which you want the hits to be listed.
 - b. From the **Rows per Page** drop-down list, select the maximum number of hits you want displayed on a single page.
- 5. To save your search criteria for the next time you generate the report, click on the **Save Settings** button; otherwise, go to the next step without changing anything.
 - To view recurring transactions using cards that are about to expire, click on the Get Expiring Cards button.
- 6. Click on the Submit Search button (or Perform Query button).
- 7. When the "Transaction List" displays, click on the **Details** button of the recurring transaction that you want to alter.
- 8. When the "Order History" page displays, you may terminate the recurring transaction; update the recurring transaction's card data, address data, and customer details; and alter the recurrence frequency of the transaction:

To terminate the recurring transaction:

- a. In the "Recurring Details" area, click on the Terminate Payment button.
- b. When the "update successful" response displays, the operation is complete.

To update the card data of the recurring transaction:

a. In the "Payment Details" area, edit the payment fields as desired.

Note: If you are using the Managed Account Updater service (see page 231) and want to discontinue having the service update this profile, select the **Disable automatic card updates for this profile** box (this option may already be selected depending on the response of the updater service).

If you are using the managed account updater service, you may switch back and forth between using the older card data (Old Card Num) and the newly updated card data (New Card Num) by clicking on the **Revert** button. If the Updater service has changed the card data multiple times, you will only be able to revert the most recent update.

- b. Click on the **Update Card Data** button.
- c. When the "update successful" response displays, the operation is complete.

To update the address data of the recurring transaction:

- a. In the "Address Verification" area, edit the address fields as desired.
- b. Click on the **Update Details** button.
- c. When the "update successful" response displays, the operation is complete.

To update the customer data of the recurring transaction:

- a. In the "Customer Data" area, edit the customer fields as desired.
- b. Click on the **Update Customer Data** button.
- c. When the "update successful" response displays, the operation is complete.

To update the frequency of the recurring transaction:

- a. In the "Recurring Details" area, and do one of the following:
 - To change the duration of a recurring billing, enter a different number in the **Recurs Remaining** field.
 - To change the status of a recurring billing, mark a "Status" radio button. (If Hold is marked, the card will not be charged. If Active is marked, the recurring billing will continue.)
- b. Click on the **Update Recurring Details** button.
- c. When the "update successful" response displays, the operation is complete.

8.3 Recurring transactions report

Follow the steps below to generate a recurring transactions report.

- 1. On the menu bar, click on **Recurring > Recurring Reports**.
- 2. Wait for the "Recurring Transaction Reports" page to display.
- 3. Select a general date range, or specify your own date/time range:

To select a general transaction date range:

- a. In the "Date" area, mark the radio button under "Date".
- b. Select a date range from the adjacent drop-down list (**Today**, **Yesterday**, **This Week**, etc.).

To specify your own transaction date/time range:

- a. Mark the radio button beside the **From** drop-down list, and then select your "from-this-date" values (hh:mm DD/MM/YYYY).
- b. Mark the radio button beside the **To** drop-down list, and then select your "to-this-date" values (hh:mm DD/MM/YYYY).
- 4. Optionally narrow the search by transaction response, card type, or "other criteria (card number, Customer ID, Order ID, amount, and batch number) as follows:

To narrow the search by transaction response:

- a. Checkmark the **Transaction Response** box.
- b. In the "Transaction Response" area, checkmark the box beside any response type (**Approved**, **Declined**, and **Incomplete**) that you want to include in the report.

To narrow the search by card type:

- a. Checkmark the Card Type box.
- b. In the "Card Type" area, checkmark the box beside any card type that you want to include in the report.

To narrow the search by "other criteria":

- a. In the "Other Criteria" area, checkmark the box beside any of the other criteria (Card Number, Amount, Customer ID, Order ID, and Batch Number) that you want to include in the report.
- b. For any box that you checkmarked in the previous step, enter the required data in the corresponding field.
 - If you enter partial data, mark the begins with or ends with radio button.

- 5. In the "Sort By" area, set your sort order preference for listing the results:
 - a. From the "Sort Transactions by" drop-down list, select the order (**Date/Time** and **Order ID**) in which you want the hits to be listed.
 - b. From the "Rows per Page" drop-down list, select the maximum number of hits you want displayed on a single page.
- 6. To save your search criteria for the next time you generate the report, click on the **Save Settings** button; otherwise, leave the search configuration as is, and go to the next step.
- 7. Click on the Submit Search button (or Perform Query button).
- 8. When the "Transaction List" and "Query Totals" display, you may view a specific transaction (e.g., a Purchase) or the view the details of a recurring transaction profile.

Note: The "RECUR ORDER ID" links to the Order History of a specific financial transaction (e.g., a Purchase that occurred according to the recurring transaction profile setup). The "ORDER ID" links to the recurring transaction profile itself.

At a minimum, the transaction list will always include details such as the transaction date ("DATE/TIME"), transaction type ("TXN TYPE"), order ID ("ORDER ID"), and recurring order ID ("RECUR ORDER ID"). For other details that you may include or exclude from this transaction list, see page 182.

To export the transaction list to a text file, see page 173.

9 Vault

With the Vault feature, you can securely store data, including tokens and customer information, create customer profiles for future transactions, and update customer profiles.

- To register a new Vault profile, see page 148.
- To manage an existing Vault profile, see page 151.
- To view a Vault profile report, see page 160.
- To set up a hosted Vault configuration, see page 162.

9.1 Registering a Vault profile

Register a Vault profile.

• For the step-by-step instructions on how to use a supported card entry method to perform the registration, refer to the table below.

Card entry method	See procedure on:
unencrypted MSR	page 149
keyed entry	page 150

9.1.1 Registering a Vault profile: unencrypted MSR

Follow the steps below to register a Vault profile by using an unencrypted magnetic stripe reader to capture the credit card data for the profile.

Note: Some chip debit cards may be used for this transaction.

- 1. On the menu bar, click on Vault > Add Profile.
- 2. Wait for the "Add Profile" page to display.
- In the "Transaction Method" area, select Credit Card MSR from the drop-down list.
 - To obtain card verification results, checkmark the Perform card verification box.
- 4. In the "Profile Details" area, optionally enter profile details in the **Customer ID**, **Phone Number**, **Email Address** and **Special Instructions** fields.

Note: For information about fields referred to in the steps below, see page 221.

- If the "Address Verification" area displays, enter the billing address data in the Street Number, Street Name (use also to enter PO box data), and Zip/Postal Code fields (for a post office box, checkmark PO Box).
- 5. Click on the **Swipe Card to Register Profile** button.
- 6. When "Please swipe credit card now" displays on the "Add Profile" page, swipe the card on the unencrypted magnetic stripe reader.
- 7. When the "registration successful" response displays (the profile's alpha-numeric data key will also be displayed), the transaction is complete.

Important! Securely and confidentially store the data key for future reference. You will need to refer to this data key when you want to perform financial transactions with this Vault profile (see pages 29, 38, and 58).

- 8. In the "Action Items" area on the "Add Profile" page, you may perform the following transactions using the newly created Vault profile:
 - Purchase (see page 155).
 - Preauthorization (see page 156).
 - Independent Refund (see page 157).
 - Add a recurring transaction (see page 158).

9.1.2 Registering a Vault profile: keyed entry

Follow the steps to register a Vault profile by manually entering (keying in) card data in the Merchant Resource Center fields.

Note: Some chip debit cards may be used for this transaction.

- 1. On the menu bar, click on Vault > Add Profile.
- 2. Wait for the "Add Profile" page to display.
- 3. In the "Transaction Method" area, select **Credit Card Keyed Entry** from the drop-down list.
 - To obtain card verification results, checkmark the Perform card verification box.
- 4. In the "Profile Details" area, optionally enter profile details in the **Customer ID**, **Phone Number**, **Email Address**, and **Special Instructions** fields.
- 5. In the "Payment Details" area, do the following:

Note: For information about fields referred to in the steps below, see page 221.

- a. In the Credit Card Number field, enter the card account number.
- b. In the **Expiry Date** field, enter the card expiry date (MMYY).
- c. From the "ECI Indicator" drop-down list, select an e-commerce descriptor.
 - If the "Address Verification" area displays, enter the billing address data in the Street Number, Street Name (use also to enter PO box data), and Zip/Postal Code fields (for a post office box, checkmark PO Box).
- 6. Click on the Register Profile button.
- 7. When the "registration successful" response and the associated data key (an alpha-numeric string) are displayed on the "Add Profile" page, the transaction is complete.

Important! Securely and confidentially store the data key for future reference. You will need to refer to this data key when you want to perform financial transactions with this Vault profile at a later time (see pages 29, 38, and 58).

- 8. While the "Add Profile" page is displayed, you may perform the following transactions using the newly created Vault profile:
 - Purchase (see page 155).
 - Preauthorization (see page 156).
 - Independent Refund (see page 157).
 - Add recurring transaction (see page 158).

9.2 Managing a Vault profile

Follow the steps below to retrieve a previously registered Vault profile so that you can alter its characteristics or delete it.

- 1. On the menu bar, click on Vault > Manage Profiles.
- 2. Wait for the "Manage Profiles" page to display.
- 3. Optionally narrow the search by create date, "other" criteria (see below), and/or card expiry date:

Narrow the search by profile create date

- a. In the "Create Date" area, checkmark the Create Date box.
- b. Select a general date range from the drop-down list (e.g., **Today**, **Yesterday**, etc.), or select a specific time and date range (hh:mm DD/MM/YYYY) from the **From/To** drop-down lists.

Narrow the search by other criteria

- a. Checkmark the box beside one or more of the following criteria: **Data Key**, **Customer ID**, **Email Address**, and/or **Managed Account Update Ignore**.
- b. For any box that you checkmarked in the previous step, enter the required data in the corresponding field.

Narrow the search by card expiry date

- a. In the "Get Expiring Cards" area, checkmark the **Get Expiring Cards** box.
- b. From the **Expiring Within** drop-down list, select a general date range.
- 4. In the "Sort By" area, set your sort order preference for listing the results:
 - a. From the "Sort Transactions by" drop-down list, select the order in which you want the hits to be listed (**Create Date**, **Data Key**, **Email Address**, etc.).
 - b. From the "Rows per Page" drop-down list, select the maximum number of hits you want displayed on a single page.
 - c. From the "Sort Order" drop-down list, select an ascending/descending order.
- 5. To save your search criteria for the next time you do the report, click on the **Save Settings** button; otherwise, go to the next step without changing anything.
- 6. Click on the **Submit Search** button (or **Perform Query** button).
- 7. Wait for the "Transaction List" to display, and then click on the **Details** button of the Vault profile that you want to view.
- 8. When the "Profile Details" page displays, you may alter the profile or initiate a financial transaction:

Altering/viewing the Vault profile:

- To update the Vault profile, see page 153.
- To delete the Vault profile, see page 154.

Initiating a financial transaction from the Vault profile:

- a. While the "Profile Details" page is displayed, you may initiate one or more of the following transactions using the Vault profile:
 - Purchase (see page 155).
 - Preauthorization (see page 156).
 - Independent Refund (see page 157).
 - Add recurring transaction (see page 158).

9.2.1.1 Updating the Vault profile

Once you have retrieved a Vault profile (see page 151) and its "Profile Details" page is displayed, follow the steps below to update the profile.

1. Do one or more of the following:

To update the profile contact details:

a. In the "Profile Details" area, enter the new data as desired in the profile fields (Customer ID, Email Address, Phone Number, and Special Instructions).

To update the payment details:

a. In the "Payment Details" area, enter the new data as desired in payment fields (Card Number and Expiry Date), and select an e-commerce descriptor from the "ECI Indicator" drop-down list.

To update the address verification details:

- a. In the "Address Verification" area, enter the address data as desired in the address fields (Street Name, Street Number, and Zip/Postal Code).
- 2. When you are finished entering the new data, click on the **Update Profile** button.
- 3. When the "update successful" response displays on the "Profile Details" page, the operation is complete.

Deleting the Vault profile 9.2.1.2

Once you have retrieved a Vault profile (see page 151) and its "Profile Details" page is displayed, follow the steps below to delete the profile.

Important! Once a profile is deleted, it cannot be re-opened.

- 1. Click on the **Delete Profile** button.
- 2. Wait for the "Confirm Profile Deletion Step 1" details to display.
- 3. Click on the **Confirm** button.
- 4. When the "profile deleted" message displays on the "Profile Details" page, the operation is complete.

9.2.1.3 Vault Purchase with debit/credit card

Once a Vault profile is registered and the profile details are displayed, follow the steps below to use the Vault profile to perform a debit/credit Purchase.

- 1. In the "Action Items" area, click on the **Purchase** button.
- 2. Wait for the "Vault Purchase" page to display.
- 3. In the "Payment Details" area, do the following:

Note: For information about fields referred to in the steps below, see page 221.

- a. In the Order ID field, optionally enter an Order ID.
- b. In the **Customer ID** field, optionally enter a Customer ID.
- c. In the **Statement Descriptor** field, enter a descriptor for the card statement.
- d. In the Amount field, enter the Purchase amount (#.##).
- e. In the Card Verification Digits field, enter the card verification digits.
- f. From the "ECI Indicator" drop-down list, select an e-commerce descriptor.
 - If the "Address Verification" area displays, confirm that the Street
 Number, Street Name, and Zip/Postal Code fields are populated with the correct billing address data.
 - To add order details (shipping/billing and product details), see page 64.
- 4. Click on the Process Transaction button.
- When the "APPROVED" or DECLINED" response displays on the "Vault Purchase" page, the transaction is complete.
- 6. Print/e-mail the transaction receipt now (see page 83).

Note: Moneris loyalty points cannot be awarded for a Purchase that is initiated from the Vault "Profile Details" page.

9.2.1.4 Vault Preauthorization with debit/credit card

Once a Vault profile is registered and the profile details are displayed, follow the steps below to use the Vault profile to perform a debit/credit Preauthorization.

Important! To receive the funds for this transaction, you must perform a debit/credit Capture at a later time (see page 43).

Note: If a purchasing card is registered to the Vault profile and your store is enabled for level 2/3 reporting (see page 232), you may be prompted to add level 2/3 details during the Capture.

- 1. In the "Action Items" area, click on the **Preauthorization** button.
- 2. Wait for the "Vault Preauthorization" page to display.
- 3. In the "Payment Details" area, do the following:

Note: For information about fields referred to in the steps below, see page 221.

- a. In the Order ID field, optionally enter an Order ID.
- b. In the **Customer ID** field, optionally enter a Customer ID.
- c. In the **Statement Descriptor** field, enter a descriptor for the card statement.
- d. In the **Amount** field, enter the Preauthorization amount (#.##).
- e. In the Card Verification Digits field, enter the card verification digits.
- f. From the "ECI Indicator" drop-down list, select an e-commerce descriptor.
 - If the "Address Verification" area displays, confirm that the Street
 Number, Street Name, and Zip/Postal Code fields are populated with the correct billing address data.
 - To add order details (shipping/billing and product details), see page 64.
- 4. Click on the Process Transaction button.
- 5. When the "APPROVED" or DECLINED" response displays on the "Vault Preauthorization" page, the transaction is complete.
- 6. Print/e-mail the transaction receipt now (see page 83).

Note: Moneris loyalty points cannot be allocated for a Preauthorization that is initiated from the Vault "Profile Details" page.

9.2.1.5 Vault Independent Refund with debit/credit card

Once a Vault profile is registered and the profile details are displayed, follow the steps below to use the Vault profile to perform a debit/credit Independent Refund (reverses a transaction that is not referenced on the Merchant Resource Center).

- 1. In the "Action Items" area, click on the **Independent Refund** button.
- 2. Wait for the "Vault Independent Refund" page to display.
- 3. In the "Payment Details" area, fill in the remaining fields:
 - a. In the Order ID field, optionally enter an Order ID.
 - b. In the **Customer ID** field, optionally enter a Customer ID.
 - c. In the **Statement Descriptor** field, enter a descriptor for the card statement.
 - d. In the Amount field, enter the Independent Refund amount (#.##).
 - e. In the Card Verification Digits field, enter the card verification digits.
- 4. Click on the Process Transaction button.
- 5. When the "APPROVED" or DECLINED" response displays on the "Vault Independent Refund" page, the transaction is complete.
- 6. Print/e-mail the transaction receipt now (see page 83).

9.2.1.6 Vault Add Recurring Transaction with debit/credit card

Once a Vault profile is registered and the profile details are displayed, follow the steps below to use the Vault profile to register a recurring (Purchase) transaction that is set to recur at regular intervals.

- 1. In the "Action Items" area, click on the Add Recurring Transaction button.
- 2. Wait for the "Vault Add Recurring Transaction" page to display.
- 3. In the "Payment Details" area, do the following:
 - a. In Order ID field, optionally enter an Order ID.
 - b. In the **Customer ID** field, optionally enter a Customer ID.
 - c. In the Card Verification Digits field, enter the card verification digits.
 - d. From the "ECI Indicator" drop-down list, select an e-commerce descriptor.
 - If the "Address Verification" area displays, confirm that the Street Number, Street Name, and Zip/Postal Code fields are populated with the correct billing address data.
- 4. In the "Recurring Details" area, do the following:
 - a. Mark a "Bill Now" radio button:
 - To start billing when the transaction is registered, mark the YES radio button, and enter the first billing amount in the Bill Now Amount field.
 - To start billing some time after the transaction is registered, mark the NO radio button.
 - b. In the **Recurring Amount** field, enter the amount to be billed at the specified recur start time.
 - c. From the **Start Date** drop-down list, select the date on which billing is to commence.
 - d. In the **Recur Every** field, enter a number that defines the interval of a single billing to the card (billing does not include the "BILL NOW" amount if this option was selected in step a).
 - **Note:** If you enter **8** for example, billing will occur after eight undefined periods of time have elapsed. (You define the periods of time in step e.)
 - e. From the "Recur Every" drop-down list, select the time frame (e.g., day(s), month(s), year(s)) to define the interval of a single billing.
 - **Note:** If **month(s)** is selected for example, the card will be billed once every "X" number of months. ("X" is defined by what you entered in step d.)
 - f. In the **Number of Recurs** field, enter a number that defines how many times a card should be billed not including the "Bill Now" option.

Note: If you enter **5** for example, a single billing will occur five times at whatever interval you specified in steps d and e.

- g. In the "Customer Details" area, enter data in the customer details fields (First Name, Last Name, Company, Address, City, State/Prov, Postal Code, Country, Phone, and Fax).
- 5. Click on the **Process Transaction** button.
- 6. When the "successfully registered" response displays on the "Vault Add Recurring Transaction" page, the operation is complete.

9.3 Vault report

Follow the steps below to generate a report about Vault profiles used to process transactions from your Merchant Resource Center store within the last 18 months.

- 1. On the menu bar, click on Vault > Vault Reports.
- 2. Wait for the "Vault Reports" page to display.
- 3. Select a date range to which to narrow the search for Vault-sourced transactions:

To select a general transaction date range:

- a. In the "Date" area, mark the radio button under "Date".
- b. Select a general date range (**Today**, **Yesterday**, **This Week**, etc.) from the adjacent drop-down list.

To specify your own transaction date/time range:

- a. Mark the radio button beside the **From** drop-down list, and then select your "from-this-date" values (hh:mm DD/MM/YYYY).
- b. Mark the radio button beside the **To** drop-down list, and then select your "to-this-date" values (hh:mm DD/MM/YYYY).
- 4. Optionally narrow the search by transaction type, transaction response, card type, or "other" criteria (see below) as follows:

To narrow the search by transaction type

- a. Checkmark the **Transaction Type** box.
- b. In the "Transaction Type" area, checkmark the box beside any transaction type (**Purchase**, **Refund**, and **Ind**. **Refund**) that you want to include in the report.

To narrow the search by transaction response:

- a. Checkmark the **Transaction Response** box.
- b. In the "Transaction Response" area, checkmark the box beside any transaction response type (**Approved**, **Declined**, and **Incomplete**) that you want to include in the report.

To narrow the search by payment type:

- a. Checkmark the **Payment Type** box.
- b. In the "Payment Type" area, checkmark the box beside any card type that you want to include in the report.

Note: To retrieve Visa Debit card transactions, checkmark the **Visa** box.

To narrow the search by "other criteria":

- a. In the "Other Criteria" area, checkmark the box beside any other criteria (Card Number, Amount, Customer ID, Data Key, Order ID, and Batch Number, ECI, and Username) that you want to include in the report.
- b. For any box that you checkmarked in the previous step, enter the required data in the corresponding field and/or make a selection from the corresponding drop-down list where applicable.
 - If you enter partial data, mark the **begins with** or **ends with** radio button.
- 5. In the "Sort By" area, set your sort order preference for listing the results:
 - a. From the "Sort Transactions by" drop-down list, select the order (**Date/Time**, **Order ID**, **Amount**, etc.) in which you want the hits to be listed.
 - b. From the "Rows per Page" drop-down list, select the maximum number of hits you want displayed on a single page.
 - c. From the "Sort Order" drop-down list, select an ascending/descending order.
- 6. Do one of the following:

Save the search criteria as the default, and generate the full report:

- a. Click on the Save Settings button.
- b. Click on the **Perform Query** button.

No change to default search criteria, and generate the full report:

- a. Click on the Submit Search button.
- 7. When the "Transaction List" and "Query Totals" display, the operation is complete.

Note: At a minimum, the transaction list will always include details such as the transaction date ("DATE/TIME"), transaction type ("TXN TYPE"), order ID ("ORDER ID"), and data key ("DATA KEY"). For other details that you may include or exclude from this transaction list, see page 182.

To export the transaction list to a text file, see page 173.

9.4 Hosted Vault configuration

This feature allows for the integration of the Vault into an independent merchant Website or application. The collection of the secure credit card or bank account data is handled on a secure Moneris Hosted Page.

Each account may have up to five unique Hosted Vault Page configurations. Please note that these configurations do not equate to different stores: All profiles are added to the same store. Each configuration can have a differing appearance as well as handle responses in varying ways.

For information about how to view or download detailed Hosted Paypage configuration instructions, see page 238.

10 Reports

From your Merchant Resource Center store, you may generate/view detailed transaction and batch reports regarding all transactions processed from your store. The following reports may be generated from the Moneris Merchant Resource Center:

Debit/credit and cash

Report type	See procedure on :
Transactions (single)*	page 164
Grouped transactions	page 166
Managed account updater	page 169
Batches	page 171

^{*} For recurring transactions report, see page 145.

Gift/loyalty

Report type	See procedure on:
Transactions	page 167
Batches	page 171

Batches:

Report type	See procedure on :
batches	page 171

^{*} For Vault profile-originated transactions report, see page 160.

10.1 Transactions report: debit/credit cards and cash

Follow the steps below to generate a report about debit/credit and cash transactions processed on your Merchant Resource Center store within the last 18 months.

- 1. On the menu bar, click on **Reports** > **Transactions**.
- 2. Wait for the "Transaction Reports" page to display.
- 3. Select a date range to which to narrow the search for transactions:

To select a general transaction date range:

- a. In the "Date" area, mark the radio button under "Date".
- b. Select a general date range (**Today**, **Yesterday**, **This Week**, etc.) from the adjacent drop-down list.

To specify your own transaction date/time range:

- a. Mark the radio button beside the **From** drop-down list, and then select your "from-this-date" values (hh:mm DD/MM/YYYY).
- b. Mark the radio button beside the **To** drop-down list, and then select your "to-this-date" values (hh:mm DD/MM/YYYY).
- 4. Optionally narrow the search by transaction type, transaction response, card type, or "other" criteria (see below) as follows:

To narrow the search by transaction type:

- a. Checkmark the Transaction Type box.
- b. In the "Transaction Type" area, checkmark the box beside any transaction type (**Purchase**, **Refund**, **Void**, etc.) that you want to include in the report.

Note: Checkmarking the **Preauth/w pending capture** box will retrieve Preauthorizations that have not yet been captured.

To narrow the search by transaction response:

- a. Checkmark the **Transaction Response** box.
- b. In the "Transaction Response" area, checkmark the box beside any transaction response type (**Approved**, **Declined**, and **Incomplete**) that you want to include in the report.

To narrow the search by card type:

- a. Checkmark the **Card Types** box.
- b. In the "Card Types" area, checkmark the box beside any card type that you want to include in the report.

Note: To retrieve Visa Debit card transactions, checkmark the **Visa** box.

To narrow the search by "other criteria":

 a. In the "Other Criteria" area, checkmark the box beside any other criteria (Card Number, Amount, Customer ID, Order ID, Customer Code, Invoice Number, Amount, Batch Number, Username, ECI, and Store ID) that you want to include in the report.

Note: The **Store ID** option is available only when multi-store login is enabled (see page 209) and you have switched between linked stores at least once during your login session.

- b. For any box that you checkmarked in the previous step, enter the required data in the corresponding field and/or make a selection from the corresponding drop-down list where applicable.
 - If you enter partial data, mark the begins with or ends with radio button.
- 5. In the "Sort By" area, set your sort order preference for listing the results:
 - a. From the "Sort Transactions by" drop-down list, select the order (**Date/Time**, **Order ID**, **Amount**, etc.) in which you want the hits to be listed.
 - b. From the "Rows per Page" drop-down list, select the maximum number of hits you want displayed on a single page.
 - c. From the "Sort Order" drop-down list, select an ascending/descending order.
- 6. Do one of the following:

Save the search criteria as the default, and generate the full report:

- a. Click on the **Save Settings** button.
- b. Click on the **Perform Query** button.

No change to default search criteria, and generate the full report:

a. Click on the **Submit Search** button.

Generate a totals report:

- a. Click on the Query Totals button.
- 7. When the "Transaction List" and/or the "Query Totals" displays, the operation is complete.

Note: At a minimum, the transaction list will always include details such as the transaction date ("DATE/TIME"), transaction type ("TXN TYPE"), order ID ("ORDER ID"), and follow-on transaction ("FOLLOW-ON"). For other details that you may include or exclude from this transaction list, see page 182.

To export the transaction list to a text file, see page 173.

10.2 Transactions report: grouped transactions

Follow the steps below to generate a report about debit/credit group transactions processed on your Merchant Resource Center store within the last 18 months.

- 1. On the menu bar, click on **Reports** > **Group Transaction Reports**.
- 2. Wait for the "Group Transaction Reports" page to display.
- 3. Select a date range to which to narrow the search for grouped transactions:

To select a general transaction date range:

- a. In the "Date" area, mark the radio button under "Date".
- b. Select a general date range (**Today**, **Yesterday**, **This Week**, etc.) from the adjacent drop-down list.

To specify your own transaction date/time range:

- a. Mark the radio button beside the **From** drop-down list, and then select your "from-this-date" values (hh:mm DD/MM/YYYY).
- b. Mark the radio button beside the **To** drop-down list, and then select your "to-this-date" values (hh:mm DD/MM/YYYY).
- 4. Optionally narrow the search by username and/or ticket # as follows:
 - a. In the "Other Criteria" area, checkmark the box beside any criteria (**Username** and **Ticket #**) that you want to include in the report.
 - b. For any box that you checkmarked in the previous step, enter the required data in the corresponding field and/or make a selection from the corresponding drop-down list where applicable.
 - If you enter partial data, mark the **begins with** or **ends with** radio button.
- 5. To save your search criteria for the next time you do the report, click on the **Save Settings** button; otherwise, go to the next step without changing anything.
- 6. Click on the Submit Search button (or Perform Query button).
- 7. When the report displays, click on the **Details** button beside the grouped transactions about which you want to view more details (grouped transactions are listed by date/time, ticket number, and username).
- When the "Transaction List" and "Query Totals" display, the operation is complete.

Note: At a minimum, the transaction list will always include details such as the transaction date ("DATE/TIME"), transaction type ("TXN TYPE"), and order ID ("ORDER ID"). For other details that you may include or exclude from this transaction list, see page 182.

10

10.3 Transactions report: gift/loyalty cards

Follow the steps below to generate a report about gift/loyalty transactions processed on your Merchant Resource Center store within the last 18 months.

- 1. On the menu bar, click on Reports > Gift Transactions.
- 2. Wait for the "Gift/Loyalty Transaction Reports" page to display.
- 3. Select a date range to which to narrow the search for gift/loyalty transactions:

To select a general transaction date range:

- a. In the "Date" area, mark the radio button under "Date".
- b. Select a general date range (**Today**, **Yesterday**, **This Week**, etc.) from the adjacent drop-down list .

To specify your own transaction date/time range:

- a. Mark the radio button beside the **From** drop-down list, and then select your "from-this-date" values (hh:mm DD/MM/YYYY).
- b. Mark the radio button beside the **To** drop-down list, and then select your "to-this-date" values (hh:mm DD/MM/YYYY).
- 4. Optionally narrow the search by transaction type, transaction response, or "other" criteria (see below) as follows:

To narrow the search by transaction type:

- a. Checkmark the Transaction Type box.
- b. In the "Transaction Type" area, checkmark the box beside any transaction type (**Purchase**, **Refund**, **Void**, etc.) that you want to include in the report.

To narrow the search by transaction response:

- a. Checkmark the Transaction Response box.
- b. In the "Transaction Response" area, checkmark the box beside any transaction response type (**Approved**, **Declined**, and **Incomplete**) that you want to include in the report.

To narrow the search by other criteria:

- a. In the "Other Criteria" area, checkmark the box beside any of the "other" criteria (Card Number, Customer ID, Order ID, Batch Number, and Username) that you want to include in the report.
- b. For any box that you checkmarked in the previous step, enter the required data in the corresponding field and/or make a selection from the drop-down list where applicable.
 - If you enter partial data, mark the begins with or ends with radio button.

- 5. In the "Sort By" area, set your sort order preference for listing the results:
 - a. From the "Sort Transactions by" drop-down list, select the order in which you want the hits to be listed (**Date/Time**, **Order ID**, **Amount**, etc.).
 - b. From the "Rows per Page" drop-down list, select the maximum number of hits you want displayed on a single page.
 - c. From the "Sort Order" drop-down list, select an ascending/descending order.
- 6. Do one of the following:

Save the search criteria as the default, and generate the full report:

- a. Click on the Save Settings button.
- b. Click on the **Perform Query** button.

No change to default search criteria, and generate the full report:

a. Click on the Submit Search button.

Generate a totals report

- a. Click on the Query Totals button.
- When the "Transaction List" and "Query Totals" display, the operation is complete.

Note: At a minimum, the transaction list will always include details such as the transaction date ("DATE/TIME"), transaction type ("TXN TYPE"), order ID ("ORDER ID"), and follow-on transaction ("FOLLOW-ON"). For other details that you may include or exclude from this transaction list, see page 182.

To export the transaction list to a text file, see page 173.

10.4 Transactions report: cash

See Transactions report: debit/credit cards and cash (page 164).

10

10.5 Managed account updater report

Follow the steps below to generate a report about registered Vault profiles and/or recurring transaction profiles for which card data have changed due to an update made through the managed account updater service (see page 231).

- 1. On the menu bar, click on **Reports > Managed Account Updater**.
- 2. Wait for the "Managed Account Updater Reports" page to display.
- 3. Select a date range to which to narrow the managed account updater search:

To select a general transaction date range:

- a. In the "Date" area, mark the radio button under "Date".
- b. Select a general date range (**Today**, **Yesterday**, **This Week**, etc.) from the adjacent drop-down list.

To specify your own transaction date/time range:

- a. Mark the radio button beside the **From** drop-down list, and then select your "from-this-date" values (hh:mm DD/MM/YYYY).
- b. Mark the radio button beside the **To** drop-down list, and then select your "to-this-date" values (hh:mm DD/MM/YYYY).
- 4. Optionally narrow the search by account type and/or card type as follows:

To narrow the search by account type:

- a. Checkmark the **Account Type** box.
- b. In the "Account Type" area, checkmark the box beside any account type (Vault or Recur) that you want to include in the report.

To narrow the search by card type:

- a. Checkmark the **Card Types** box.
- b. In the "Card Types" area, checkmark the box beside any card type that you want to include in the report.
- 5. In the "Sort By" area, set your sort order preference for listing the results:
 - a. From the Sort Transactions by drop-down list, select the order (**Date/Time** or **Order ID/Data Key**) in which you want the hits to be listed.
 - b. From the "Rows per Page" drop-down list, select the maximum number of hits you want displayed on a single page.
 - c. From the "Sort Order" drop-down list, select an ascending/descending order.
- 6. Click on the **Submit Search** button.

- 7. When the "Transaction List" and "Query Totals" display, the operation is complete.
 - To export the transaction list to a text file, see page 173.
- 8. Please note that managed account updater totals are shown at the top of the report. Totals are broken down into five categories:
 - **CLOSED:** Indicates the card (account) number registered to a Vault profile or recurring transaction on your store has been closed/cancelled. The card should not be used to process transactions.
 - CONTACT: Indicates the cardholder should be contacted for further details regarding the card (account) number registered to the Vault profile or recurring transaction on your store. The card should not be used to process transactions.
 - **EXPIRY:** Indicates the card (account) number registered to a Vault profile or recurring transaction on your store has expired but has since been updated. The card can be used to process transactions.
 - UPDATE: Indicates the card (account) number registered to a Vault profile or recurring transaction has been updated. This card can be used to process transactions.

10.6 Batches report: all card transactions

Follow the steps below to generate a report about all batches processed within the last 18 months from your Merchant Resource Center store.

Note: Cash transactions are not included in totals.

- 1. On the menu bar, click on Reports > Batches.
- 2. Wait for the "Batch Reports" page to display.
 - If the "Store ID" area displays, select the Merchant Resource Center store about which you want to generate the report.

Note: This option is available only if multi-store login is enabled (See page 209).

3. Select a general date range, or specify your own date/time range:

To select a general batch date range:

- a. In the "Date" area, mark the radio button under "Date".
- b. Select a general date range (**Current Open Batches**, **Today**, **Yesterday**, etc.) from the adjacent drop-down list.

To specify your own batch date/time range:

- a. Mark the radio button beside the **From** drop-down list, and then select your "from-this-date" values (hh:mm DD/MM/YYYY).
- b. Mark the radio button beside the **To** drop-down list, and then select your "to-this-date" values (hh:mm DD/MM/YYYY).
- 4. Optionally narrow the search as follows:

To narrow the search by batch status:

- a. Checkmark the batch status box.
- b. In the "Batch Status" area, mark the radio button beside the status type (In Balance or Out of Balance) that you want to include in the report.

To narrow the search by batch number:

- a. Checkmark the Batch Number box.
- b. In the "Batch Number" area (**Batch Number** field), enter the batch number that you want to include in the report.

To narrow the search by batch status

- a. Checkmark the Terminal ID box.
- b. In the "Terminal ID" area, checkmark the box beside any terminal ID that you want to include in the report.

Note: If a terminal ID is greyed, it means that it has been deactivated.

- 5. In the "Sort By" area, set your sort order preference for listing the results:
 - a. From the "Sort Batches by" drop-down list, select the order (**Terminal ID**, **Date/Time**, or **Batch Status**) in which you want the hits to be listed.
- 6. To save your search criteria for the next time you do the report, click on the **Save Settings** button; otherwise, go to the next step without changing anything.
- 7. Click on the **Submit Search** button (or **Perform Query** button).
- 8. When the "Query Results" list displays, click on the **Details** button beside the batch about which you want to view more details.
- 9. When the "Transaction List" and "Query Totals" display on the "Batch Details" page, the operation is complete.

Note: At a minimum, the transaction list will always include details such as the transaction date ("DATE/TIME"), transaction type ("TXN TYPE"), and order ID ("ORDER ID"). For other details that you may include or exclude from this transaction list, see page 182.

To export the transaction list to a text file, see page 173.

10.7 Exporting a report (transaction list) to a file

Follow the steps below to export a report's transaction list to a text file.

Note: The transaction list will be generated in comma-separated-values (CSV) format.

- 1. Generate a report (see page 163).
- 2. Once the report results ("Transaction List") are displayed, locate the **Export Transactions To File** button, and then click on it.
- 3. When the .txt file is generated, download and/or open the file.

Note: To configure which transaction list data are included in the file, see page 184.

4. The operation is complete.

11 End-of-day procedure

To ensure that funds are deposited to your merchant account the next business day, follow the appropriate end-of-day procedure.

If your Merchant Resource Center store is set to manual batch close (see page 195):

Close your batch(es) before 11 PM Eastern Standard Time by following the steps below.

- 1. On the menu bar, click on Reports > Batches.
- 2. Wait for the "Batch Reports" page to display.
- 3. Close a batch:
 - a. In the "Terminal ID" area, locate the batch that you want to close, and click on the corresponding **Close Batch** button.
 - b. Wait for the "Batch Close" page to display.
 - c. Confirm that the "Batch Close Successful" response displays in the "Batch Close Results" area.
 - d. Click on the Continue button.
- 4. Repeat steps 3a-d for each of your remaining batches.
- 5. The operation is complete.
- 6. To determine if the batch/batches that you closed is/are in balance, generate a Batches report (see page 171).

Note: If the report indicates an "Out of Balance" status for any batch, contact Moneris within 5 business days for assistance.

If your Merchant Resource Center store is set to automatic batch close (see page 195):

 If Moneris Gift/Loyalty is enabled on your store, manually close the gift/loyalty batch between 10 PM and 11PM Eastern Standard Time (follow steps 1-6 above).

Note: To determine which terminal ID represents your gift/loyalty batch, contact Moneris.

2. To determine if your closed batch/batch(es) are in balance, generate a Batches report (see page 171).

Note: If the report indicates an "Out of Balance" status for any batch, contact Moneris within 5 business days for assistance.

12 Managing your own user profile

From your Merchant Resource Center store, you may configure settings (listed below) that affect only user profile.

Note: To configure settings that affect all other users and your Merchant Resource Center store, use the Admin functions (see page 186).

User profile information

- Login password (see page 176).
- Security questions/answers (see page 177).
- Registered e-mail address (see page 177).

Default page

See page 178.

Transaction settings

- Default card entry method (see page 179).
- Default electronic commerce indicator (see page 180).
- Default display language (see page 180).
- Default PINpad com port number (see page 181).
- Default headers/fields to include your transaction report summaries (see page 182).
- Default headers/fields to include reports that you export to a CSV-format file (see page 184).

Login history

See page 185

12.1 Modifying your user profile's login information

12.1.1 Modifying your login password

Follow the steps below to modify your user profile's login password.

- 1. On the menu bar, click on **Firstname Last Name > Account Information**.
- 2. Wait for the "Account Information" page to display.
- 3. In the "Change Password" area, do the following:
 - a. In the **Old Password** field, enter your current password.
 - b. In the New Password field, enter your new password.

Note: The new password must adhere to these restrictions (password fields are case sensitive): include 7-16 characters; start with a letter; contain a number; and cannot be the same as the previous 4 passwords.

- c. In the **Confirm New Password** field, enter the same password as you did in the previous step.
- d. Click on the **Change Password** button.

Note: You must change your password periodically. If your password expires, you will be prompted to create a new password.

Important! Passwords should be kept confidential and not shared with any one. Change your password immediately if you have any reason to believe that someone else has access to it or has tried to log into your account.

4. When the "success" message displays, the operation is complete.

Follow the steps below to modify one or more of your Security pass-phrase questions/answers. Periodically you will be prompted to answer one of these questions before being logged in.

12

- 1. On the menu bar, click on **Firstname Lastname > Account Information**.
- 2. Wait for the "Account Information" page to display.
- 3. In the "Security Question and Answers" are a, optionally update one or more of your security questions/answers as follows:
 - a. Select a question from a **Security Question #** drop-down list.
 - b. In the corresponding **Security Answer** # and **Confirm Answer** fields, enter a new answer.
 - c. Repeat steps 3a to b for any remaining question/answer that you want to modify.
- 4. When you are finished, click on the Save Reset Password Data button.
- 5. When the "success" message displays, the operation is complete.

12.1.3 Modifying your registered e-mail address

Follow the steps below to modify the e-mail address currently registered to your user profile.

Note: If you need to have your password reset, a temporary password will be sent to this e-mail address.

- 1. On the menu bar, click on **Firstname Lastname > Account Information**.
- 2. Wait for the "Account Information" page to display.
- 3. In the "Security Question and Answers" area, do the following:
 - a. In the **Email address** field, enter the new e-mail address that you want to register for your user profile.
- 4. When you are finished, click on the **Save Reset Password Data** button.
- 5. When the "success" message displays, the operation is complete.

12.2 Modifying your user profile's default transaction settings

12.2.1 Setting your Merchant Resource Center default page

Follow the steps below to specify a Merchant Resource Center default page for your user profile. Once the default page is set, it will display each time you log into the Merchant Resource Center.

Note: If no default page is specified, the "Merchant Resource Center" main page will display each time you log in.

- 1. Log into the Merchant Resource Center (see page 5).
- 2. Click on a Merchant Resource Center menu bar item, and wait for the corresponding page to display (e.g., if you click on **Terminal** > **Purchase**, the "Purchase" page will be displayed).
- 3. Once the desired Merchant Resource Center page is displayed, click on the Favourite ricon (e.g., if the "Purchase" page is displayed, it will be set as your default page).
- 4. The operation is complete.

Note: The default page will display each time you log into the Merchant Resource Center.

Follow the steps below to specify the default card entry method for your user profile.

Note: You may alter the card entry method on a transaction-by-transaction basis.

- 1. On the menu bar, click on Firstname_Lastname > Account Settings.
- 2. Wait for the "Account Settings" page to display.
- 3. In the "Default Transaction Method" area, do the following:
 - a. From the "Default Transaction Method" drop-down list, select a new default card entry method for your user profile:

12

Card entry method	Description
Keyed	Manually capture card data by entering it directly in Merchant Resourced Center fields.
Mag swipe reader	Capture card data by swiping the card on an unencrypted magnetic stripe reader that is connected to your computer.
Pinpad	Capture the card data by inserting, tapping, swiping, or manually entering (keying) the card on an iPP320 PINpad that is connected to your computer (see page 13).

- b. Click on the Save Transaction Method button.
- 4. When the "success" message displays above the button, the operation is complete.

12.2.3 Setting your default electronic commerce indicator

Follow the steps below to specify the default electronic commerce indicator for your user profile.

Note: You may alter the electronic commerce indicator on a transaction-by-transaction basis.

- 1. On the menu bar, click on **Firstname Lastname > Account Settings**.
- 2. Wait for the "Account Settings" page to display.
- 3. In the "Default Transaction ECI" area, do the following:
 - a. From the "Default ECI" drop-down list, select a new default electronic commerce indicator for your user profile (for list of indicators, see page 223).
 - b. Click on the Save Default ECI button.
- 4. When the "success" message displays above the button, the operation is complete.

12.2.4 Setting your default display language

Follow the steps below to specify the default language for your user profile. The Merchant Resource Center will default to the set language the next time you log in.

Note: Regardless of how you configure this setting, you may change the electronic commerce indicator at the time you are performing a financial transaction.

- 1. On the menu bar, click on **Firstname_Last Name > Account Settings**.
- 2. Wait for the "Account Settings" page to display.
- 3. In the "Default Lanague" area, do one of the following:
 - To select English as the default language, mark the English radio button
 - To select French as the default language, mark the French radio button.
- 4. Click on the Save Default Language button.
- 5. When the "success" message displays above the button, the operation is complete.

12.2.5 Setting your default PINpad com port number

Follow the steps below to specify the default com port number that the iPP320 PINpad is using while it is connected to the computer from which you are performing Merchant Resource Center financial transactions.

12

Note: Before you attempt to perform PINpad transactions on another computer, you must first update this Merchant Resource Center com port setting and ensure it is still valid for your PINpad connection.

- 1. On the menu bar, click on Firstname Lastname > Account Settings.
- 2. Wait for the "Account Settings" page to display.
- 3. In the "PInpad COM Port" area, do the following:
 - a. In the **Pinpad COM Port** field, enter the com port being used by the iPP320 PINpd while it is connected to your computer.
 - b. Click on the Save COM port button.
- 4. When the "success" message displays above the button, log out of the Merchant Resource Center, close your browser, and then log back in.
- 5. The operation is complete.

Setting the default headers/fields to include a report's 12.2.6 transaction list

Follow the steps below to specify the headers/fields that you want to include in any applicable report (transaction list) generated from your Merchant Resource Center store.

- 1. On the menu bar, click on Firstname Lastname > Account Settings.
- 2. Wait for the "Account Settings" page to display.
- 3. In the "Transaction Summary Fields" area, checkmark the box beside any field (bolded in the table below) that you want to include in an applicable report's transaction list.

Note: Each field has a corresponding header, will display at the top of the transaction list if you checkmark the field.

In the table below, a black dot (" •") indicates that the report supports the corresponding field/header. A hyphen ("-") indicates that the report does not support the corresponding field/header.

D/C = debit/credit transactions report (see page 164);

Group = group transactions report (see page 166);

G/L = qift/loyalty transactions report (see page 167);

R = Recurring transactions report (see page 145);

V = Vault transaction report (see page 160);

B = Batches report (see page 171)

Field	Header	D/C	Group	G/L	R	V	В
Amount 1	"AMOUNT"	•	•	•	•	•	•
Authorization Code ²	"AUTH CODE"	•	•	-	•	•	•
AVS Result	"AVS"	•	-	-	•	•	•
Batch Number	"BATCH"	•	•	•	•	•	•
Card Number	"PAN"	•	•	•	•	•	•
Card Type	"CARD"	•	•	•	•	•	•
Customer Code	"CUST CODE"	•	-	-	-	-	-
Customer ID	"CUST ID"	•	•	-	•	•	•
CVD Result	"CVD"		•	-	•	•	•
ECI	"ECI"	•	•	•	•	•	•
Expiry date	"EXP"		•	-	•	•	•

Field	Header	D/C	Group	G/L	R	V	В
Invoice Number	"INVOICE"	•	-	-	-	-	-
Response Code	"RESP CODE"	•	•	•	•	•	•
Result	"RESULT"	•	•	•	•	•	•
Username	"USERNAME"	•	-	-	•	-	•
VBV/SecureCode Result	"VBV/SC"	•	-	-	•	-	-
Wallet Indicator	"WALLET"	•	-	-		-	•

- 4. Click on the Save Transaction Summary Settings button.
- 5. When the "success" message displays above the button, the operation is complete.

¹ In the gift/loyalty report, the **Amount** field corresponds to two transaction list headers: "AMOUNT" and "POINTS".

² In the gift/loyalty report, the **Authorization Code** field corresponds to the transaction list header "REF NUM".

12.2.7 Setting the headers/fields to include in an exported report

Follow the steps below to specify the default fields and corresponding headers (if any) that you want to include in any Merchant Resource Center report (transaction list) that you export to a .txt file in CSV-format (see page 173).

- 1. On the menu bar, click on Firstname Lastname > Account Settings.
- 2. Wait for the "Account Settings" page to display.
- 3. In the "Export to File Fields" area, checkmark the box beside any field (bolded below) that you want to include in an exportable report.

Note: The corresponding header for each field is enclosed in quotation marks ("").

Amount ("amount"); Auth Code ("auth_code"); AVS Result ("avs_result"); Batch Number ("batch_no"); Card Number ("first4last4"); Card Type ("card_type"); Customer Code ("customer_code"); Customer ID ("cust_id"), CVD Result ("cvd_result"); Date / Time ("transaction_date_time"); ECI ("eci"), Expiry date ("exp_date"); Invoice Number ("invoice_number"); Order ID ("order_no"); Orig Transaction Number ("orig_transaction_no"); Reference Number ("ecr_seq_no"); Response Code ("response_code"); Result ("result"), Sequence ("seq_no"); Swiped ("swiped"); Terminal ID ("ecr_no"); Transaction Number ("transaction_no"); Transaction Type ("transaction_name"); Username ("clerk"); VBV/SecureCode Result ("cavv_result"); Wallet Indicator ("wallet_indicator")

- If you want the exported report to include the field headers, checkmark the **Include Field Headers** box.
- 4. Click on the Save Export to File Settings button.
- 5. When the "success" message displays above the button, the operation is complete.

12.3 Viewing your login history

Follow the steps below to view the last ten successful and unsuccessful login attempts for your user profile.

12

- 1. On the menu bar, click on Firstname_Lastname > Login History.
- 2. Wait for the "Login History" page to display.
- 3. The operation is complete.

13 Admin: managing store settings/other user profiles

Use the Admin functions to manage your Merchant Resource Center store settings and manage other user profiles (e.g., assign user permissions, add/remove user profiles, and check audit logs).

This section includes information about how to do the following:

User profiles

- Add a new user profile (see page 188).
- Modify an existing user profile:
 - First/last name (see page 189).
 - Password (see page 190).
 - Permissions (see page 191).
 - Admin access level (see page 192).
- Deactivate a user profile (see page 193).

Notification

Add/remove e-mail addresses from the notification list (see page 194).

Store settings

 Configure settings that affect the entire store such as batch close time, tip prompts, cash payments, PCI mode settings, and receipt header (see pages 195 to 200).

Cloud wallets

See pages to 201 to 208.

Multi-store login

See page 209.

Security

- View audit logs (see page 212).
- Restrict IP access (see page 215).

Web integration

- Configure DirectPost (page 218).
 Configure Hosted Paypage (page 219).
 Configure Hosted Tokenization (page 220).

13.1 Adding a new user profile

Follow the steps below to add a new user profile to your Merchant Resource Center store.

- 1. On the menu bar, click on Admin > Add User.
- Wait for the "Add User" page to display.
- 3. In the "User Information" area, do the following:
 - a. In the **Last Name** and **First Name** fields, enter the new user's last and first names.
 - b. In the **Username** field, enter the username under which the new user will log into your Merchant Resource Center store.
 - c. In the **Temporary Password** and the **Confirm Temporary Password** fields, enter the new user's password.

Note: The new password must adhere to these restrictions (password fields are case sensitive): include 7-16 characters; start with a letter; contain a number; and cannot be the same as the previous 4 passwords.

When the new user signs into the Merchant Resource Center for the first time, they will be prompted to change their password.

- 4. Click on the Save User button.
- 5. Enable/disable permissions as desired (for a full listing of user permissions, see page 226):

To enable one or more user permissions:

a. Checkmark the box beside any permission that you want to enable.

Note: To simultaneously checkmark all boxes, click on the **Select All** button.

To disable one or more user permissions:

a. Unmark the box beside the permission that you want to disable.

Note: To simultaneously unmark all boxes, click on the **Deselect All** button.

- 6. Click on the Save Permissions button.
- 7. Assign the level of administrative access the new user can assign to other users (for a full listing of admin access levels, see page 224).
- 8. Click on the Save Level button.
- 9. When the "success" message displays above the button, the operation is complete.

13.2 Modifying a user profile

13.2.1 Modifying a user profile's first name/last name data

Follow the steps below to change the first and last name information of an active user profile on your Merchant Resource Center store.

- 1. On the menu bar, click on Admin > Modify User.
- 2. Wait for the "Modify User" page to display.
- 3. Retrieve the user profile that you want to modify:

To refine the search by last name:

- a. In the "Locate User" area, enter the name data in the **Last Name** and/or **Username** field.
- b. In the "Order By" area, select a sort order (mark the **Name** or **Username** radio button) for listing the results.

To retrieve all user profiles:

- a. Go to step 4.
- 4. Click on the Locate User button.
- 5. Wait for the "Select User" list of profiles to display.
- Click on the Edit User button beside the user profile that you want to modify.
- 7. Wait for the user profile to display.
- 8. In the "User Information" area, enter new data in the **Last Name** and/or **First Name** field.
- 9. Click on the **Update User** button.
- 10. When the "success" message displays above the button, the operation is complete.

13.2.2 Modifying a user profile's password

Follow the steps below to change the password of a user profile (active) on your Merchant Resource Center store.

Note: To modify your own user profile's password, see page 176.

- 1. On the menu bar, click on Admin > Modify User.
- 2. Wait for the "Modify User" page to display.
- 3. Retrieve the user profile that you want to modify:

To refine the search by last name:

- a. In the "Locate User" area, enter the name data in the **Last Name** and/or **Username** field.
- b. In the "Order By" area, select a sort order (mark the **Name** or **Username** radio button) for listing the results.

To retrieve all user profiles:

- a. Go to step 4.
- 4. Click on the Locate User button.
- 5. Wait for the "Select User" list of profiles to display.
- Click on the Edit User button beside the user profile that you want to modify.
- 7. Wait for the user profile to display.
- 8. In the "Change Password" area, enter the new password data in the **New Password** and **Confirm Password** fields.

Note: The new password must adhere to these restrictions (password fields are case sensitive): include 7-16 characters; start with a letter; contain a number; and cannot be the same as the previous 4 passwords.

- 9. Click on the **Update User** button.
- 10. When the "success" message displays above the button, the operation is complete.

Note: When the user next logs in, they must enter the new password.

13.2.3 Modifying a user profile's user permissions

13

Follow the steps below to change the user permissions of an active user profile on your Merchant Resource Center store.

- 1. On the menu bar, click on Admin > Modify User.
- 2. Wait for the "Modify User" page to display.
- 3. Retrieve the user profile that you want to modify:

To refine the search by last name:

- a. In the "Locate User" area, enter the name data in the **Last Name** and/or **Username** field.
- b. In the "Order By" area, select a sort order (mark the **Name** or **Username** radio button) for listing the results.

To retrieve all user profiles:

- a. Go to step 4.
- 4. Click on the Locate User button.
- 5. Wait for the "Select User" list of profiles to display.
- 6. Click on the **Edit User** button beside the user profile that you want to modify.
- 7. Wait for the user profile to display.
- 8. In the "Set Permissions" area, click on the **Set Permissions** button.
- 9. When the permissions display, enable/disable the permissions as desired (for a full listing of user permissions, see *User permissions* on page 226):

To enable one or more user permissions:

a. Checkmark the box beside any permission that you want to enable.

Note: To simultaneously checkmark all boxes, click on the **Select All** button.

To disable one or more user permissions:

a. Unmark the box beside the permission that you want to disable.

Note: To simultaneously unmark all boxes, click on the **Deselect All** button.

- 10. Click on the **Update Permissions** button.
- 11. When the "success" message displays above the button, the operation is complete.

13.2.4 Modifying a user profile's admin access level

Follow the steps below to change the level of administrative, transactional, and reporting access that a user can assign to another user on your Merchant Resource Center store.

- 1. On the menu bar, click on Admin > Modify User.
- 2. Wait for the "Modify User" page to display.
- 3. Retrieve the user profile that you want to modify:

To refine the search by last name:

- a. In the "Locate User" area, enter the name data in the **Last Name** and/or **Username** field.
- b. In the "Order By" area, select a sort order (mark the **Name** or **Username** radio button) for listing the results.

To retrieve all user profiles:

- a. Go to step 4.
- 4. Click on the Locate User button.
- 5. Wait for the "Select User" list of profiles to display.
- 6. Click on the **Edit User** button beside the user profile that you want to modify.
- 7. Wait for the user profile to display.
- 8. In the "Admin Level" area, click on the Set Level button.
- 9. When the various access levels display, assign an administrative, transaction, and reports level (for a list of available levels, see page 224):

To change an administrative level:

a. In the "Administrative Level" area, mark the radio button beside the administrative level that you want to assign to this user.

To change a transaction level:

a. In the "Transaction Level" area, mark the radio button beside the transaction level that you want to assign to this user.

To change a report level:

- a. In the "Report Level" area, mark the radio button beside the reports level that you want to assign to this user.
- 10. Click on the Update Level button.
- 11. When the "success" message displays above the button, the operation is complete.

13.3 Deactivating a user profile

Follow the steps below to permanently deactivate a user profile from your Merchant Resource Center store.

Note: Once a user profile is deactivated, its login credentials can no longer be used to access your store. The historical data for the activities of the user profile will continue to remain accessible even after the user profile is deactivated.

- 1. Click on Admin > Modify User.
- 2. Wait for the "Modify User" page to display.
- 3. Retrieve the user profile that you want to deactivate:

To refine the search by last name:

- a. In the "Locate User" area, enter the name data in the **Last Name** and/or **Username** field.
- b. In the "Order By" area, select a sort order (mark the **Name** or **Username** radio button) for listing the results.

To retrieve all user profiles:

- a. Go to step 4.
- 4. Click on the Locate User button.
- 5. Wait for the "Select User" list of profiles to display.
- 6. Click on the **Deactivate** button beside the user profile that you want to deactivate.
- 7. When the "success" message displays above the button, the operation is complete.

Note: A record of the deactivated user profile will remain on the system; however, the text "inactive" will display beside the deactivated username.

13.4 Notification settings

13.4.1 Adding an e-mail address to the notification list

Follow the steps below to add an e-mail address to the Merchant Resource Center notification list.

- 1. On the menu bar, click on Admin > Notification.
- 2. Wait for the "Email Notification" page to display.
- 3. In the "Add Email" area, enter the e-mail address (**Email Address** field) to have added to the notification list.
- 4. Click on the Add Email Address button.
- 5. When the "success" message displays above the button, the operation is complete.

13.4.2 Removing an e-mail address from the notification list

Follow the steps below to unsubscribe an e-mail address from the Merchant Resource Center notification list.

- 1. On the menu bar, click on **Admin > Notification**.
- 2. Wait for the "Email Notification" page to display.
- 3. In the "Notification Emails" area, click on the **Remove** button beside the e-mail address that you want to remove from the notification list.
- 4. In the "Confirm Delete" area, click on the **Remove Email** button.
- 5. When the "success" message displays, the operation is complete.

13.5 Store settings

13.5.1 Automated logout setting

Follow the steps below to specify the number of minutes before an inactive session is automatically logged off from your Merchant Resource Center store.

- 1. On the menu bar, click on Admin > Store Settings.
- 2. Wait for the "Store Settings" page to display.
- 3. In the "Automated Logout" area, do the following:
 - a. In the **Auto Logout Time** field, enter the number of minutes (minimum 10 min; maximum 720 min) .that must elapse before an inactive session is automatically logged out.
- 4. Click on the Save Logout Period button.
- 5. When the "success" message displays above the button, the operation is complete.

13.5.2 Batch close time setting

Follow the steps below to specify when you want your Merchant Resource Center store batch(es) to close and at what time.

- 1. On the menu bar, click on Admin > Store Settings.
- 2. Wait for the "Store Settings" page to display.
- 3. In the "Batch Close Time" area, mark the radio button beside one of the following options to enable it:

Option	Description
Manually close batch via API or Merchant Resource Centre	The batch never closes unless you close it via an API or the Merchant Resource Center.
Automatically close between 10 and 11 pm (Eastern Time)	The batch closes automatically each day between 10 PM and 11 PM (Eastern Time).
Automatically close at : hh:mm:ss	The batch closes automatically on a daily basis at a time that you specify (Eastern Time). A time between 10-11 PM is not valid.

- 4. Click on the Save Close Time button.
- 5. When the "success" message displays above the button, the operation is complete.

13.5.3 Cash payments setting

Follow the steps below to enable/disable cash as a payment option (Purchases and Refunds only) on your Merchant Resource Center store.

- 1. On the menu bar, click on Admin > Store Settings.
- 2. Wait for the "Store Settings" page to display.
- 3. In the "Cash Settings" area, do one of the following:
 - To enable cash payments, checkmark the Enable cash payments box.
 - To disable cash payments, unmark the Enable cash payments box.
- 4. Click on the **Update Cash Settings** button.
- 5. When the "success" message displays above the button, the operation is complete.

13.5.4 PCI mode setting

Follow the steps below to enable/disable PCI mode on your Merchant Resource Center store. When PCI mode is enabled, users are prevented from manually entering (keying) debit/credit card data to perform financial transactions.

Note: Even if PCI mode is enabled, it will still possible manually enter card data, but you must enable the user permission **Enable Keyed in PCI mode** for any user whom you want to have this ability (see page 191).

- 1. On the menu bar, click on Admin > Store Settings.
- 2. Wait for the "Store Settings" page to display.
- 3. In the "Encrypted Reader Settings PCI Mode" area, do one of the following:
 - To enable PCI mode, checkmark the **Enable PCI Mode** box.

Note: If PCI mode is enabled, the Card Verification transaction and all Vault and Recurring functionality (if supported on your store) will be disabled.

To disable PCI mode, unmark the Enable PCI Mode box.

Note: If PCI mode is disabled, Card Verification (page 60), Vault (page 147), and Recurring (page 140) functionality will be enabled.

- 4. Click on the **Update PCI Mode** button.
- 5. When the "success" message displays above the button, the operation is complete.

Follow the steps below to configure your business contact information (e.g., address, Web site URL, contact telephone number, refund policy, etc.) that you want to appear in

1. On the menu bar, click on Admin > Store Settings.

receipts generated on your Merchant Resource Center store.

13

- 2. Wait for the "Store Settings" page to display.
- 3. In the "Receipt Details" area, enter any data in fields that you want to include in receipts (Street Address 1, Street Address 2, City, Province, Postal Code, Website URL, Contact Tel #, Fax #, and Refund Policy).

Note: If your refund policy is greater than 50 characters (**Refund Policy** field), you may enter a URL that links to the full refund policy.

- 4. Click on the boxes beside any data element (listed below) that you want to include in receipts:
 - Include Line Item details.
 - Include Shipping details.
 - Include Billing details.
 - Include Customer ID.
 - Include extra details Client Email Address and Note.
- 5. Click on the **Save Receipt Data** button.
- 6. When the "success" message displays above the button, the operation is complete.

13.5.6 Tip setting: iPP320 PINpad

Follow the steps below to enable/disable tip prompting on any iPP320 PINpad that is allocated to your Merchant Resource Center store. When enabled, tip prompts display only during debit/credit Purchase transactions for which the iPP320 PINpad is used as the card entry method.

- 1. On the menu bar, click on Admin > Store Settings.
- 2. Wait for the "Store Settings" page to display.
- 3. In the "Tip Settings" area, do one of the following:
 - To enable tip prompting, checkmark the Enable tip on Pinpad box.
 - To disable tip prompting, unmark the Enable tip on Pinpad box.
- 4. Click on the **Update Tip Settings** button.
- 5. When the "success" message displays above the button, the operation is complete.

13.5.7 API token: viewing/regenerating the token

The API Token is a store-specific string of alphanumeric characters. Moneris uses the API token to validate the identity of your online store when e-commerce transactions are being performed as part of an integrated Web solution. When you opt to send e-commerce transactions directly from your Website, the transaction requests originate from a Merchant Resource Center API.

Follow the steps below to view the current API token or to generate a new API token.

Important! You MUST NOT transmit this token in an e-mail or any other insecure communication medium. If you believe that your token has been compromised, you should generate another token.

- 1. On the menu bar, click on Admin > Store Settings.
- 2. Wait for the "Store Settings" page to display.
- 3. In the "API Token" area, the store's current API token should be displayed.

If you need to regenerate the API token:

Important! The old token cannot be re-activated/used once a new one is generated.

- a. Click on the Re-generate API Token button.
- b. Wait for the warning message to display.
- c. Click on the **Re-generate API Token** button again.
- d. Wait for the new API token to be generated.
- e. Have all users currently logged into your store log out.
- f. Ensure that your integrated Web solution is configured to support the new API token.
- g. The operation is complete (users may now log in again).

13

Follow the steps below to configure the Asynchronous Transaction Response parameters to enable a server-to-server post of the terminal response data in XML format as a secondary method of obtaining the response data. The response data will be sent to the specified URL.

Note: Response URLs must be secure (HTTPS) in the production environment. Self-signed certificates will work. HTTP addresses will not work.

- 1. On the menu bar, click on Admin > Store Settings.
- 2. Wait for the "Store Settings" page to display.
- 3. In the "Asynchronous Transaction Response" area, do the following:
 - a. Checkmark the **Perform asynchronous data post** box.
 - b. In the Async Response URL field, enter the destination URL.
- 4. Click on the Save Asynchronous Settings button.
- 5. When the "success" message displays above the button, the operation is complete.

13.5.9 Multi-store login status

Follow the steps below to determine the status of your Merchant Resource Center store when it is configured to be part of a multi-store configuration (see page 209).

- 1. On the menu bar, click on Admin > Store Settings.
- 2. Wait for the "Store Settings" page to display.
- 3. In the "Multi Store" area, look for the following indicators:

Indicator	Description
Master Store	The store is a "master" store.
	The store is a "child" store.

4. The operation is complete.

13.5.10 Managed account updater setting

Follow the steps below to enable the Merchant Resource Center to automatically update stored credit card data using Visa and/or Mastercard updating services.

- 1. On the menu bar, click on Admin > Store Settings.
- 2. Wait for the "Store Settings" page to display.
- 3. In the "Managed Account Updater" area, do the following:

Note: If the Visa or Mastercard account updater service returns a "closed" or "contact" response for a registered card (account) number that you have used to set up a recurring transaction and/or a vault profile, the Merchant Resource Center will stop automatic card updates for the profile (see page 169).

- a. Configure managed account updater setting for recurring transactions:
 - To enable the managed account updater for recurring transactions, checkmark the Automatically update recurring transactions box.
 - To disable the managed account updater for recurring transactions, unmark the **Automatically update recurring transactions** box.
- b. Configure the managed account updater setting for Vault profiles
 - To enable the managed account updater for Vault profiles, checkmark the Automatically update vault transactions box.
 - To disable the managed account updater for Vault profiles, unmark the Automatically update vault transactions box.
- 4. Click on the Save Account Updater Settings button.
- 5. When the "success" message displays above the button, the operation is complete.

13.6 Mastercard MasterPass configuration

If your Merchant Resource Center store is set up in an integrated environment through Hosted Paypage or an API, follow the steps below to configure a Mastercard MasterPass profile for your store so that the Mastercard MasterPass payment solution ("cloud" wallet) can be used by your customers to pay for goods and services from your store.

Note: Customers/cardholders must establish their cloud wallet credentials directly through the card brands and are responsible for securing their wallet credentials in the same way they would secure their other payment information.

- 1. On the menu bar, click on Admin > Mastercard MasterPass.
- 2. Wait for the "MasterCard MasterPass Checkout Configuration" page to display.
- 3. In the **MasterPass Display Name** field, enter the name of the business that will support the Mastercard MasterPass payment solution (this field may be pre-filled with your Merchant Resource Center store's business name).
- 4. Enter the contact data about the person who will serve as the primary contact for the business that is supporting the Mastercard MasterPass payment solution:

Note: Mastercard may verify these data for tracking purposes. These data will not be visible to the public.

- a. In the first **Address** field, enter the primary contact's mailing address street number and street name.
- b. In the second **Address** field, enter the primary contact's mailing address unit number or apartment number (or PO box number) if applicable.
- c. In the **City** field, enter the primary contact's mailing address city location.
- d. In the **Postal Code** field, enter the primary contact's mailing address postal code.
- e. In the **Phone** field, enter the primary contact's phone number (do not include an extension number).
- f. In the **Email** field, enter the primary contact's e-mail address.
- 5. Enter the following required Web addresses for the business that is supporting the Mastercard MasterPass payment solution:
 - a. In the Website field, enter the business' home page Web address.
 - b. In the **Production URL** field, enter the Web address at which the business will host the Mastercard MasterPass payment solution while operating in a live production environment.
 - c. In the **Sandbox URL** field, enter the Web address at which the business will host the Mastercard MasterPass payment solution while operating in a QA test environment.

- d. In the Logo URL field, enter the Web address at which business' logo is hosted.
- e. In the "Integration Method" area, do one of the following:
 - If you are integrating your payment solution via an API, mark the API radio button.
 - If you are integrating your payment solution via Hosted Paypage, mark the Hosted Paypage radio button.
- In the Callback URL field, enter the Web address to which the Mastercard MasterPass data is to be sent.

Note: If you are integrating your payment solution via a Hosted Paypage, please note that the Moneris Gateway will manage the Mastercard MasterPass data transfer. If you are integrating your solution via an API, you must specify the Web address to which you want the Mastercard MasterPass token and any additional fields (e.g., billing/shipping) to be sent.

- 6. Read the terms and conditions, and checkmark the **By clicking "I agree"...** box.
- 7. Click on the **Save Profile** button.
- 8. Wait for the "success" response to display on the "MasterCard MasterPass" Checkout Configuration" page.
- 9. Do one of the following:

Note: Ensure that the Merchant Resource Center "Store Settings" user permission is enabled for your user profile (see page 191).

- If you will use the Mastercard MasterPass payment solution through a Hosted Paypage, configure your Hosted Paypage now.
- If you will use the Mastercard MasterPass paymente solution through an API, obtain the necessary integration guide from the Moneris Developer Portal (see page 238) and follow the steps to set up your API.

13.7 Visa Checkout configuration

If your Merchant Resource Center store is set up in an integrated environment through Hosted Paypage or an API, follow the steps below to configure a Visa Checkout profile for your store so that the Visa Checkout payment solution ("cloud" wallet) can be used by your customers to pay for goods and services from your store.

Note: Customers/cardholders must establish their cloud wallet credentials directly through the card brands and are responsible for securing their wallet credentials in the same way they would secure their other payment information.

- 1. On the menu bar, click on Admin > Visa Checkout.
- 2. Wait for the "Visa Checkout Configuration" page to display.
- 3. Enter the contact data about the person who will serve as the primary contact for the business that is supporting the Visa Checkout payment solution:

Note: Visa may verify these data for tracking purposes. These data will not be visible to the public.

- a. In the **Contact First Name** field, enter the primary contact's first name.
- b. In the **Contact Last Name** field, enter the primary contact's last name.
- c. In the **Phone** field, enter the primary contact's phone number (do not include an extension number).
- d. In the **Email** field, enter the primary contact's e-mail address.
- e. In the **Website** field, enter the home page Web address of the business that will support the Visa Checkout payment solution.
- f. In the first **Address** field, enter the primary contact's mailing address street number and street name.
- g. In the second **Address** field, enter the primary contact's mailing address unit number or apartment number (or PO box number) if applicable.
- h. In the City field, enter the primary contact's mailing address city location.
- i. In the **Postal Code** field, enter the primary contact's mailing address postal code.
- 4. Enter the following information about the business that is supporting the Visa Checkout payment solution:
 - a. In the **Checkout Display Name** field, enter the business' name (this field may be pre-filled with your Merchant Resource Center store's business name).
 - b. In the **Logo URL** field, enter the Web address at which the business' logo is hosted.

- c. In the "Accepted Card Types" area, checkmark the box beside any card type that you want to be selectable when customers use the Visa Checkout payment solution to buy goods and services from your business.
 - **Note:** If you checkmark a card type that is not enabled for your Moneris merchant account, the authorizing host will always reject any submitted transaction for which the ineligible card type has been selected via the Visa Checkout payment solution.
- d. In the "Visa Debit Accepted" area, do one of the following depending on your Moneris merchant account setup:
 - If your merchant account is enabled to accept Visa Debit, mark the True radio button.
 - If your merchant account is not enabled to accept Visa Debit, mark the **False** radio button.
- e. In the "Collect Shipping Address" area, do the following:
 - If you want Visa Checkout to always send the cardholder's preferred shipping address data to you via Hosted Paypage or API, checkmark the True box.
 - If you do not want Visa Checkout to send the cardholder's preferred shipping address sent back to you via Hosted Paypage or API, checkmark the False box.
- f. In the "Accepted Shipping Regions" area, do one of the following:
 - If you want to restrict the region(s) to which the business can ship/render goods and services when cardholders use the Visa Checkout payment solution, checkmark the box beside any desired shipping region (e.g., Canada, United States, etc.).
 - If you do not want to restrict the shipping region to which the business can ship/render goods and services when cardholders use the Visa Checkout payment solution, unmark all the shipping region boxes.
- q. In the "Accepted Billing Regions" area, do one of the following:
 - If you want to restrict the region(s) to which the business can bill for goods and services when cardholders use the Visa Checkout payment solution, checkmark the box beside any desired billing region (e.g., Canada, United States, etc.).
 - If you do not want to restrict the billing region to which your business can bill for goods and services when cardholders use the Visa Checkout payment solution, unmark all the shipping region boxes.
- 5. Read the terms and conditions, and checkmark the **By clicking "I agree"...** box.
- 6. Click on the Save Checkout Profile button.
- 7. Wait for the "success" response to display on the "Visa Checkout Configuration" page.
- 8. Do one of the following:

13

Note: Ensure that the Merchant Resource Center "Store Settings" user permission is enabled for your user profile (see page 191).

- If you will use the Visa Checkout payment solution through a Hosted Paypage, configure your Hosted Paypage now.
 If you will use the Visa Checkout payment solution through an API, obtain the
- If you will use the Visa Checkout payment solution through an API, obtain the necessary integration guide from the Moneris Developer Portal (see page 238) and follow the steps to set up your API.

13.8 Apple Pay in-app configuration

If you want to use the Moneris Apple Pay SDK and develop a solution that allows you to support Apple Pay payments in an integrated environment, follow the steps below to obtain and upload the necessary certificates that will allow Moneris to decrypt the Apple Pay payment token.

Note: If you want to use the Apple API instead of the Moneris Apple Pay SDK, refer to the Apple Developer library and the Moneris payment API.

- 1. Visit the Apple Developer Portal at https://developer.apple.com/ https://developer.apple.
- 2. Download a certificate signing request (CSR) file from the Merchant Resource Center:
 - a. Log into the Merchant Resource Center (see page 5).

Note: Do not log out from the Merchant Resource Center until you have completed the configuration steps below.

- b. On the menu bar, click on Admin > Apple Pay In-app Configuration.
- c. Wait for the "Apple Pay In-app Configuration" page to display.
- d. In the "Download CSR" area, enter your Apple Pay merchant ID in the **Apple Merchant ID** field.
- e. Click on the Download button.
- f. When the CSR file is generated, download it to your computer.
- 3. Go back to the Apple Developer Portal at https://developer.apple.com/library/prerelease/content/ApplePay Guide/Configuration.html, and upload the CSR file that you just downloaded to your computer (on the site, refer to the procedure for configuring a certificate for your Apple merchant ID).
- 4. When the Apple Pay certificate file is generated, download it to your computer.
- 5. Upload the Apple Pay certificate to the Merchant Resource Center:
 - a. Return to the Merchant Resource Center's "Apple Pay In-app Configuration" page (Admin > Apple Pay In-app Configuration).
 - b. In the "Upload Apple Pay certificate" area, browse for and select the Apple Pay certificate file that you just downloaded to your computer.
 - c. When the Apple Pay certificate is displayed in the field, click on the **Upload** button.

13

d. In the "Apple Merchant Certificates" area, confirm that a new "Vendor ID" and corresponding "Certificate Date" are listed (Moneris can now decrypt the Apple Pay payment token).

Important! Although you have successfully followed the steps to enable Moneris to decrypt the Apple Pay payment token, you must still integrate Apple Pay into your application. To do this, you must follow the steps in the appropriate Moneris integration guide (to obtain this guide, visit the Moneris Developer Portal (see page 238)).

Note: Ensure that the Merchant Resource Center "Store Settings" user permission is enabled for your user profile (see page 191).

13.9 Android Pay in-app configuration

If you want to use the Android SDK and develop a solution that allows you to support Android Pay payments in an integrated environment, follow the steps below to obtain the public key that will allow Moneris to decrypt the Android Pay payment token.

- 1. On the menu bar, click on Admin > Android Pay In-App.
- 2. Wait for the "Android Pay In-App Configuration" page to display.
- 3. Click on the Enable Android Pay button.
- 4. When the public key (an alpha-numeric string) displays, the operation is complete.

Note: Once the public key is displayed, it will remain available to view for future reference.

Important! Although you have successfully followed the steps to enable Moneris to decrypt the Android Pay payment token, you must still integrate Android Pay into your application. To do this, you must follow the steps in the appropriate Moneris integration guide (to obtain this guide, visit the Moneris Developer Portal (see page 238)).

13.10 Multi-store login configuration

If you have multiple Merchant Resource Center stores, the multi-store login feature allows you to link your stores together for easier access to reports and transaction processing across multiple stores at the same time without the need for you to log into each store separately using multiple login credentials.

- To link one store to another, see page 210.
- To remove a linked store from the group, see page 211.
- To switch between linked stores, see page 211.
- To determine the status of your store, see page 199.

13.10.1 Linking a child store to the master store

Follow the steps below to link one of your other Merchant Resource Center stores to the store that you are currently logged into.

Note: The store that you will link in effect becomes a "child" store while the store through which you are setting up the multi-store configuration becomes the "master" store.

- 1. Designate the "master" store by doing the following:
 - a. Log into the store that you want to designate as the "master" store (see page 5).
 - b. Enable the **Configure Multi Merchant** user permission for your user profile (see page 191).
 - c. Log out of the master store (see page 9).
- 2. Designate the "child" store by doing the following:
 - a. Log into the store that you want to designate as the "child" store (see page 5).
 - b. Enable the **Configure Multi Merchant** user permission for your user profile (see page 191).
 - c. Log out of this "child" store (see page 9).
- 3. Log back into your master store.
- 4. On the menu bar of your master store, click on **Admin** > **Multi Store**.
- 5. Wait for the "Multi Store Setup" page to display.
- 6. In the "Add Store" area, do the following:
 - a. In the **Username**, **Store ID**, and **Password** fields, enter your login credentials for the child store that you want to link to the master store.
 - b. Click on the **Authenticate Access** button.
 - c. When the "Store has been successfully paired" response displays, the stores have been successfully linked (the child store ID will be displayed in the "Manage Stores" area.
- 7. The operation is complete (to link another child store, repeat steps 2 to 6).

13.10.2 Unlinking a child store from the master store

Follow the steps below to unlink a child store from a master store.

13

- 1. Log into the master store (for login steps, see page 5).
- 2. On the menu bar of your master store, click on Admin > Multi Store.
- 3. Wait for the "Multi Store Setup" page to display.
- 4. In the "Manage Stores" area, do the following:
 - a. Locate the store that you want to unlink, and then checkmark the corresponding **Remove** box beside it.
 - b. Click on the **Remove Stores** button.
 - c. When the "success" response displays, the store has been unlinked (the child store ID will that you unlinked will no longer be displayed in the "Manage Stores" area).
- 5. The operation is complete.

Note: If there are no other stores linked to the main store, the multi-store bar will not display at the top of the page of the master store (see below).

13.10.3 Switching from one linked store to another linked store through multi-store login

Follow the steps below to switch from one Merchant Resource Center store to another Merchant Resource Center store when both are linked through a multi-store login setup.

- 1. Log into the master store (for login steps, see page 5).
- 2. Above the menu bar, locate the drop-down list displaying the name of the store you are currently logged into as an active user (see example below):



- 3. From the drop-down list, select the store that you want to access, and click on the **GO** button.
- 4. When the linked store name is displayed above the menu bar, the operation is complete (i.e., you have now started a login session in the "child" store).
- 5. The operation is complete.

13.11 Audit logs

13.11.1 Access violations log: viewing

Follow the steps below to view a log of user attempts to access or perform functions for which they do not have sufficient permissions.

- 1. Click on **Admin > Audit Logs**.
- 2. Wait for the "Audit Logs" page to display.
- 3. In the "Access Violations" area, select the **From /To** dates (hh:mm /DD/MM/YYYY) from the drop-down lists.

To narrow the scope of the log for a given date range:

- a. Checkmark the Username, Page Violation, and/or Violation Type box.
- b. For each box you checkmarked, select a line item from the corresponding drop-down list.

To retrieve all access violations for a given date range:

- a. Go to step 4.
- 4. Click on the **Search for Access Violations** button.
- 5. When the "Access Violations" log displays, the operation is complete.

13.11.2 Admin changes log

Follow the steps below to view a log of user-made administrative changes.

13

- 1. Click on Admin > Audit Logs.
- 2. Wait for the "Audit Logs" page to display.
- 3. In the "Admin Changes" area, select the **From /To** dates (hh:mm /DD/MM/YYYY) from the drop-down lists.

To narrow the scope of the log for a given date range:

- a. Checkmark the **Username** and/or **Change** box.
- b. For each box you checkmarked, select a line item from the corresponding drop-down list.

To retrieve all admin changes for a given date range:

- a. Go to step 4.
- 4. Click on the Search Admin Changes button.
- 5. When the "Admin Changes" log displays, the operation is complete.

13.11.3 User changes log

Follow the steps below to view a log of changes made by one user affecting another user.

- 1. Click on **Admin > Audit Logs**.
- 2. Wait for the "Audit Logs" page to display.
- 3. In the "User Changes" area, select the **From /To** dates (hh:mm /DD/MM/YYYY) from the drop-down lists.

To narrow the scope of the log for a given date range:

- a. Checkmark the **Username**, **Affected User**, and/or **Change** box.
- b. For each box you checkmarked, select a line item from the corresponding drop-down list.

To retrieve all user-to-user changes for a given date range:

- a. Go to step 4.
- 4. Click on the Search User Changes button.
- 5. When the "User Changes" log displays, the operation is complete.

13.11.4 Login history

Follow the steps below to view a log showing five successful or failed logins for one or more users.

- 1. Click on Admin > Audit Logs.
- 2. Wait for the "Audit Logs" page to display.
- 3. In the "Login History" area, do one of the following:

To narrow the scope of the log:

- a. Checkmark the Username and/or Login Result box.
- b. For each box that you checkmarked, select a line item from the corresponding drop-down list.

To retrieve all login attempts:

- a. Go to step 4.
- 4. Click on the Search Login History button.
- 5. When the "Login History" log displays, the operation is complete.

13.12 IP access

13.12.1 Restricting store access to specific IP address(es)

Follow the steps below to restrict access to your Merchant Resource Center store to one or more specific IP addresses.

- 1. On the menu bar, click on Admin > IP Access.
- 2. Wait for the "IP Access" page to display.
- 3. In the "Resource Center IP Restriction" area, do the following:
 - a. In the **Full or Partial IP** field, enter the IP Address (full or partial) that you want users to be restricted to using when accessing your Merchant Resource Center store.

Note: To define a partial IP address, include the '.' (period) after a completed octet so as to limit access to that precise octet. For example: "192.16." will allow only IPs that start with "192.16"; however, "192.16" will allow "192.16", "192.160, 192.161", etc.

b. From the **Bypass User** drop-down list, select a user profile that you do not be subject to the IP address restriction.

Important! This "Bypass user" will be the same for all listed IP Addresses. The bypass user exists in case your IP address changes. Should this happen, at least one user will still be able to access the Merchant Resource Center to update the IP address list.

- 4. Click on the Save IP button.
- 5. Confirm that the new IP address is listed under the "Allowed IP Addresses" area.
- 6. Do one of the following:
 - To add another IP address to the list of addresses from which your store can be accessed, repeat step 3a and steps 4 to 5.
 - If you do not want to add another IP address, go to step 7.
- 7. The operation is complete (all users except the bypass user will be restricted to accessing your Merchant Resource Center store from the specified IP address(es)).

13.12.2 Blocking an IP address when IP restrictions enforced

Follow the steps below to remove an IP address from the list of addresses from which your Merchant Resource Center store can be accessed.

- 1. On the menu bar, click on Admin > IP Access.
- 2. Wait for the "IP Access" page to display.
- 3. In the "Allowed IP Addresses" area, click on the **Remove** button beside the IP address that you want to remove from the "Allowed IP Addresses" list.

Important! If no address is listed, users will not be restricted to accessing your Merchant Resource Center store from a particular IP address.

- 4. When the "Confirm Delete" list displays, click on the Remove IP button.
- 5. The operation is complete (the IP address that you deleted will no longer display).

13.13 Web integration options

To integrate your site with the Merchant Resource Center, you may choose from among several available Web integration options such as DirectPost (page 218), Hosted Paypage (page 219), Hosted Tokenization (page 220), or one of the APIs. Determining which Web integration option to use is dependent on a number of factors such as:

- The skill/knowledge level of the developer responsible for completing the integration
- The system requirements and/or limitations of the system being integrated
- The importance to your business of the branding on the payment page and PCIcompliance responsibilities.

For assistance in determining which integration method is right for you, contact onlinepayments@moneris.com.

13.13.1 DirectPost configuration

DirectPost is one of the Web integration options (see page 217) available for integrating MOTO/e-commerce transaction processing with the Merchant Resource Center.

How DirectPost works

- 1. When a transaction is initiated, the transaction-specific data is sent to the Merchant Resource Center DirectPost via an HTTP POST.
- 2. The Merchant Resource Center processes the transaction and directs the cardholder and the response back to your merchant site so that a custom receipt can be created.
- 3. Transaction verification can be performed to ensure that what is being sent is a legitimate transaction.

If you opt use DirectPost integration

If you opt use DirectPost integration, you must complete a DirectPost configuration from the Merchant Resource Center.

• For information about how to view or download detailed DirectPost configuration instructions, see page 238.

13.13.2 Hosted Paypage configuration

Hosted Paypage is one of the Web integration options (see page 217) available for integrating MOTO/e-commerce transaction processing with the Merchant Resource Center.

How Hosted Paypage works

- 1. When a transaction is initiated, the non-secure transaction details are sent via an HTTP POST to the Merchant Resource Center, and the cardholder is redirected to a secure Moneris-hosted payment page.
- 2. On the hosted payment page, the cardholder enters their secure payment details (i.e. credit card or bank account data).
- 3. Upon receipt of this data, the Merchant Resource Center either generates a receipt on your behalf or directs the cardholder and response back to your merchant site so that a custom receipt can be created.
- 4. Transaction verification can be performed to ensure that the response is from a legitimate transaction.

If you opt to use Hosted Paypage integration

If you opt to use Hosted Paypage integration, you must complete a Hosted Paypage configuration from the Merchant Resource Center.

• For information about how to view or download detailed Hosted Paypage configuration instructions, see page 238.


13.13.3 Hosted tokenization

Hosted Tokenization is one of the Web integration options (see page 217) available for integrating MOTO/e-commerce transaction processing with the Merchant Resource Center. Similar to the Hosted Paypage option (see page 219), Hosted Tokenization offers a mechanism whereby a secure card number can only be entered on a secure Moneris hosted site. All other non-secure transaction details are collected on your merchant site.

This option is ideal if you have your own API and do not wish to handle credit card numbers directly on your Website, but you would like the ability to fully customize the checkout Web page. Hosted Tokenization offers the security of the Hosted Paypage while offering full control over the look and feel of the checkout page. At no time is the cardholder redirected from your merchant site.

Hosted Tokenization may be used in one of 2 scenarios:

- Processing a one-time financial transaction. OR
- Collecting the card data so that it may be stored within the Moneris Vault (see page 147).



To set up your Hosted Pay Page Temporary Tokenization (HPPTT) page, do the following:

- 1. On the menu bar, click on **Admin** > **Hosted Tokenization**.
- 2. Wait for the "Hosted Card Tokenization" page to display.
- 3. In the **Source Domain** field, enter the domain address from which requests on your Website will be initiated.
- 4. Click on the Create Profile button.
- 5. When the "success" response displays, the operation is complete.
- 6. Visit the Developer Portal (see page 238), and download the integration specifications that will provide guidance on how to do development work on your Website.

14 Appendix

14.1 Payment/transaction fields

The table below (continues to page 222) lists common Merchant Resource Center payment/transaction fields that may be displayed on transaction pages. Descriptions of what data to enter in each field are also included.

Field	Enter this data:
Amount	The transaction amount. When specifying an amount, do not enter the dollar sign or any other special characters. The amount must include the full cent values (#.##).
Auth Code	Authorization/reference code as received from an IVR or equivalent terminal.
Card Number	For debit/credit transaction, see <i>Credit Card Number</i> . For gift transaction, see <i>Gift Card Number</i> . For loyalty transaction, see <i>Loyalty Card Number</i> .
Card Verification Code	3- or 4-digit security code printed on the back or front of the gift/loyalty card.
Card Verification Digits	3- or 4-digit security code printed on the back or front of the debit/credit card.
Credit Card Number	Primary/personal account number (PAN) printed on the front of the card being used for the transaction. Note: Some chip debit card numbers may be entered instead of a credit card number.
Customer Code	Transaction identifier (optional).
Customer ID	Transaction identifier (optional).
CVC	See Card Verification Code.
CVD	See Card Verification Digits.
Data Key	A unique alpha-numeric string that is associated with each Vault profile.
ECI	See Electronic Commerce Indicator.

Field	Enter this data:
Electronic Commerce Indicator	Specify how the card number was obtained from the cardholder (for details, see page 223).
Expiry Date	The expiry date of the card which is being used for the transaction (MMYY). This date must correspond with the date found on the card itself.
Gift Card Number	The card account number printed on the front of a gift card.
Invoice Number	Transaction identifier (optional).
Loyalty Card Number	The card account number printed on the front of a loyalty card.
Order ID	The order ID is a unique identifier appended to every financial transaction. If you leave this field is left blank, the system will automatically generate the ID when the transaction is submitted for processing. If you enter your own ID, ensure that the ID you enter has never been used in the past. Order IDs may be up to 50 characters long, may contain letters and numbers, and may also contain the following special characters: -:.@
Points to Redeem	Number of points that you want to redeem from a loyalty card.
Statement Descriptor	Describes the transaction (appears on the cardholder's credit card statement).
Street Name	The street name of the cardholder's mailing address. This name should be the same as that found on the cardholder statement for the card being used (see page 235).
Street Number	The street number of the cardholder's mailing address. This number should be the same as that found on the cardholder statement for the card being used (see page 235).
Zip/Postal Code	The zip/postal code of the cardholder's mailing address. This code should be the same as that found on the cardholder statement for the card being used (see page 235).

14.2 Electronic commerce indicator (ECI)

The ECI is a descriptor that specifies how a debit/credit card number was obtained from the cardholder for the debit/credit financial transaction. The table below lists the ECIs supported on the Merchant Resource Center.

ECI	Description
M - Manually Keyed Card Present	-
0 - Not an electronic commerce transaction	-
1 - Mail/Telephone Order - Single	Cardholder provides credit card details via phone or on paper. Authorizes the use of the card for one payment.
2 - Mail/Telephone Order - Recurring	Cardholder provides credit card details via phone or on paper. Authorizes the use of the card for multiple payments processed at predetermined intervals.
3 - Mail/Telephone Order - Instalment	Cardholder provides credit card details via phone or on paper. Authorizes the use of the card for a single payment of goods or services billed to the card in multiple segments over a period of time.
4 - Mail/Telephone Order	Unknown classification: Cardholder provides credit card details via phone or on paper. Transaction type is unknown at time of authorization – may be one time or multiple payments.
5 - Authenticated E-commerce Transaction (VBV/MCSC)	Applicable to e-commerce transactions whereby the cardholder provides their card data over the Internet on a secure site and authenticates their identity via Verified by Visa/Mastercard SecureCode.
6 - Non Authenticated E-commerce Transaction (VBV/MCSC)	Applicable to e-commerce transactions whereby the cardholder provides their card data over the Internet on a secure site and attempts to authenticate their identity via Verified by Visa/Mastercard SecureCode.
7 - SSL Transaction (Not Authenticated)	Applicable to e-commerce transactions whereby the cardholder provides their card data over the Internet on a secure site.
8 - Non-Secure Transaction - Web or E-mail based	Applicable to e-commerce transactions whereby the cardholder provides their card data on an unsecured website or via e-mail.

14.3 Permissions

14.3.1 Admin access level

Admin-level access permissions are grouped into three main areas: administrative level, transaction level, and report level (refer to the respective tables below).

Important! A user possessing full admin-level permissions has complete control over other user profiles and your Merchant Resource Center store. Assign permissions to users based on business requirements. For information about payment card industry best security practices, refer to the Payment Card Industry (PCI) Security Standards Council's Web site at www.pcisecuritystandards.org/index.shtml.

Administrative level

The access levels listed* in the table below display in the "Administrative Level" area on the "Modify User" (or "Add User") page of the user profile that you are modifying.

Access level	If the access level is marked:
All Administrative Access	Allows user to grant the ability to enable full administrative access.
Add/Modify User and Audit Logs	Allows user to grant the ability to add/modify user profiles and to view audit logs.
Add/Modify User	Allows user to grant the ability to add or modify user profiles.
Modify User Only	Allows user to grant the ability to modify user profiles.
None (User is unable to grant Admin access to others.)	User cannot grant administrative access.

Transaction level

The access levels listed* in the table below display in the "Transaction Level" area on the "Modify User" (or "Add User") page of the user profile that you are modifying.

Access level	If access level marked:
All transactions, including Gift/Loyalty Activate, Gift Purchase, and Balance Inquiry.	User can grant the ability to perform all financial transactions.
All transactions except Void, Refund, and Independent Refund. (Also excludes Gift/Loyalty Deactivate, Void, Refund, and Independent Refund.)	User can grant the ability to perform all financial transactions except Voids, Refunds, Independent Refunds, and gift/loyalty deactivations.
None - User is unable to grant Transaction access to others.	User cannot grant transaction access.

Report level

The access levels listed in the table below display in the "Report Level" area on the "Modify User" (or "Add User") page of the user profile that you are modifying.

Access level	If access level marked:
All reports, including Gift/Loyalty Transaction report.	User can grant the ability to view, generate all reports.
All reports, except the ability to close batches.	User can grant the ability to view, generate all reports (excluding the ability to close batches).
None - User is unable to grant Report access to others.	User cannot grant report access.

14.3.2 User permissions

User permissions are grouped into several main areas: administrative permissions (see below), transaction permissions (see page 227), report permissions (see page 228), gift/loyalty permissions (see page 229), and Vault permissions (see page 230).

Administrative permissions

The user permissions listed in the table below display in the "Administrative Permissions" area on the "Modify User" (or "Add User") page of the user profile that you are modifying.

Permission	If permission checkmarked, then:
Add User	User can access the transaction page.
Alter Notification Addresses	User can access the transaction page.
Alter Batch	User can change the configuration.
Audit	User can access the transaction page.
Configure DirectPost	User can access the transaction page.
Configure Hosted Paypage	User can access the transaction page.
Configure Multi Merchant	User can access the transaction page.
Modify User	User can access the transaction page.
Save Changes *	User can execute any of the functions listed this section. (If this box is unmarked, the user will be restricted to view-only access. Any attempt to alter the configuration settings by this user will be logged.)
Set IP Access	User can access the transaction page.
Store Settings	User can access the transaction page.
View API Token	User can access the transaction page.

Transaction permissions

The user permissions listed in the table below display in the "Transaction Permissions" area on the "Modify User" (or "Add User") page of the user profile that you are modifying.

Permission	If permission checkmarked, then:	
Add Recurring	User can access the transaction page.	
Capture	User can access the transaction page.	
Create Group	User can access the transaction page.	
Enable Keyed in PCI mode	When PCI mode is enabled (see page 196), user can do keyed card entry in Merchant Resource Center fields.	
Execute Transactions*	User can perform transactions. (If this box is unmarked, the user will only be able to access the transaction page, but they will not be able to process the transaction.)	
Independent Refund	User can access the transaction page.	
Mandatory AVS	User must enter address verification data if transaction supports it.	
Mandatory CVD	User must enter card verification digits if transaction supports it.	
Preauth	User can access the transaction page (also applies to "Reauth" page).	
Purchase	User can access the transaction page.	
Refund	User can access the transaction page.	
Retry Recurring	Retry a declined recurring transaction.	
Statement Descriptor	User can submit statement descriptor data if transaction supports it.	
Verification	User can access the transaction page.	
Voice Auth	User can access the transaction page.	
Void	User can access the transaction page.	

Report Permissions:

The user permissions listed in the table below display in the "Report permissions" area on the "Modify User" (or "Add User") page of the user profile that you are modifying.

Permission	If permission checkmarked, then:
Allow batch close	User can perform a manual Batch Close.
Allow view of all users' transactions*	User can view all the transactions processed on the Merchant Resource Center. (If this box is unmarked, the user will be able to view only the transactions that they themselves performed.)
Alter Recurring Transactions	User can modify a recurring transaction.
Batches	User can access the transaction page. (The generated Batch report details will display all transactions regardless of the Allow view of all users' transactions permission.)
Execute Transactions/Batches:	User can perform follow-on transactions and process Batch Close transactions.
Grouped Transactions	User can access the transaction page.
Manage Recurring Transactions	User can access the transaction page.
Recurring Transaction Reports	User can access the transaction page.
Transactions	User can access the transaction page.

Gift/loyalty permissions:

The user permissions listed in the table below display in the "Gift/Loyalty Permissions" area on the "Modify User" (or "Add User") page of the user profile that you are modifying.

Permission	If permission checkmarked, then:
Execute Gift/Loyalty Transactions Reports*	User can perform gift/loyalty transactions and generate reports. (If this box is unmarked, the user will only be able to view the transaction and/or report page; they will not be able to perform the actual transaction/generate the report.)
Gift/Loyalty Activate	User can access the transaction page.
Gift/Loyalty Balance Inquiry	User can access the transaction page.
Gift/Loyalty Deactivate	User can access the transaction page.
Gift/Loyalty Independent Refund	User can access the transaction page.
Gift/Loyalty Purchase	User can access the transaction page.
Loyalty Redemption	User can access the transaction page.
Gift/Loyalty Refund	User can access the transaction page.
Gift/Loyalty Transaction Report	User can access the transaction page.
Gift/Loyalty Void	User can access the transaction page.

Vault permissions:

The user permissions listed in the table below display in the "Vault Permissions" area on the "Modify User" (or "Add User") page of the user profile that you are modifying.

Permission	If permission checkmarked, then:
Add Profile	User can access the transaction page.
Delete Profile	User can perform this transaction.
Execute Vault Transactions/Reports	User can perform Vault transactions and generate reports. (If this box is unmarked, the user will only be able to view the transaction page, but they will not be able to perform the transaction.)
Manage Profiles	User can access the transaction page.
Vault Reports	User can access the transaction page.
Update Profile Details	User can perform this transaction.

14.4 Managed account updater service

The managed account updater service allows you to maintain accuracy of your customers' data stored in Merchant Resource Center Vault and Recurring transactions with the Visa Account Updater (VAU) and the Mastercard Automatic Billing Updater (ABU).

VAU and ABU are mechanisms for updating cardholder account information electronically among participating card issuers, payment processors, and merchants who accept account-on-file transactions.

Note: Not all card issuers participate in the VAU and ABU programs, which may impact the availability of updated cardholder account information.

How does it work?

- 1. Participating card issuers submit cardholder account changes, such as card numbers and expiry dates, to the VAU and ABU databases.
- 2. As the merchant, you enrol in the Merchant Resource Center managed account update service.
- 3. When the service is enabled on your store, you must configure the setting to specify whether you want the service to work for Recurring transactions and/or Vault profiles (see page 200).
- 4. Periodically, your stored customer data are automatically submitted to VAU and ABU databases and then your store profiles are updated accordingly:
 - Note: If the VAU or ABU database returns a response indicating "closed" or "contact" for a registered card (account) number that you have used to set up a Vault profile or Recurring transaction on your store, the Merchant Resource Center will stop automatic card updates for the Vault profile or Recurring transaction (if the automatic update options are enabled for your store as referenced in step 3).
 - Recurring transactions data submitted 5 days before the next billing date
 - Vault profiles all the stored customer profiles are submitted once a week.
- 5. You may use the managed account updater report to see which recurring and/or vault profiles have been updated (see page 169).

14.5 Level 2/3 reporting

If your store is enabled for the level 2/3 reporting feature, the Merchant Resource Center will give you the option to add "level 2/3" tax and product details to eligible transactions if a supported purchasing card is used to process those transactions. Level 2/3 details may be added only to Captures (see pages 43 and 45) and Refunds (see page 51).

If level 2/3 details are added to a transaction that has been successfully processed, you will be given the option to view the level 2/3 details from the transaction's "Order History" page (see page 84).

Note: If you enter a supported purchasing card when performing a debit/credit Purchase, the Merchant Resource Center will prompt you to choose whether or not you want to add level 2/3 details to the transaction. If you opt to add level 2/3 details, the Merchant Resource Center automatically transitions the Purchase into a Preauthorization transaction. You will have the opportunity to add level 2/3 details at the time you capture the Preauthorization.

If your store is not enabled for level 2/3 reporting, you may still accept purchasing cards for payment; however, the Merchant Resource Center will not give you the option to add level 2/3 details.

Differences between level 2 and level 3 details

Note: For information about common level 2/3 details fields, see page 233.

- Level 2 details include a breakdown of sales tax data (e.g. GST, PST, HST, QST where applicable) Customer ID, P.O. number, general ledger code or account number, brokerage fees, and duty amount.
- Level 3 details include product description, unit/measurement, shipping information, product codes, and freight/delivery charges (similar to the level of detail found on invoices).

14.5.1 Level 2/3 details fields

The table below (continues to page 234) lists common level 2/3 details fields that may be displayed on the "Capture" page. Descriptions of what data to enter in each field are also included.

Field	Enter this data:
Buyer Name	Buyer/recipient name required by CRA for transactions greater than \$150.00.
Commodity Code	Line item commodity code. (If "Commodity Code" data is not sent, then "Product Code" data must be sent.)
Customer Ref. Identifier	16 character value which the customer may choose to provide at the point of sale (must be entered if provided by the customer). If "Customer Code" data was collected at time of the original preauthorization, this field will be prefilled by the customer code, but it does not need to be the same as the customer code.
Description	Line item description.
Destination Country	This field is prefilled if data is entered in the "Destination Postal Code" field; otherwise, select the country where goods will be delivered.
Destination Postal Code	The postal code where goods will be delivered (must be provided if shipping to an address within Canada). If shipping outside Canada please leave blank.
Duty Amount	Duty on total purchase amount. Mandatory for international sales if duty applies.
Freight Amount (inc taxes)	If shipping is not provided as a line item, it must be provided here (freight charges on total purchase) if applicable.
GST Amount	See HST Amount.
HST Amount	Must reflect the amount of national tax (GST or HST) appearing on the invoice.
Invoice Tax Exempt	If GST/HST (and PST/QST if applicable) can be exempted on the specific line item then this option needs to be selected. Otherwise, if not selected, the applicable national and federal taxes will be sent based on the destination postal code.

Field	Enter this data:
Product Code	Line item product code (if this field is not sent, then item "Commodity Code" must be sent). If the order has a "Freight/Shipping" line item, the "Product Code" data has to be "Freight/Shipping". If the order has a "Discount" line item, the "Product Code" data has to be "Discount".
PST Amount	Must reflect the amount of local tax (PST or QST) appearing on the invoice. If shipping to a province that only supports HST, this field will not appear as an option. If it appears, it is mandatory.
QST Amount	See PST Amount.
Quantity	Quantity of line item (must be a numeric value).
Unit Cost	Line item cost per unit. Must contain 2 decimal places.
Unit Meas.	Unit of measure.
VAT Reference Num	Unique value-added tax invoice reference number. Must be populated with the invoice number. Cannot be all spaces or all zeroes.

14.6 Address verification service (AVS)

The address verification service (AVS) is a fraud prevention feature that enables the card issuer to compare the street number, street name, and zip/postal code data that you entered during the transaction with the corresponding data that appears on the cardholder's statement.

To use AVS, your store must be enabled for the e-Fraud protection feature.

How to know if your store is enabled for AVS:

If your store is enabled for this feature, an "Address Verification" area, including associated address fields, will display on several virtual terminal transaction pages (see page 23).

You must enter the street number, street name, and zip/postal code data in the appropriate fields.

Note: It is strongly recommend that you include AVS details with all of your manually entered (keyed) transactions (MOTO/e-commerce). Doing so will ensure transactions are qualifying at the best possible interchange rate and will minimize costs to accept credit cards. If AVS is not present, the transaction may be assessed a higher interchange fee. AVS is not supported for UnionPay cards.

 For a full list of possible AVS result codes refer to the CVD AVS Result Code table on the Developer Portal (see page 238).

14.7 Card Validation Digits (CVD)

The card validation digits (CVD) value refers to the numbers appearing on the back of the credit card. It is an optional fraud prevention tool that enables you to verify data provided by the cardholder at transaction time. This data is submitted along with the transaction to the issuing bank, which provides a response indicating whether the data is a match.

Note: A CVD response will not be returned for UnionPay cards.

 For a full list of possible CVD result codes refer to the CVD AVS Result Code table on the Developer Portal (see page 238).

14.8 Using the Merchant Resource Center store in a test environment

The Merchant Resource Center test environment is designed to replicate the production environment as closely as possible. The test environment is accessible 24 hours a day, 7 days a week. Follow the steps below to login into the Merchant Resource Center test environment.

Note: Moneris cannot guarantee 100% availability of the Test environment. Please be aware that other merchants are using the test environment; hence, you will likely see transactions and user IDs that you did not create. As a courtesy to others who are also testing Moneris asks that you work only with the transactions/users that you created.

- 1. Visit https://esqa.moneris.com/mpg/.
- 2. Wait for the "Merchant Resource Center" login page to display.
- 3. Enter the "demouser" credentials in the fields:

To test this feature	Field	Enter this data:
	Username	demouser
eFraud (AVS , CVD)	Store ID	store1
		store2
		store3
		store5
VBV		moneris
	Password	abc1234

- 4. Click on the **Submit** button.
- 5. The operation is complete.

14.8.1 Test card numbers

Use the following test card account numbers with any future expiry date:

Important! These cards are for the Test environment only. DO NOT use in the Production environment.

Card type	Card number
Amex	373599005095005
Diners	36462462742008
Discover	651000000000182
JCB	3566007770015365
Mastercard	54545454545454
Visa	42424242424242
UnionPay	6250944000000773

Although the test environment is designed to replicate the production environment as closely as possible, one major difference is that test transactions are not sent to the production authorization network. This means issuer responses are simulated. In Addition, the requirement to emulate approval, decline, and error situations dictates the use of certain transaction variables to initiate various response and error situations.

The test environment approves and declines transactions based on the penny value of the amount field. For example, a transaction processed for \$399.00 or \$1.00 will be approved since the .00 penny value is set to "approve" in the test environment. Transactions in the test environment should not exceed \$1000.00. (This limit does not exist in the production environment.)

• For a list of all current test environment responses for various penny values, download the appropriate documentation (i.e., the *Test Environment Penny Response* table as well as the *Test Environment e-Fraud Response* table). For instructions on how to obtain this documentation, see page 238.

14.9 Assistance and resources

Assistance	
 Enabling store features (e.g., Recurring billing, gift/loyalty) 	Call toll free: 1-866-319-7450.
 Creating merchant accounts 	
 Enabling Independent Refunds (temporarily) 	
 Adding card plans, pricing and other sales-related 	
Technical issues	For online assistance, e-mail:
Training	onlinepayments@moneris.com OR For telephone assistance, call toll free: 1-866-319-7450.

Documentation	
Error Codes and MessagesIntegration Guides	 Go to the Merchant Resource Center login page (visit https://www3.moneris.com/mpg/).
	 Click on the Developer Portal link at the bottom of the page (you may be required to register for an account).

Drivers and APIs	
APIs	 Go to the Merchant Resource Center login page (visit https://www3.moneris.com/mpg/). Click on the Developer Portal link at the
	bottom of the page (you may be required to register for an account).
 PINpad drivers 	1. Go to: https://github.com/moneris/ .
ICC Simulators	

Other	
 Activating your store 	1. Visit moneris.com/activate.
	2. For instructions see page 3.