FIRST TIME SETUP AND USE
NEW API

v5-10-2024

Rick Pomygalski
Director of Product Development
& Advanced Solutions
mailto:rick@clubready.com

Welcome to the ClubReady API! Now that you have set up your account and subscribed to the API, you must now set up your access key and generate your first API Token.

Please note: The API referenced in this document is still in Beta. *The product is still undergoing testing and could contain errors or functionality issues. Your use of this Beta product is with the understanding that it is provided "AS IS". Should you encounter any bugs, glitches, lack of functionality or other problems, please generate a support ticket with details, screenshots, and any content that will help us to replicate that issue to: support@clubready.com. We cannot guarantee a timely solution or fix to any reported issue.*

NEW API – FIRST USE AND CREATING YOUR ACCESS TOKEN:

Example API account info. (You should already have been provided with your info):

Username: 48aaba77-3cb0-4d1d-93ae-123456789123
Password: 7ddcb6d4-8b6a-4383-90c4-123456789123

1. You must encode that to Base64 format which can be done at: https://www.base64encode.org/

   Convert the USERNAME:PASSWORD. (Colon in between) …

   

   RESULT:

   

2. **COPY the Result.**

   That is what you use each time you generate your Token, and **it will never change**. ***Tokens last for 14 days***.

3. Log into the API portal and go to this endpoint:
   https://crprod-apim.developer.azure-api.net/api-details#api=SecurityV1&operation=access-token

Click “Try It”



Take the result you copied above and preface it with “Basic“… so for example, I would copy and paste that into the field shown in the image below…

Example:

Basic ODQ5ZWQ2YTktZDY1NS00ZGM5LTkzYWUtNmI4ZWFjOTRmMGM4OjdkZGN iNmQ0LThiNmEtNDM4Myxxxxxxxxxxxxxxxxxxxxxxxxxxxxxxx

…which you copy and Paste into the Authorization field:



Click “Send” at the bottom of the page.

HTTP response

```
HTTP/1.1 200 OK

content-encoding: gzip
content-type: application/json; charset=utf-8
date: Fri, 10 May 2024 16:22:44 GMT
request-context: appId=cid-v1:694e3e0d-236a-4845-9c44-49125a97a69c
transfer-encoding: chunked
vary: Accept-Encoding
x-powered-by: ASP.NET

{
  "token_type": "bearer",
  "expires_in": 604800,
  "access_token": "eyJhbGciOiJIUzI1NiIsInR5cCI6IkpXVCJ9.eyJjaGFpbklkIj
pbIjM3IiwiMzc0IiwiNTYiLCI3NzMiLCI5NCIsIjM1NiIsIjU0OSIsIjE4IiwiNjIyIiwi
[redacted]
LcO4LiCh0yAPcraKCJw",
  "refresh_token": null
}
```

The highlighted section shown is your Bearer Token… this is what you will use for your API request. As mentioned above, it will expire every 14 days so you will need to write some code to “auto-renew” the token and reference that token variable for all of API-related code.

Now that you have your token you can use the API endpoints. With the valid Access Token, you can use most of the endpoints. *If it doesn’t already exist*, click ‘+ Add Header’ and type ‘Authorization’ …

Paste your token into the corresponding field preceded by “Bearer”

Example:

```
Bearer
eyJhbGciOiJIUzI1NiIsInR5cCI6IkpXVCJ9.eyJjaGFpbklkIjpbIjM3IiwiMzc0IiwiNTYiLCI3NzMiLCIxOCJdLCJzdG9yZ
UlkIjoiMTg2NSIsImV4cCI6MTYzMxxxxxxxxxxxxxxxxxxxxxxxxxxFkexxxxxxxxxxxxxxxxxxxxxxxxxxxx
```

It should appear like this:



Click ‘Send’ to execute the request. That’s it!