


Internal



Tamm Actual Driver Service

Integration Guide

Date : 04-12-2023

Version : 0.4

Document Privacy: Confidential

Contents

1	Introduction	4
1.1.1	Purpose	4
1.1.2	Scope	4
1.1.3	Definitions, acronyms, and abbreviations	4
2	Actual Driver	
3	Actual Driver	6
3.1.1	Verify vehicle plate	6
3.1.2	Do issue Actual driver	9
4	Cancel Actual Driver	11
4.1.1	Verify Cancel Actual Driver	11
4.1.2	Do cancel driving authorization	13

Internal
Document History Log

Version	Author	Issue Date	Revision Source	Changes
0.1	Manazir Khan	04-12-2023		Initiated
0.2	Mohammad Hewedy	04-12-2023		Adding changes and modification

1 Introduction

1.1.1 Purpose

The purpose of this document is to communicate to the client the APIs for use.

This document discusses in detail APIs of Actual drivers, their resources and their request/response parameters. The details of each parameter field like its type is also described, so that the clients of the API are aware of the expected inputs and the response provided by the API with samples of request and response.

1.1.2 Scope

The document mainly focuses on the APIs available for Actual driver and the parameters required in invoking these web services.

1.1.3 Definitions, acronyms, and abbreviations

Acronym or Abbreviation	Definition
NIC	National Information Center
NIN	National Identification Number
OTP	One Time Password
URL	Uniform Resource Locator
HTTP	Hyper Text Transfer Protocol

2 Actual Driver

Please refer to the *Profile Management* Integration Guide or the *Integrators* Integration Guide in case you are an integrator.

3 Actual Driver

This API allows the user to issue a actual driver for a person on a vehicle belongs to the client.

This API consists of three steps:

- Verify vehicle using plate number
- Verify and assigned National Id, Birth Year and mobile number
- Do Issue actual driver using OTP validation


3.1.1 Verify vehicle plate

The main function of this API is to validate vehicle by passing plate information

URL

POST {{baseUrl}}/api/v1/actual-driver/addition/verifyVehicle

Input

Name	Description	Example	Type	Required
plateDto	Vehicle plate details	<pre>{ "text1": "ر", "text2": "ح", "text3": "ب", "number": 100, "type": { "code": 1 } }</pre> 	JSON string	Yes

Output

Name	Description	Type
id	Conversation Id – this id used in the next step to be added in the header	String
vehicleWithAuthorizationNumber	<pre>{ "vehicleDto": { "sequenceNumber": 526421056, "plate": { "text1": "ب", "text2": "س", "text3": "س", "number": 4926, "type": { "code": 1, "nameAr": "خصوصی", "nameEn": "خصوصی" } } }, "weight": 1500, "makerAndModel": { "maker": "هوندا", "model": "اکورد" } }</pre>	Json

Internal

	<pre> "year": 2020 }, "color": { "major": "ابيض", "minor": null }, "transferRestricted": false }, "authorizationNumber": null }, }</pre>	
--	---	--

3.1.2 Verify National ID information

The main function of this API is to validate national Id of person.

An OTP is being send if verification succeed. The OTP should be included in the subsequent “Do issue driving authorization” Request.

URL

POST {{baseUrl}}/api/v1/actual-driver/addition/verify

Input

Name	Description	Example	Type	Required
type	Internal or international	1 => internal authorization 2 => International authorization	Number	Yes
birthYear	Vehicle plate details	1958	Number (max 4)	Yes
idNumber	10-digit numeric number starting with 1 or 2	1042509247	String (max 10)	Yes
mobileNumber	9-digit numeric number	563093382	String (max 9)	Yes

Output

Name	Description	Type
id	Conversation Id – this id used in the next step to be added in the header	String
vehicleWithAuthorizationNumber	<pre>{ "vehicleDto": { "sequenceNumber": 526421056, "weight": 1500, "makerAndModel": { "maker": "هوندا", "model": "اکورد", "year": 2020 }, "color": { "major": "ابيض", "minor": null } }, }</pre>	Json

actualDriverDtoWithPrice	<pre> "plate": { "text1": "ب", "text2": "س", "text3": "س", "number": 4926, "type": { "code": 1, "nameAr": "خصوصي", "nameEn": "خصوصي" } }, "transferRestricted": false }, "authorizationNumber": null }, { "actualDriverDataDto": { "id": null, "name": "هارون مبروك الرحمن عبد شيدة", "type": "SAUDI", "mobile": "558526036", "gender": "FEMALE", "idNumber": 1120721723, "plateInfo": "4926 1", "ownerName": "هارون مبروك الرحمن عبد شيدة", "birthYear": 1958, "ownerIdNumber": 7001396907, "vehicleSeq": 526421056, "isRemoved": null, "birthDate": "1958-01-20", "createdDate": null, "modifiedDate": null, "residentIqamaId": null, "crossValidationBy": null, "createdUserIdNumber": null, "branchName": { "ar": "الإسناد فرع", "en": "branch" }, "crossValidationPlateDto": { "text1": "", "text2": "", "text3": "", "number": null, "type": { "code": null, "nameAr": null, "nameEn": null } }, "removedDate": null, "actualDriverReferenceNumber": null, "plateType": 1 }, "price": "10.0", "otpId": "6ed14f2f-f4ea-4b91-971b-7c6cb96a72b7" } </pre>	Json
---------------------------------	--	-------------

Example:

Input	<pre> { "plateDto": { "text1": "ب", "text2": "س", "text3": "س", "number": "4926", "type": { "code": 1, "nameAr": "خاص", "nameEn": "Private Car" } } } </pre>
Output	<pre> { "id": "4abe6e885c38885f", "vehicleWithAuthorizationNumber": { "vehicleDto": { "sequenceNumber": 526421056, "plate": { "text1": "ب", "text2": "س", "text3": "س", </pre>

Internal

```
{
  "number": 4926,
  "type": {
    "code": 1,
    "nameAr": "خصوصي",
    "nameEn": "خصوصي"
  },
  "weight": 1500,
  "makerAndModel": {
    "maker": "هوندا",
    "model": "اكورد",
    "year": 2020
  },
  "color": {
    "major": "ابيض",
    "minor": null
  },
  "transferRestricted": false
},
"authorizationNumber": null
},
"actualDriverDtoWithPrice": null
}
```

3.1.3 Do issue Actual driver

This API allow the user to issue a addition of actual driver.

URL

POST {{baseUrl}}/api/v1/actual-driver/addition/

Input

Name	Description	Type	Required
otp	One Time Password sent to the authorized person mobile number	String (4)	Yes
X-Conversation-Id	The id from the 1 st step, need to be used in the request header.	String Request Header	Yes

Output

Name	Description	Type
referenceNumber	Authorization number from NIC	Long

Example

Internal

Input	<pre>{ "otp": "1234" }</pre>
Output	<pre>{ "referenceNumber": 50000404316 }</pre>

Internal

4 Cancel Actual Driver

To cancel a actual driver for a vehicle given its plate number.

4.1.1 Verify Cancel Actual Driver

This API allow the user to verify the ability to cancel driving authorization.

URL

POST {{baseUrl}}/api/v1/actual-driver/removal/verify

Input

Name	Description	Sample	Type	Required
plateDto	Vehicle plate details	<pre>{ "plateDto": { "text1": "ب", "text2": "س", "text3": "س", "number": "4926", "type": { "code": 1, "nameAr": "خاص", "nameEn": "Private Car" } } }</pre>	JSON string	Yes

Output:

Name	Description	Type	Required
id	Conversation Id – this id used in the next step to be added in the header	String	Yes
deleteActualDriverDtoWithVehicleDto	Delete Actual Driver	<pre>{ "actualDriverDto": { "id": null, "name": "هارون مبروك الرحمن عبد شيدة", "type": "SAUDI", "mobile": null, "gender": "FEMALE", "idNumber": "1120721723", "plateInfo": "4926_1", "ownerName": "هارون مبروك الرحمن عبد شيدة", "birthYear": null, "ownerIdNumber": "7001396907", "vehicleSeq": "526421056", "isRemoved": null, "birthDate": "1958-01-20", "createdDate": "2023-12-04T11:42:54.510Z", "modifiedDate": null, "residentIqamaId": null, "crossValidationBy": null, "createdUserIdNumber": null, "branchName": { "ar": "الإسناد فرع", "en": "branch" }, "crossValidationPlateDto": null, "removedDate": null, "actualDriverReferenceNumber": "50000404311", "plateType": 1 }, "vehicleDto": {</pre>	JSON string

Internal

		<pre> "sequenceNumber": 526421056, "plate": { "text1": "ب", "text2": "س", "text3": "س", "number": 4926, "type": { "code": 1, "nameAr": "خصوصي", "nameEn": "Private Car" } }, "weight": 1500, "makerAndModel": { "maker": "هوندا", "model": "أكورد", "year": 2020 }, "color": { "major": "البيض", "minor": null }, "transferRestricted": false }, "assignmentConfiguration": "AUTHORIZE_BRANCH_USER_TO_ASSIGN_VEHICLE_BRANCH", "branchName": { "ar": "الإسناد فرع", "en": "branch" }, "branchId": 71000 </pre>	
--	--	---	--

Example:

Input	<pre> { "plateDto": { "text1": "ب", "text2": "س", "text3": "س", "number": "4926", "type": { "code": 1, "nameAr": "خاص", "nameEn": "Private Car" } } } </pre>
Output	<pre> { "id": "165b044a41277648", "deleteActualDriverDtoWithVehicleDto": { "actualDriverDto": { "id": null, "name": "هارون مبروك الرحمن عبد شيدة", "type": "SAUDI", "mobile": null, "gender": "FEMALE", "idNumber": 1120721723, "plateInfo": "بسس_4926_1", "ownerName": "هارون مبروك الرحمن عبد شيدة", "birthYear": null, "ownerIdNumber": 7001396907, "vehicleSeq": 526421056, "isRemoved": null, "birthDate": "1958-01-20", "createdDate": "2023-12-04T11:42:54.510Z", "modifiedDate": null, "residentIqamaId": null, "crossValidationBy": null, "createdUserIdNumber": null, "branchName": { "ar": "الإسناد فرع", </pre>

Internal

```
        "en": "branch"
      },
      "crossValidationPlateDto": null,
      "removedDate": null,
      "actualDriverReferenceNumber": 50000404311,
      "plateType": 1
    },
    "vehicleDto": {
      "sequenceNumber": 526421056,
      "plate": {
        "text1": "ب",
        "text2": "س",
        "text3": "س",
        "number": 4926,
        "type": {
          "code": 1,
          "nameAr": "خصوصي",
          "nameEn": "خصوصي"
        }
      },
      "weight": 1500,
      "makerAndModel": {
        "maker": "هوندا",
        "model": "اكورد",
        "year": 2020
      },
      "color": {
        "major": "ابيض",
        "minor": null
      },
      "transferRestricted": false
    },
    "assignmentConfiguration": "AUTHORIZE_BRANCH_USER_TO_ASSIGN_VEHICLE_BRANCH",
    "branchName": {
      "ar": "الاسناد فرع",
      "en": "branch"
    },
    "branchId": 71000
  }
}
```

4.1.2 Do cancel actual driver

This API allow the user to cancel actual driver for a vehicle.

URL

DELETE

{{baseUrl}}/api/v1/actual-driver/removal/?moveVehicleToCurrentBranch=false}

Input

Name	Description	Sample	Type	Required
moveVehicleToCurrentBranch	Vehicle to branch	false	Request parameter (Boolean)	Yes

Internal

Output

Name	Description	Sample	Type	Required
No output				

4.1.3 Error codes

Code	Type	Message
400	Business error	Business error message translated in Arabic and English
500	System error	"Generic error occurred" or "حدث خطأ أثناء تنفيذ طلبك"