

Tachograph for Euro Truck Simulator 2

BETA V. 1.0.0

By Mr_Jachowski21

01.06.2026

Instructions & Installation

Table of Contents:

- 1. General Information**
- 2. Installation Instructions**
 - 2.1. General Information**
 - 2.2. Python**
 - 2.3. Verification&Installation Program**
 - 2.4. Telemetry**
 - 2.5. Necessary Code Changes**
- 3. Tachograph Operation**
 - 3.1. General Information**
 - 3.2. DRIVING Mode**
 - 3.3. BREAK Mode**
 - 3.4. OTHER WORK Mode**
 - 3.5. Tachograph Printouts**
 - 3.6. Button Instructions**
- 4. Useful Tips**
- 5. Conclusion and Copyright**

1. General Information

Welcome to the beginning of this guide on how to use the tachograph I created for ETS2 (mr_jachowski21). If you're here, you probably want to learn how to install all the necessary components and how to operate it. I'd be happy to explain all of these things. First, though, some general information: I created this free tachograph for ETS2 as a fan of realistic driving. It's important to emphasize that this project is 100% mine and free for use. The tachograph is in Polish, so all functions will be explained in English in this manual. It's worth noting that the tachograph operates in the ETS 2 time unit, which adds even greater realism.

2. Installation Instructions

2.1. General Information

The Tachograph program runs on Python. Additionally, telemetry is required, the installation process of which will be discussed (as well as Python and its add-ons) on the next page.

2.2. Python

The tachograph is powered by the familiar PYTHON programming language and its ubiquitous imported add-ons. Downloading Python isn't a big deal; you can download it (if you don't already have it on your computer) from the following link:

<https://www.python.org/downloads/>

After installing it on your computer, the tachograph program still won't run properly (it needs to be installed). If you have Visual Studio Code or run the Python console, you can download the required add-ons. (If you don't have an add-on installed, in the

Python console (not the one you run by double-clicking the program, but by entering:
"C:/Program Files/Python313/python.exe" -- (or your Python path)
"c:/Users/jangl/OneDrive/Attachments/Dokumenty/euro-truck-simulator-2-tachograph-v.1.0.0/tachograph/tachograph.py" (or your tachograph path))

then enter:

pip install [add-on name]

You can also skip this manual installation step and use the "verification&installation.py" file, which is also described in the following chapters.

2.3. Verification&Installation Program

You can skip all the steps involved with manually INSTALLING Python add-ons and telemetry (which will be described in the next section) with our proprietary "verification&installation.py" program. It runs in the console and doesn't require any add-ons to run. Simply double-click the "verification&installation.py" file.

Once you do this, the console will open and you will see this view:

```
=====
CHRONOS TACHOSYSTEM - ENVIRONMENT VERIFIER
=====

Checking system dependencies & modules:
- tkinter      (Built-in GUI Library      ): [INSTALLED]
- json         (Built-in JSON Parser      ): [INSTALLED]
- urllib       (Built-in URL Request Engine): [INSTALLED]

=====
AVAILABLE ACTIONS:
[1] Install / Repair missing Python modules manually
[2] Download and deploy Funbit ETS2 Telemetry Server v3.2.5
[3] Refresh verification status
[4] Exit program
=====
Select an option (1-4):
```

Here you'll see whether plugins requiring installation are installed on your computer (you'll see "[INSTALLED]" like I did) or not installed (you'll see "[NOT INSTALLED]").

To install all the necessary plugins, enter "1" in the designated space.

After that, the plugins will begin installing for your Python.

By typing "2" you can download all the things needed for telemetry, and telemetry from FunBit, I also want to include his copyright for telemetry, at the end of this manual.

you will then see this message:

```
=====
CHRONOS TACHOSYSTEM - ENVIRONMENT VERIFIER
=====

Checking system dependencies & modules:
- tkinter      (Built-in GUI Library      ): [INSTALLED]
- json         (Built-in JSON Parser      ): [INSTALLED]
- urllib       (Built-in URL Request Engine): [INSTALLED]

=====
AVAILABLE ACTIONS:
[1] Install / Repair missing Python modules manually
[2] Download and deploy Funbit ETS2 Telemetry Server v3.2.5
[3] Refresh verification status
[4] Exit program
=====
Select an option (1-4): 2

--- FUNBIT ETS2 TELEMETRY SERVER v3.2.5 DEPLOYMENT ---
Enter target directory path to deploy Funbit Telemetry Server:
```

*Remember to use the shortest possible path during installation, as providing a long path causes an error I've seen. Additionally, remember that it must be easily accessible, as you'll be opening the telemetry file every time you use the tachograph. after entering it, the download will start.

Once it is finished, you will be able to extract the files and proceed to its installation.

2.4. Telemetry

You can also download the telemetry manually from GitHub:

<https://github.com/Funbit/ets2-telemetry-server#>

*Remember to use the shortest possible path during installation, as providing a long path causes a known bug. Additionally, remember that it must be easily accessible, as you will be opening the telemetry file every time you use the tachograph.

Once you download it—whether from the program or from an external link (GitHub—when you do, remember to unzip the files), go to the "server" folder and open the "Ets2Telemetry" application. Telemetry installation instructions will appear. After completing them, the main program window will open, and after opening the game, the telemetry will be connected (just like with our tachograph).



2.5. Necessary Code Changes

For the tachograph to work properly, you must/can change certain things in the code. These include paths, IP servers, and driver names.

1. Drivers Names:

for more realism you can change it in lines 18 and 19

```
17 # Dane konfiguracyjne i stan tachografu
18 self.driver1_name = "DRIVER 1"
19 self.driver2_name = "DRIVER 2"
```

Remember to save your changes after the operation is completed.

2. IP Telemetry:

For the telemetry server to work properly and connect to our tachograph, you need to replace the first characters of the telemetry URL, i.e., from the one marked in the screenshot below, "111.222.3.44," with your own IP address—which will also be displayed in the telemetry application. Remember to keep the ":25555" and "/api/ets2/telemetry" endings. This is one of the most important changes, found on line 155.

```
155 url = "http://111.222.3.44:25555/api/ets2/telemetry"
```

Remember to save your changes after the operation is completed.

3. Tachograph Operation

3.1. General Information

The tachograph operates in accordance with the standards defined by the European Union and described in the table below. It's worth noting that this is version 1.0.0 of the tachograph, and its functions will become increasingly more extensive. The tachograph is in

Polish, which may be inconvenient for some. Version 1.1.0 will include English and other national languages. In this section, I'll try to explain how the functions work and translate them from Polish to English.

Activities on the tachograph and their duration in accordance with European Union requirements	
Continuous driving time	4 h 30 min (x2 - after break) = 9 hours (can be extended to 10 hours)
Break between the first 4:30 and the second 4:30	45 min (or 15 + 30 mins)
Break after 9 hours of driving	11 hours (can be reduced to 9 hours)



3.2. **DRIVING Mode**

Driving Mode is activated AUTOMATICALLY after the engine is started and the vehicle speed is above 0 kilometers per hour. Its duration is $4:30 \text{ h} \times 2 = 9 \text{ h}$, with the option of extending it to 10 hours. It's worth noting that the tachograph operates in the ETS 2 time unit, which adds even greater realism.

3.3. **BREAK Mode**

Driving Mode activates AUTOMATICALLY after the engine is turned off and lasts:


45 minutes after 4 hours and 30 minutes of driving (can be divided into 30 minutes and 15 minutes) and 11 hours (can be reduced to 9 hours) after 9 hours of driving. This is also available in ETS 2 units.

3.4. **OTHER WORK Mode**

This mode is activated AUTOMATICALLY after starting the engine without driving (speed = 0).

3.5. **Tachograph Printouts**

Printouts are also currently only available in POLISH. To print them, click the "Wydruk (24h)" translating - "Print (24h)" button.



The printout will be made in the console and saved as a .txt file


```
=====
WYDRUK OPERACYJNY CHRONOS RETRO 24H
=====
KIEROWCA:      JAN GŁOWACZ
AKTYWNOŚĆ:     ODPOCZYNEK
JAZDA CIĄGŁA:  00h00
JAZDA DZIENNA: 00h00
INNA PRACA:    00h00
ODPOCZYNEK:    00h00
PRZEDŁUŻENIA 10H: 0/2
POJAZD:
GODZINA ETS2:  00:00
MAGISTRALA API: ONLINE
=====
```


Translation of the tachograph printout:

Polish	English
<pre>===== ===== WYDRUK OPERACYJNY CHRONOS RETRO 24H ===== ===== KIEROWCA: JAN GŁOWACZ AKTYWNOŚĆ: ODPOCZYNEK JAZDA CIĄGŁA: oohoo JAZDA DZIENNA: oohoo INNA PRACA: oohoo ODPOCZYNEK: oohoo PRZEDŁUŻENIA 10H: 0/2 POJAZD: GODZINA ETS2: 00:00 MAGISTRALA API: ONLINE ===== =====</pre>	<pre>===== ===== WYDRUK OPERACYJNY CHRONOS RETRO 24H ===== ===== DRIVER: JAN GŁOWACZ ACTIVITY: ODPOCZYNEK CONTINUOUS DRIVING: oohoo DAYTIME DRIVING: oohoo OTHER WORK: oohoo REST: oohoo 10H EXTENSIONS: 0/2 VEHICLE: ETS2 HOUR: 00:00 API BUS: ONLINE ===== =====</pre>

3.6. Button Instructions

In this chapter, I will explain the operation of individual tachograph buttons and texts.







1. Backspace:
Always backspaces from screens 2 through 5 to screen 1.




2. up arrow (↑):
Changes the Screen (from 1 to 5) by adding (+) - translating to human language - if there is screen 1, then after clicking the arrow, screen 2 will appear




3. down arrow (↓):
Changes the Screen (from 1 to 5) by removing (-) - translating to human language - if there is screen 5, then after clicking the arrow, screen 4 will appear




4. OK:
Activates the extension of the driving time from 9 hours to 10 hours.



5. Driver 1:
Activates 1st driver - his times are then counted.




6. Driver 2:
Activates 2nd driver - his times are then counted.




7. Print (24h) [PL - Wydruk 24h] :
makes a printout from the tachograph

Meaning of the text on the tachograph screen:


Screen 1:



Screen 2:



Screen 3:



Screen 4:



Screen 5:



Well, it's impossible to describe everything, but practice makes perfect.

4. Useful Tips

Using this tachograph on a second screen would be nice, but not doing so will certainly be fantastic fun too. Other tips will likely appear here after the official release of the first version of the tachograph.

5. Conclusion and Copyrights

Thank you for reading this guide. If you have any questions, problems, or errors, please contact me on:

My Discord - @mr_jachowski21 - please mention that you're referring to the tachograph

My email - janglowacz25@gmail.com

Enjoy using my tachograph :)

Copyrights:

Tachograph version 1.0.0: Jan Głowacz, Mr_Jachowski21

Program for checking and installing: Jan Głowacz,

Mr_Jachowski21

Manual: Jan Głowacz, Mr_Jachowski21

Telemetry Server: Funbit - [Funbit \(Funbit\) · GitHub](#)

All rights reserved