JUNIT Unit Testing	Framework - [TestNG ANT
https://testng.org/doc/download.htm	nl
TestNG -, Next Generation	Unit Testing

Features of Test G: - Unit Testing Annotations > small piece of code, decides

the execution Methods sequence of starts mith s (a) Execution of methods happens alphabetically order

(2) Generate the Test Result Report (3) Parallel Execution on a Single M/c across

dels Growser (5) Prouping - login, logont, meale now, sompi deliteuser Smokes functionel, Regneration, Smokes functional, Regneration, (6) Assertions - for validations - if lebe X (F) depends On Mélhods - Login (), Logont () (8) Synore the TestiCase_

Note: In Testalgr There is no need of psv main() method.

A Before Test -> (a) Before Class - (1 Time) N.M. × (a Before Method 5 -> N.M. (I Time) Methode (a) Test -> for Test Case - Mandatory (a) After Method -, N.M (17tme) @ Aftulan (Test Suite 4 Mettion of TCs) @AfferTest ->
@AfterSwite ->

Before Test Before Class Before Method After Method Before Method After Melhod After After Class After Soute

- User Mynt 77 TC3 - Chrome "Close

- Jojin TG2
- Contact TC3

- @BeforeSuite this method gets Executed at project level, before the BeforeTest annotation or other annotations
- @BeforeTest this method gets Executed at before the beforeclass annotation
- @BeforeClass this method gets Executed at class level, before the execution of @test or any other annotations
- @BeforeMethod this method gets Executed before the each @Test method
- @Test aTestCase TestCase1
- @AfterMethod this method gets Executed after the each @Test method
- @BeforeMethod this method gets Executed before the each @Test method
- @Test bTestCase TestCase2
- @AfterMethod this method gets Executed after the each @Test method
- @AfterClass this method gets Executed at class level, after the execution of @test or any other annotations
- @AfterTest this method gets Executed after the afterclass or other annotation
- @AfterSuite this method gets Executed at project level, after the BeforeTest annotation or other annotations

```
<?xml version="1.0" encoding="UTF-8"?>
<!DOCTYPE suite SYSTEM "http://testng.org/testng-1.0.dtd">
<suite name="All Test Suite">
<test verbose="2" preserve-order="true" name="F:/Upgradation_Selenium/</p>
LearnSeleniumTool">
 <classes>
       <class name="testNGDemos.TestNGAnnotations">
         <methods>
           <include name="aTestCase"/>
           <include name="bTestCase"/>
           <include name="afterMethodAnnot"/>
           <include name="afterClassAnnot"/>
         </methods>
       </class>
       <class name="testNGDemos.TestNGAnnotations_realEx">
         <methods>
           <include name="browserLaunch"/>/
           <include name="launchApp"/>
           <include name="loginApp"/>
         </methods>
       </class>
     </classes>
  </test>
</suite>
```