# **UNIVERSITY OF KARACHI**



# **ASSEMBLY LANGUAGE PROGRAMMING**

BSCS-403

Name of Student: MUHAMMAD AMAS

Seat No: B20102077

Class Roll No: 34

Section: A

Semester No: 3rd

Submitted to: MS FARHEEN FAISAL SIDDIQUI

### **DEPARTMENT OF COMPUTER SCIENCE**

UNIVERSITY OF KARACHI

#### PROGRAM TO SWAP TWO NUMBERS:

```
File Edit Search View Options Help
                                C:NLT61.ASM
 DOSSEG
 MODEL SMALL : MODEL DIRECTIVE
 STACK 100H
              :STACK DIRECTIVE
 .DATA
               : VARIABLE DECLERATION
 .CODE
               :CODE SPACE
 MAIN PROC
 MOV AX, '1'
 PUSH AX
 MOV BX,'2'
 PUSH BX
 POP AX
 POP BX
 MOU DX,AX
 MOV AH,2
 INT 21H
 MOU DX,BX
 MOV AH,2
INT 21H
F1=Help
                                                    Line:1 Col:1
C:N>EDIT LTG1.ASM
C:\>MASM LT61.ASM;
Microsoft (R) Macro Assembler Version 5.00
Copyright (C) Microsoft Corp 1981–1985, 1987. All rights reserved.
 51710 + 464834 Bytes symbol space free
     0 Warning Errors
     O Severe Errors
C:\>LINK LT61.OBJ;
Microsoft (R) Overlay Linker Version 3.60
Copyright (C) Microsoft Corp 1983-1987. All rights reserved.
C:\>LT61.EXE
```

### PROGRAM TO REVERSE A STRING:

```
File Edit Search View Options Help
                               C:\LT62.ASM
 DOSSEG
 .MODEL SMALL :MODEL DIRECTIVE
 STACK 100H
              :STACK DIRECTIVE
              : VARIABLE DECLERATION
 .DATA
STRING DB'MUHAMMAD AMAS'
              :CODE SPACE
 .CODE
MAIN PROC
MOV AX,@DATA
MOU DS,AX
MOV SI, OFFSET STRING
MOU CX,13
L1:
MOV BX, [SI]
PUSH BX
INC SI
LOOP L1
MOV CX,13
L2:
POP DX
MOV AH,2
F1=Help
                                                   Line:1 Col:1
```

```
File Edit Search View Options Help
                                C:\LT62.ASM
 MOU SI, OFFSET STRING
 MOU CX,13
 L1:
 MOV BX, [SI]
 PUSH BX
 INC SI
 LOOP L1
 MOV CX,13
 L2:
 POP DX
 MOV AH,2
 INT 21H
 LOOP L2
 MOV AH, 4CH : TO EXIT THE REGISTER
 INT 21H
 MAIN ENDP
 END MAIN
                                                       Line:28
F1=Help
                                                                  Col:1
C:\>EDIT LT62.ASM
C:N>MASM_LT62.ASM;
Microsoft (R) Macro Assembler Version 5.00
Copyright (C) Microsoft Corp 1981-1985, 1987. All rights reserved.
 51632 + 464912 Bytes symbol space free
      0 Warning Errors
      O Severe Errors
C:\>LINK LT62.OBJ;
Microsoft (R) Overlay Linker Version 3.60
Copyright (C) Microsoft Corp 1983-1987. All rights reserved.
C:\>LT62.EXE
sama dammahum
C:/>_
```