

PNETLab | Topology

Ask Gemini

QEMU (Win1)

```
C:\WINDOWS\system32\cmd.exe
50.255.255.255 255.255.255.255 50.0.0.0 50.0.0.10 10
60.0.0.0 255.0.0.0 50.0.0.1 50.0.0.10 1
127.0.0.0 255.0.0.0 127.0.0.1 127.0.0.1 1
224.0.0.0 255.0.0.0 50.0.0.10 50.0.0.10 10
255.255.255.255 255.255.255.255 50.0.0.10 50.0.0.10 1
Persistent Routes:
None
C:\Documents and Settings\User>
C:\Documents and Settings\User>ping 50.0.0.10
Pinging 50.0.0.10 with 32 bytes of data:
Reply from 50.0.0.10: bytes=32 time=2ms TTL=127
Reply from 50.0.0.10: bytes=32 time=1ms TTL=127
Reply from 50.0.0.10: bytes=32 time=1ms TTL=127
Reply from 50.0.0.10: bytes=32 time=1ms TTL=127
Ping statistics for 50.0.0.10:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 0ms, Maximum = 2ms, Average = 0ms
C:\Documents and Settings\User>
```

QEMU (Win2)

```
C:\WINDOWS\system32\cmd.exe
50.0.0.0 255.0.0.0 50.0.0.10 50.0.0.10 10
60.255.255.255 255.255.255.255 60.0.0.0 60.0.0.10 10
127.0.0.0 255.0.0.0 127.0.0.1 127.0.0.1 1
224.0.0.0 255.0.0.0 60.0.0.10 60.0.0.10 10
255.255.255.255 255.255.255.255 60.0.0.10 60.0.0.10 1
Persistent Routes:
None
C:\Documents and Settings\User>ping 50.0.0.10
Pinging 50.0.0.10 with 32 bytes of data:
Reply from 50.0.0.10: bytes=32 time=1ms TTL=127
Reply from 50.0.0.10: bytes=32 time=1ms TTL=127
Reply from 50.0.0.10: bytes=32 time=1ms TTL=127
Reply from 50.0.0.10: bytes=32 time=1ms TTL=127
Ping statistics for 50.0.0.10:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 1ms, Maximum = 1ms, Average = 1ms
C:\Documents and Settings\User>
```

Router

```
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#int e0/0
Router(config-if)#ip address 50.0.0.1 255.0.0.0
Router(config-if)#no shutdown
Router(config-if)#exit
Router(config)#int e0/1
Router(config-if)#ip address 60.0.0.1 255.0.0.0
Router(config-if)#no shutdown
Router(config-if)#exit
Router(config)#do show ip int brief
Interface              IP-Address      OK? Method Status  Prot
ocol
Ethernet0/0             50.0.0.1        YES manual up      up
Ethernet0/1             60.0.0.1        YES manual up      up
Ethernet0/2             unassigned      YES TFTP  down    down
Ethernet0/3             unassigned      YES TFTP  down    down
Router(config)#
```

01 : 00 : 00 START