Using the Request and Server Context Through Built-in Object



Sekhar Srinivasan ARCHITECT @sekharonline4u www.sekhartheguru.net



Module Overview



Request

Response

PageContext

Out

Session

Application

Config



Request



Request Object Methods

```
setAttribute
getAttribute
getCookies()
getHeaderNames()
getHeader(string name)
getMethod()
get Parameter(string name)
getQueryString(string name)
getLocale()
```




Response



response object





sendRedirect(String location)
response.sendRedirect("sucess.jsp")

addCookie(Cookie cookie)
response.addCookie(userCookie)



Out



In Servlets

Prinitwriter out =response.getWriter();

In JSP

Out [Builtin Object]

jspWriter out=pagecontext.getout()

>Throws IOException



Out Builtin Object Methods

print
println
flush



out.print("Today is:"+java.util.Calendar.getInsatance().getTime());

Syntax

To display the current date and time



PageContext



Important Methods to PageContext setAttribute

getAttribute

findAttribute

removeAttribute



```
<%Float no1=new Float (62.5)%>
<%pageContext.setAttribute("no1",no1);</pre>
%>
<%pageContext.getAttribute("no1",no1)</pre>
%>
<%Float no2=new Float(84.3)%>
<%pageContext.setAttribute</pre>
("no2",no2,PageContext."SESSION SCO
PE");%>
<%pageContext.getAttribute</pre>
("no2",PageContext."SESSION SCOPE")
:%>
```

■ To set a page -scoped attribute

■ To read a page-scoped attribute

■ To set a session-scoped attribute


■ To read a session-scoped attribute



Session



Session Object





Session Builtin Object

setAttribute (String name,Object value)

getAttribute(String name)

removeAttribute(String name)



<% pageContext.setAttribute</pre>

("no",value,PageContext.SESSION_SCOPE); %>

<%session.setAttribute("no",value)%>

Syntax


To set the session



Application




Application Object



javax.servlet.ServletContext application=pageContext.getServeltContext()



Application Object





application.setAttribute(String name,Object value)

Syntax

To Set



application.setAttribute(String name)

Syntax


To Read



Config



Config Object





Config Implicit Object

```
getInitParameter(String name)
getInitParameterNames()
getServletContext()
getServletName()
```



Config Implicit Object

```
getInitParameter(String name)
getInitParameterNames()
getServletContext()
getServletName()
```



Summary



Request

Response

PageContext

Out

Session

Application

Config

