

Introduction

- Next two topics are interconnected, and they also are important for understanding how to manage the operating system
- Important terms:

CMOS - Complementary Metal Oxide Semiconductor . Chip stores the settings like date and time, fan speed, booting sequence

BIOS - Basic Input/Output System . Firmware to boot the computer

UEFI - Unified Extensible Firmware Interface . Bootloader

GRUB - GRand Unified Bootloader . Bootloader

ESP - EFI System Partition

GUID - Globally Unique Identifier (or UUID)

MBR - Master Boot Record . Partition table

GPT - GUID Partition Table . Partition table


Contents

1 General knowlage

2 Bootloaders

3 Partition tables

4 Sources



Computer boting procedure

Boot procedure

- It will be a very high-level overview of the boot process. For more precise, see [Operating systems](#) course.
- User pressing the button, completing the electronic circuit, and providing the power to all.
- The CPU starts up but needs some instructions to work on (remember, the CPU always needs to do something). Since the main memory is empty at this stage, CPU defers to load instructions from the firmware chip on the motherboard and begins executing instructions
- The firmware code does a Power On Self Test (POST), initializes the remaining hardware, detects the connected peripherals (mouse, keyboard, pen drive etc.), and checks if all connected devices are healthy. You might remember it as a 'beep' that desktops used to make after POST is successful.
- Finally, the firmware code cycles through all storage devices and looks for a bootloader (usually located in the first sector of a disk). If the bootloader is found, then the firmware hands over control of the computer to it.

Boot procedure

- So now that the bootloader is loaded, its job is to load the rest of the operating system. GRUB is one such bootloader that is capable of loading unix-like operating systems and is also able to chain-load Windows OS. The bootloader is only available in the first sector of a disk, which is 512 bytes. Given the complexity of modern operating systems, some of these bootloaders tend to do multi-stage loading, where the main bootloader loads the second-stage-bootloader in an environment, which is not restricted to 512 bytes.
- The bootloader then loads the kernel into memory. Unix-like operating systems then run the init process (the master process, from which other processes are forked/executed) and finally initialize the run-levels.
- After all this, and after some other drivers are initialized, the Graphical User Interface (GUI) is loaded, and you are presented with the login screen.




BIOS VS UEFI

BIOS BOOTING

BIOS


BASIC INPUT/OUTPUT
SYSTEM



UEFI BOOTING

UEFI

UNIFIED EXTENSIBLE FIRMWARE
INTERFACE



Bios

- BIOS is stored on an EPROM (Erasable Programmable Read-Only Memory), allowing the manufacturer to push out updates easily
- It provides many helper functions that allow reading boot sectors of attached storage and printing things on screen
- BIOS menu access is platform-dependent, but usually it's pressing 'Del' or 'F12' during the initial boot phase
- Intel is not supporting BIOS from 2020
- Uses only MBR partitions



UEFI

- UEFI does the same job as a BIOS
- Stores all data about initialization and startup in an **.efi** file, instead of storing it on the firmware
- This **.efi** file is stored on a special partition called ESP on the hard disk. This ESP partition also contains the bootloader
- UEFI supports bigger drive size, provides faster boot time, runs in 32-bit or 64-bit mode, can be used with GPT
- Has a **Legacy mode** - UEFI mode that behaves in a way as BIOS did



Bootloaders



Bootloaders overview

- Bootloader - a program responsible for booting the operating system
- Bootloader stored on a specific partition
- When PC is powered off, all data is stored on the non-volatile memory
- But for OS to work, it should be in the RAM
- Bootloader is responsible for loading the system to RAM
- There are too many platforms and too many ways how bootloaders could be used
- To simplify, here is an overview of: x86 architecture, modern Linux OS (kernel v5+)

GRUB

- GRUB - most wide-common used bootloader for our systems from the GNU project
- Can be used in both **UEFI** and **Legacy** modes
- If installed, during booting GRUB loads **/boot/grub/grub.cfg** file. Do not edit it!
- To change anything in that file, change it only in **/etc/default/grub** (remember, there are all setting files) and then use command
`grub-mkconfig -o /boot/grub/grub.cfg`
- But **GRUB** is too old and slow.
- More about it is on [Arch wiki](#)



systemd-boot

- Simple UEFI boot manager
- Executes configured EFI images
- Included with `systemd`
- Can only start EFI executables such as UEFI Shell, `Linux EFISTAB` , Windows, GRUB, Windows boot manager etc
- Can be installed only with ESP mounted
- Much faster than all other bootloaders (if your init system is `systemd`) which is true for both Manjaro and Arch (Ubuntu also)
- The reason - it starts fewer things in general and starts almost everything in parallel
- Simple in maintaining and setting up:
- `bootctl install` for installation
- `/boot/loader/entries/` is a location for config files. If you want to add new entry, just add new `.conf` file here



PARTITION TABLES

Partitioning

- Linux see each device as a separate file a.e. `/dev/sdX`, `/dev/nvmeOnX`
- **Partitioning** - adding logical devices remaining the same amount of physical. It make possible to manage each partition separate
- Each such logical device called partition
- **Partition table** - area on a disk where the disk stores the information about every partition
- **Partition editors** can be used to add/delete, adit new partitions (a.e. `fdisk`, `cfdisk`, `parted`, `gparted`)

```
Disk: /dev/sda
      Size: 223.6 Gib, 240057409536 bytes, 468862128 sectors
      Label: gpt, identifier: E471810B-5954-48E6-B4F0-5D369ADCC514

      Device        Start        End    Sectors   Size Type
>> /dev/sda1       2048     411647    409600  200M EFI System
      /dev/sda2     411648     821247    409600  200M Linux filesystem
      /dev/sda3     821248   274087935   273266688 130.3G Linux filesystem
      /dev/sda4   274087936   378945535   104857600   50G Linux filesystem
      /dev/sda5   378945536   452476927   73531392   35.1G Linux filesystem
      /dev/sda6   452476928   468860927   16384000    7.8G Linux swap


Partition name: EFI System Partition
Partition UUID: 2062335E-51B6-49E8-BC3C-4C6D449E6805
Partition type: EFI System (C12A7328-F81F-11D2-BA4B-00A0C93EC93B)
  Filesystem: vfat
  Filesystem label: EFI
  Filesystem UUID: F2BC-BFEC
  Mountpoint: /boot/efi (mounted)

[ Delete ] [ Quit ] [ Type ] [ Help ] [ Write ] [ Dump ]
```

Master boot record

What everybody should know about MBR ?

- Very old, unfortunately still not deprecated, and you can see it even on the very new laptops
- Don't support UEFI
- Max disk size - 2TB. If you have more, only 2TB will be visible
- Only four general partitions available
- **Do not use it, use GPT!**
- The best and easiest way - delete or move everything from the physical disk and change the partition table
- Otherwise - there are some applications for Windows/Linux how to make it without data loss (usually quite expensive)




GUID Partition Table

What about GPT ?


- GPT - also quite old - 30 years - but conceptually still the best way for partitioning
- Can support UEFI
- 128 partitions available
- Max disk size - 18EB. As far as the biggest HDD's I know are only 18TB each it won't be a limitation for nearest decades

GUID Partition Table Scheme



How and why to use partitioning?

- Usually partitioning is used only when installing a new OS or changing partitions info (add/remove swap, etc)
- Usually `cfdisk` is used for such manipulations
- For more deep things (create, change, remove table) `parted`, `Gparted`, `fdisk` are recommended
-



Sources

Sources

- UCU Linux Club resources
- Boot procedure
- Wiki Bootloader
- GRUB Arch Wiki
- Systemd-boot Arch wiki
- GRUB vs systemd-boot
- Partitioning Arch wiki