
DORETTE

CROCHET STUDIO

Version 1.6.0

A practical guide to design milestones, stitch notes, accessible chart viewing, measurement, grid-snapped shapes, and simulated crochet texture.



FOR DORETTE | NOVEMBER 2026

New in v1.6.0 + the complete v1.5 tool reference

Contents and navigation

NEW IN VERSION 1.6.0

Safe upgrade and practice test 3

Beginner view and visibility se... 4

Save and compare design versions 5

Attach stitch, row and section ... 6

Measure and draw grid shapes 7

Simulated finished-stitch preview 8

Release testing and boundaries 9

COMPLETE STUDIO REFERENCE

Cover 10

Contents 11

Getting started and safeguardin... 12

Explore the workspace 13

Read the numbered grid 14

Detect an imported crochet grid 15

Straighten photos and remove ba... 16

Simplify photos to fewer colors 17

Text, symbols and favorite styles 18

Edit, drag and resize layers 19

Expand, crop or scale the chart 20

Crochet technique presets 21

Work on large chart sections 22

Analyze yarn-color changes 23

Pattern quality and cleanup 24

Personal yarn colors and size 25

Project gallery, templates and ... 26

Export as PDF, PNG or SVG 27

Samsung tablet and screen-awake... 28

Backups, compatibility and limi... 29

Real-device testing checklist 30

Tap a chapter to jump to it. The PDF sidebar also includes chapter bookmarks.

Start safely: protect existing work

1 Back up projects in the CURRENT Studio

On your existing GitHub Pages website, choose Back up all and save the PROJECT backup ZIP privately. Do not confuse the project backup with an application source-code ZIP.

2 Install the GitHub update

Extract v1.6.0-GitHub-Update.zip, upload its CONTENTS to the ROOT of the existing Dorette-Crochet-Studio repository, then commit. Do not upload the enclosing folder.

3 Refresh without erasing browser storage

Open the same GitHub Pages address in the same browser and profile. Confirm the v1.6.0 badge. Never clear site data or uninstall the installed app as a troubleshooting step.

4 Practice first

Use a new 10 x 10 or 25 x 25 project to test versions, notes, shapes, Undo, guide buttons, chart PDF, and ZIP restore before modifying a cherished design.

What is and is not synchronized

Projects and their design versions/notes stay in this browser and are included in project ZIP backups. Separate yarn libraries, motifs, and text favorites are device-local and do not sync automatically.


Original website

mythrilman86.github.io/Dorette-Crochet-Studio/

Append ?v=160 to check the new deployment online.

Beginner mode and visual accessibility

Use the display bar above the chart



Beginner and Advanced

Beginner hides the more complex editing panels and tools but leaves project data intact. Switch back to Advanced when you need layers, quality analysis, shapes or version history.

High-contrast and color cues


High-contrast grid darkens the grid outlines. Yarn shape cues overlays distinct marks on colored stitch squares when they are large enough to draw. Emphasize yarn letters displays yarn symbols at smaller zoom levels when legible.

Bigger number labels and rulers

Set Number size to Standard, Large or Extra large. The ruler switch is in Stitch Ruler & Measurement and places tick marks along the chart margins every five squares.

Tip: if two yarn shades look similar, enable both high contrast and yarn shape cues. These are viewing aids; they do not change yarn colors or the exported chart.

Project version history



SAVE

Give the current design a meaningful name, then Save design version.

COMPARE

Choose an earlier version to see side-by-side thumbnails and a changed-stitch count.


RESTORE

Restore as copy creates a new project. Your current one stays untouched.

Why this is useful

Save a design before changing wording, resizing motifs or trying new colors. The Studio stores up to eight named versions per project. If there are more, the oldest named milestone is replaced. Versions are included in project-backup ZIPs.

Stitch, row and section notes



ATTACH

Select a square or working section, choose the note scope, type a reminder, then tap Add reminder.

JUMP OR REMOVE


Tap a saved reminder to move the working chart to its stitch, row or section. Remove deletes that reminder.

ON THE CHART

Small orange indicators identify attached reminders. The note never changes the stitch color.

To print reminders, enable the extra checklist and project notes pages in Printable PDF Export. The PDF notes text has a length limit; keep your full notes in the project ZIP.

Measure stitches and draw shapes



SELECT AN AREA

Choose Select area, then drag across the working chart to establish two corners.

MEASURE

Click Measure selected area. The panel shows stitch columns, rows, totals, and approximate real dimensions if you entered a measured gauge.


DRAW A SHAPE

Choose straight line, outline/filled rectangle, ellipse or circle. Preview the orange cells. Select a yarn color and Apply shape. Undo is available.

Keep stitch placement precise

All shapes snap to the square stitch grid. Circles/ellipses are pixel-like approximations. Physical size depends on your swatch, yarn, crochet technique and tension.

Preview a crocheted appearance



1. Choose a stitch texture style.
2. Click Preview crocheted appearance.
3. Compare the chart and simulated texture.

Important limitation

The texture shows a repeatable visual suggestion of stitches. It does not model true fabric tension, stitch height, physical yarn fibers, hook size, drape, or finished garment shape. It never modifies chart cells.

Release testing and device checklist

- [ ] Create a small practice chart, then save and compare a named version.
- [ ] Add a stitch note, open it, remove it, and create a row reminder.
- [ ] Use Select area; preview and apply a line, rectangle, and circle.
- [ ] Confirm Undo removes a shape without changing an editable text layer.
- [ ] Measure 10 x 10 stitches using a real swatch and inspect the ruler.
- [ ] Switch Beginner / Advanced, high contrast, number size and yarn cues.
- [ ] Preview soft and detailed simulated crochet textures side by side.
- [ ] Export a chart PDF with extra notes; inspect the printed reminder.
- [ ] Back up and restore an updated project ZIP as a NEW project.
- [ ] Try pinch/zoom and stylus on the actual Samsung tablet.
- [ ] Open the installed Studio while online once, then check offline use.

Safety and compatibility

Database name/version, active-project key and the project-backup version remain unchanged. No background cloud synchronization or hands-free voice controls were added. Samsung S Pen behavior and offline installation require real-device checks.


The following appendix preserves the full v1.5 tool reference.

DORETTE CROCHET STUDIO

Create. Edit. Crochet.

Version 1.5.0

Illustrated guide to accurate crochet grids, editable layers, yarn planning, guided progress, pattern exports, and safe project backups.



Row 1 is always at the bottom. Every square represents one chart cell.

Contents

Select a chapter to jump directly to that page. Use the bookmark panel in your PDF reader for navigation.

03 Getting started and safeguarding projects

04 Explore the workspace

05 Read the numbered grid

06 Detect an imported crochet grid

07 Straighten photos and remove backgrounds

08 Simplify photos to fewer colors

09 Text, symbols and favorite styles

10 Edit, drag and resize layers

11 Expand, crop or scale the chart

12 Crochet technique presets

13 Work on large chart sections

14 Analyze yarn-color changes

15 Pattern quality and cleanup

16 Personal yarn colors and size

17 Project gallery, templates and duplicates

18 Export as PDF, PNG or SVG

19 Samsung tablet and screen-awake controls

20 Backups, compatibility and limitations

21 Real-device testing checklist

Getting started and safeguarding projects


- Open the published Dorette Crochet Studio URL in the browser profile where your projects already live. The v1.5.0 version badge confirms the code has updated.

- Before replacing GitHub files, use Back up all in the previous Studio and privately save that ZIP. Application ZIP files are not project backups.

- Projects use the same existing IndexedDB database and are saved on that device; downloading a ZIP does not upload or share the project.

- Restore project backups through the Studio Restore button. Restores create new project copies instead of overwriting originals.

ILLUSTRATIVE VIEW / NOT A LIVE SCREENSHOT




Note: Some advanced features may depend on device or browser support.

Explore the workspace

- Use Create for images and lettering, Edit for painting and layered design, and Crochet for following a pattern.
- Switch Single or Dual charts. The left overview fits the whole design; the working chart lets you pan and zoom.
- Show/hide the Projects and Settings panels when you need more space. Chart split allocates width between the two charts on wider screens.
- Pin crochet controls to keep the progress dock visible; unpin it if you prefer it to scroll.

ILLUSTRATIVE VIEW / NOT A LIVE SCREENSHOT




Note: Some advanced features may depend on device or browser support.

Read the numbered grid

- Every square is one crochet chart cell. Column 1 is at the LEFT and column numbers increase toward the RIGHT.
- Row 1 starts at the BOTTOM. Row numbers increase upward. This orientation is preserved in PDF exports.
- At an overview scale, only some row and column numbers appear for legibility; zoom in to inspect each boundary.
- The highlighted square, row and column appear in both views and share exactly the same project data.

ILLUSTRATIVE VIEW / NOT A LIVE SCREENSHOT



Row 1 at bottom; column 1 at left

Note: Some advanced features may depend on device or browser support.

Detect an imported crochet grid


- Import an existing gridded image in Image to Chart; open Detect existing chart grid & clean photo background.

- Analyze visible source grid estimates the count of repeated dark grid lines. Results include an approximate line-regularity score.

- Compare detected numbers with the ORIGINAL squares, not line counts. Correct the Columns and Rows fields manually if necessary.

- The detector works best with high-contrast, unwarped grid images. Complex art, shadows, warped grids or missing borders may not detect reliably.

ILLUSTRATIVE VIEW / NOT A LIVE SCREENSHOT



Verify 12 columns and 9 rows

Note: Some advanced features may depend on device or browser support.

Straighten photos and remove backgrounds


- If an imported photo is slightly rotated, use the rotation correction slider and Straighten source image; this rotates the reference image, not the saved stitch colors.

- Remove similar background from edges uses the colors at the four photo corners as a starting estimate, removing matching connected background.

- Choose Background tolerance carefully; high values can remove parts of a light-colored subject. Undo or reimport the source if the result is too aggressive.

- Always Preview stitches and inspect the full chart before applying converted colors.

ILLUSTRATIVE VIEW / NOT A LIVE SCREENSHOT



Note: Some advanced features may depend on device or browser support.

Simplify photos to fewer colors


- Choose Grayscale conversion to reduce the chart to a limited number of black, white and gray yarns.

- The side-by-side 2 / 3 / 4 gray comparison displays the same source with different shade counts. Choose Preview on chart for a candidate.

- A limited palette can make crocheting simpler but may lose fine details. Preview both overall shapes and fine lettering at high zoom.

- Use the existing color-palette and Replace Everywhere tools when you need to merge a particular yarn shade.

ILLUSTRATIVE VIEW / NOT A LIVE SCREENSHOT



Preview 2, 3 and 4 gray variations

Note: Some advanced features may depend on device or browser support.

Text, symbols and favorite styles


- Enter letters, words, numbers or symbols; choose a stitch-friendly style, letter height, spacing, wrapping, rotation and layout.

- Preview before Apply. Applying creates an editable text layer instead of permanently painting the base pattern.

- Select an area with Select area, then use Auto-fit or Center in selected area for precise placement.

- Save your preferred font/spacing/size combinations under Saved lettering style and reuse them in another project. The style library is stored on this device.

ILLUSTRATIVE VIEW / NOT A LIVE SCREENSHOT



Note: Some advanced features may depend on device or browser support.

Edit, drag and resize layers


- Select an editable text or motif layer in the Layers list. It can be shown, hidden, locked, reordered, duplicated or flattened.

- Enable Drag or resize selected layer directly on the working chart. Drag inside the orange outline to move the layer.

- Drag the orange upper-right handle to resize on the stitch grid, or select an area and press Fit selected layer into chosen area.

- Resizing converts the artwork into a stitched shape. The original typeface metrics may no longer be editable after resizing; Undo or keep a duplicate layer.

ILLUSTRATIVE VIEW / NOT A LIVE SCREENSHOT



Note: Some advanced features may depend on device or browser support.

Expand, crop or scale the chart


- In Chart settings, choose new column and row counts, then open Advanced canvas resize / crop.

- Expand / crop canvas maintains original stitch size. Choose center, left, right, top or bottom anchor to control where existing stitches land.

- Scale entire chart remaps all the stitch cells and editable layers using nearest-neighbor mapping; it changes visual proportions and can lose detail.

- Cropping removes cells outside the smaller grid. Make a project backup beforehand and review the result before further work.

ILLUSTRATIVE VIEW / NOT A LIVE SCREENSHOT



Resize with care: expand != scale

Note: Some advanced features may depend on device or browser support.

Crochet technique presets


- Standard colorwork, tapestry colorwork and single-crochet graph presets use normal row-by-row chart progression.

- The Corner-to-corner (C2C) preset adds a separate diagonal chart-cell progress path and buttons for stepping backward or completing the next diagonal cell.

- C2C chart cells are NOT full instructions for C2C block construction, shaping, turning chains, increases or decreases. Follow a trustworthy technique pattern for those details.

- You can switch presets without changing the saved yarn-color grid.

ILLUSTRATIVE VIEW / NOT A LIVE SCREENSHOT




C2C chart-cell path moves diagonally

Note: Some advanced features may depend on device or browser support.

Work on large chart sections

- Choose 20, 25, 30 or 40-stitch sections. Each section specifies its absolute column and row range.
- Jump to section centers the working chart on the selected area. Complete section marks those chart cells finished without recoloring the yarn.
- Purple boundaries are shown on both chart views and numbered PDF detail pages.
- The PDF can include a section checklist. Large charts may have more sections than fit on its first checklist page; the Studio remains the complete section list.

ILLUSTRATIVE VIEW / NOT A LIVE SCREENSHOT



Purple boundaries mark working sections

Note: Some advanced features may depend on device or browser support.

Analyze yarn-color changes


- Use Analyze yarn changes by row to review total horizontal color transitions and the rows with the most changes.

- The isolated-stitch suggestion highlights a limited set of cells whose color differs from both horizontal neighbors.

- The orange preview is a PROPOSAL, not proof of an error. Preserve highlights such as eyes, letters, outlines and deliberate accent stitches.

- Apply previewed suggestions changes only base chart cells. Undo restores the previous version.

ILLUSTRATIVE VIEW / NOT A LIVE SCREENSHOT




Inspect isolated colors before simplifying

Note: Some advanced features may depend on device or browser support.

Pattern quality and cleanup

- Run the existing quality checker to see isolated islands, edge colors, empty rows and overall transitions.
- Use Inspect row to jump to color-heavy rows. Also zoom to problem areas and look at neighboring rows.
- Smart cleanup previews orange proposed fixes for isolated color patches. Protect important selected areas and apply only after reviewing the preview.
- Cleanups do not automatically change the intended technique, carried yarns, or construction methods.

ILLUSTRATIVE VIEW / NOT A LIVE SCREENSHOT



Zoom to inspect possible problem stitches

Note: Some advanced features may depend on device or browser support.

Personal yarn colors and size


- Save regularly used yarn names, RGB colors and available inventory in the personal yarn library.

- Find closest saved yarn offers an approximate computer color-distance match. It is not a guarantee about brand, dye lot or how a real skein appears in daylight.

- Enter an actual crochet swatch to estimate project size and yarn amount. Generic counts alone cannot accurately predict yardage.

- Yarn and motif libraries are stored locally in that browser and are not automatically included with project backup ZIPs.

ILLUSTRATIVE VIEW / NOT A LIVE SCREENSHOT




Note: Some advanced features may depend on device or browser support.

Project gallery, templates and duplicates

- Search your projects by name or category. Select the category filter or show favorites only to narrow the gallery.
- Use the star on a gallery item to favorite it. Use Duplicate current project to experiment safely with a separate copy.
- New-project templates offer square designs, blankets, border strips and initials, with editable dimensions in the Create form.
- Thumbnails are generated from the saved color cells and visible layers; they are not uploaded online.

ILLUSTRATIVE VIEW / NOT A LIVE SCREENSHOT




Note: Some advanced features may depend on device or browser support.

Export as PDF, PNG or SVG

- Printable PDF exports the full chart, yarn legend, numbered stitch pages, and optional completed-stitch indicators and page overlap.
- Select Include section checklist & project notes PDF pages to append a checklist and the notes you typed in PDF Export.
- PNG provides a convenient raster picture. SVG is a vector image suitable for further resizing. Export sizes depend on your selected pixels-per-stitch scale.
- Use the project ZIP, not an image or printed PDF, if the recipient needs to continue editing the pattern and progress.

ILLUSTRATIVE VIEW / NOT A LIVE SCREENSHOT




Note: Some advanced features may depend on device or browser support.

Samsung tablet and screen-awake controls

- On the Galaxy Tab, test single and dual layouts, zoom and finger gestures, and the S Pen before starting an important pattern.
- Pattern lock can prevent accidental paint changes during crochet. Stylus-only editing lets a pen paint while fingers navigate.
- Keep screen awake is optional and requests the browser Screen Wake Lock API while Crochet View is active. It may be unavailable or denied by device policies or power-saving mode.
- Switch out of Crochet View or turn the setting off when you do not need the display to stay awake.

ILLUSTRATIVE VIEW / NOT A LIVE SCREENSHOT




Note: Some advanced features may depend on device or browser support.

Backups, compatibility and limitations

- Back up all projects before installing code updates. Do not clear browser storage, uninstall the PWA, or change the GitHub Pages site origin when you have unsynced projects.
- Version 1.5 keeps the existing dorette-crochet-studio IndexedDB database and version 1 ZIP project payload.
- Older projects can be restored into this version as separate copies. Versions older than 1.4 may not preserve new editable-layer metadata if a newer ZIP is restored into those old versions.
- The app remains offline-first/local; motif, yarn and favorite-lettering libraries do not automatically sync between devices.

ILLUSTRATIVE VIEW / NOT A LIVE SCREENSHOT




Note: Some advanced features may depend on device or browser support.

Real-device testing checklist

- Test a fresh 10 x 10 practice chart first. Check paints, Undo, layers, row progress, diagonal chart cells, and section completion.
- Import a high-contrast gridded image. Check detected columns/rows manually, then preview grayscale and background-removal results.
- Export and restore a practice project ZIP. Verify layers, notes, category, technique and progress after restore.
- Generate chart PDFs, PNG and SVG files. On the physical Galaxy Tab, verify S Pen, touch mode, screen awake and installed-app offline reload.

ILLUSTRATIVE VIEW / NOT A LIVE SCREENSHOT



Note: Some advanced features may depend on device or browser support.