NAME

split − split a file into pieces

SYNOPSIS

split [*OPTION*]... [*INPUT* [*PREFIX*]]

DESCRIPTION

Output fixed−size pieces of INPUT to PREFIXaa, PREFIXab, ...; default size is 1000 lines, and default PREFIX is 'x'. With no INPUT, or when INPUT is −, read standard input.

Mandatory arguments to long options are mandatory for short options too.

−a, **−−suffix−length**=*N*
> generate suffixes of length N (default 2)

−−additional−suffix=*SUFFIX*
> append an additional SUFFIX to file names

−b, **−−bytes**=*SIZE*
> put SIZE bytes per output file

−C, **−−line−bytes**=*SIZE*
> put at most SIZE bytes of lines per output file

−d, **−−numeric−suffixes**[=*FROM*]
> use numeric suffixes instead of alphabetic; FROM changes the start value (default 0)

−e, **−−elide−empty−files**
> do not generate empty output files with '−n'

−−filter=*COMMAND*
> write to shell COMMAND; file name is $FILE

−l, **−−lines**=*NUMBER*
> put NUMBER lines per output file

−n, **−−number**=*CHUNKS*
> generate CHUNKS output files; see explanation below

−u, **−−unbuffered**
> immediately copy input to output with '−n r/...'

−−verbose
> print a diagnostic just before each output file is opened

−−help display this help and exit

−−version
> output version information and exit

The SIZE argument is an integer and optional unit (example: 10K is 10*1024). Units are K,M,G,T,P,E,Z,Y (powers of 1024) or KB,MB,... (powers of 1000).

CHUNKS may be: N   split into N files based on size of input K/N   output Kth of N to stdout l/N split into N files without splitting lines l/K/N   output Kth of N to stdout without splitting lines r/N   like 'l' but use round robin distribution r/K/N   likewise but only output Kth of N to stdout

AUTHOR

Written by Torbjorn Granlund and Richard M. Stallman.

REPORTING BUGS

GNU coreutils online help: <http://www.gnu.org/software/coreutils/>
Report split translation bugs to <http://translationproject.org/team/>

COPYRIGHT

This is free software: you are free to change and redistribute it. There is NO WARRANTY, to the extent permitted by law.

SEE ALSO

Full documentation at: <http://www.gnu.org/software/coreutils/split>
or available locally via: info '(coreutils) split invocation'