

Test Case ID	Test Case Summary	Related Requirement	Test Procedure	Test Data	Priority	Expected Result	Actual Result	Status	Remarks	Test Case Author	Executed By	Test Environment	Frequency
TC-0001	Check whether user can login with wrong password	User logging	1. Go to the application 2. Then goto Login page 3. Enter username in the field 4. Enter wrong password in the password field	username: Raida password: 1111	High	1. proper error message will be dispalyed "The Username and/or password you entered does not match our records. Try again."		Not Executed		Namisa		Browser: Chrome Server Info: Device Info-Dell Laptop Others:	0
TC-0002	Check whether user can login with correct password	User logging	1. Go to the application 2. Go to the Login page 3. Enter username in the field 4. Enter correct password in the password field	username: standard_user password: secret_sauce	High	1. User should be redicted to the products page		Not Executed		Namisa		Browser: Chrome Server Info: Device Info-Dell Laptop Others:	0
TC-0003	Check whether user can login with empty username field	User logging	1. Go to the application 2. Go to the Login page 3. Keep the username field empty 4. Enter correct password in the password field	username: password: secret_sauce	Medium	1. proper error message will be displayed "The username field cannot be empty. Try again"		Not Executed		Namisa		Browser: Chrome Server Info: Device Info-Dell Laptop Others:	0
TC-0004	Check whether user can login with empty password field	User logging	1. Go to the application 2. Go to the Login page 3. Enter the username 4. Keep the password field empty	username: standard_user password:	Medium	1. proper error message will be displayed "The password is incorrect. Try again"		Not Executed		Namisa		Browser: Chrome Server Info: Device Info-Dell Laptop Others:	0
TC-0005	Check whether user can logout from the website	user log-out	1. Go to the application 2. Log in successfully 3. Go to the products page 4. Click on the sidebar 5. Click the logout button	username: standard_user password: secret_sauce	Medium	1. User is logged out and redirected to the Login page.		Not Executed		Namisa		Browser: Chrome Server Info: Device Info-Dell Laptop Others:	0
TC-0006	Check whether user can add item to the cart	Cart functionality	1. Log in Successfully 2. Click "add to cart" button for an item	username: standard_user password: secret_sauce	High	1. Item is added to cart and the cart icon is updated		Not Executed		Namisa		Browser: Chrome Server Info: Device Info-Dell Laptop Others:	0
TC-0007	Check whether user can remove item from the cart	Cart functionality	1. Log in successfully 2. Click "Add to cart" 3. Click "remove" button	username: standard_user password: secret_sauce	High	1. Item is removed from the cart and the cart icon is updated		Not Executed		Namisa		Browser: Chrome Server Info: Device Info-Dell Laptop Others:	0
TC-0008	Check whether user can checkout correctly	Checkout functionality	1. Log in successfully 2. Add an item to cart 3. Proceed to checkout 4. Enter checkout details 5. Complete the order	username: standard_user password: secret_sauce	High	1. Order is compleeted and confirmation page is shown		Not Executed		Namisa		Browser: Chrome Server Info: Device Info-Dell Laptop Others:	0
TC-0009	Check whether user can sort items by price	Product listing functionality	1. Log in successfully 2. Click the sort dropdown button 3. Select "Price(high to low)"	username: standard_user password: secret_sauce	Medium	1. Products are sorted by price in descending order.		Not Executed		Namisa		Browser: Chrome Server Info: Device Info-Dell Laptop Others:	0
TC-0010	Check whether user can sort items by name	Product listing functionality	1. Log in successfully 2. Click the sort dropdown button 3. Select "Name(A to Z)"	username: standard_user password: secret_sauce	Medium	1. Items are sorted by name in ascending order		Not Executed		Namisa		Browser: Chrome Server Info: Device Info-Dell Laptop Others:	0
TC-0011	Check whether product details are displayed correctly	Product Information functionality	1. Log in successfully 2. Click on any product	username: standard_user password: secret_sauce	Medium	1. Product details page shows correct information		Not Executed		Namisa		Browser: Chrome Server Info: Device Info-Dell Laptop Others:	0
TC-0012	Check whether App state is reset after clicking "Reset app state" button	Session management	1. Log in successfully 2. Add an item to cart 3. Click "Reset app state" button	username: standard_user password: secret_sauce	Low	1. The cart should be empty		Not Executed		Namisa		Browser: Chrome Server Info: Device Info-Dell Laptop Others:	0
TC-0013	Check whether App state is in the same state after loggin out and loggin in again	Session management	1. Log in successfully 2. Add an item to cart 3. Log out 4. Log in with correct credentials	username: standard_user password: secret_sauce	Medium	1. The cart should be in the previous state and the icon should be updated accordingly		Not Executed		Namisa		Browser: Chrome Server Info: Device Info-Dell Laptop Others:	0
TC-0014	Check whether the footer links work or not	UI elements	1. Log in successfully 2. Scroll to the footer section 3. Click on the "x", "facebook", "linkedin" buttons	username: standard_user password: secret_sauce	Low	1. The page should be redirected to respective links		Not Executed		Namisa		Browser: Chrome Server Info: Device Info-Dell Laptop Others:	0
TC-0015	Check whether user can checkout with empty cart	Cart functionality	1. Log in functionality 2. Click on the cart icon 3. Proceed to checkout	username: standard_user password: secret_sauce	Medium	1. Proper error message should be shown "Cart cannot be empty while checking out"		Not Executed		Namisa		Browser: Chrome Server Info: Device Info-Dell Laptop Others:	0