

ECO Triplet-w QA Checklist

Inspected by Sales or Repair Order Date

Customer

Sensor

ECO S/N Optics head S/N Pressure test

Channel 1 Channel 2 Channel 3

Other options Hardware options

Documentation

Sensor build checklist

Number of Cal/Char sheet(s)

Laminate the Calibration sheet(s) ☒

On CD:

Sensor user manual

ECOView user manual

ECOView software

Device file ☒

Repair summary

Parts

Lock collar, dummy plug S/N label

Spare parts card UV Warning label

Test cable Mounting bracket

Verify jumper plug (battery units) Check torque of bulkheads ☒

Functionality

Output in N/U column

Ch 1	Ch 2	Ch 3
NTU 700 nm	Chl 695 nm	CDOM 460 nm

From Cal/Char sheet

Scale Factor	0.0487	0.0182	0.0907
Dark Counts	50	47	49
Max output	4130	4,130.0000	4130

Set number of samples to 0	☒	Clear internal memory	☒
Check sample rate ~ 1 Hz	☒	Internal battery voltage	9.27
Turn on internal logging	☒	S/N in output	☒
Sensor has no mechanical defects	yes	Get screen captures of Raw Data and Setup tabs	☒
Check for saturation	☒	No continuity to plating of faceplate (anodizing)	N/A

Notes

Incoming settings in repaired sensors ☐ Save a copy of cal folder into the order folder ☐

ECO View: v1.23 Apr 9 2013 ECO: Ver Triplet5.33

File

Host: 10/31/18 10:24:22
ECO: 11/01/18 10:24:37
Sample Rate: 1.01 Hz

Recording: OFF
Raw File:
Raw File Size: 0 K
Device File: D:\BBFL2WB-1755.dev
Engr Units File:
Engr Units File Size: 0 K

Stop Data

Start Data

Record Raw

Record Engr

Stop Record

Shutter Status: Open

Bytes Read: 14129

Host Port Selection
Host Port - COM 3

19200 Baud

Meter Setup | NTU-Setup | Raw Data | Plot Data | Transfer Data

11/01/18 10:24:29	700	4130	695	525	460	4130	530
11/01/18 10:24:30	700	4130	695	525	460	4130	530
11/01/18 10:24:31	700	4130	695	525	460	4130	530
11/01/18 10:24:32	700	4130	695	525	460	4130	530
11/01/18 10:24:33	700	4130	695	525	460	4130	530
11/01/18 10:24:34	700	4130	695	525	460	4130	530
11/01/18 10:24:35	700	4130	695	525	460	4130	530
11/01/18 10:24:37	700	4130	695	525	460	4130	530

Ser BBFL2WB-1755
Ver Triplet5.33
Ave 18
Pkt 0
M1d 50
M2d 47
M3d 49
M1s 4.870E-02
M2s 1.820E-02
M3s 9.070E-02
Seq 0
Rat 19200
Set 0
Rec 0
Man 0
Int 00:00:15
Dat 11/01/18
Clk 10:24:37
Mst 18:50:55
Mem 0
\$sto
done

Send w/o CR LF

ECO View: v1.23 Apr 9 2013 ECO: Ver Triplet5.33

File

Host: 10/31/18 10:24:22
ECO: 11/01/18 10:24:37
Sample Rate: 1.01 Hz

Recording: OFF
Raw File:
Raw File Size: 0 K
Device File: D:\BBFL2WB-1755.dev
Engr Units File:
Engr Units File Size: 0 K

Stop Data

Start Data

Record Raw

Record Engr

Stop Record

Shutter Status: Open

Bytes Read: 14129

Host Port Selection
Host Port - COM 3

19200 Baud

Meter Setup | NTU-Setup | Raw Data | Plot Data | Transfer Data

Change Settings To

Current Ram Settings

Set Avg / Data Rate 30 Average: 18 Sample Rate: 1.01 Hz

Set Number of Samples 0 Number of Sample: 0

Set Number of Cycles 1 Number of Cycles: 0

Set Cycle Interval HHMMSS Cycle Interval: 00:00:15

Turn Logging ON Internal Log: Logging: OFF

Erase Memory Used: 0 K 0.0 % Free: 1055 K 100% No version found

Open Shutter

Close Shutter

Get Date/Time/Setup

Set Date

Set Time

Store To Flash

Get RAM Setup

Reload Flash Setup

Get Device File