

GENERAL ASSEMBLER DIRECTIVES

Table 6-1 (Cont.)
Directives in Chapter Six

Directive	Function	Section Reference
.ASECT	Similar to .PSECT.	6.7.2
.BLKB	Allocates bytes of data storage.	6.5.3
.BLKW	Allocates words of data storage.	6.5.3
.BYTE	Stores successive bytes of data.	6.3.1
.CROSS	Enables cross reference.	6.2.2
.CSECT	Similar to .PSECT.	6.7.2
.DSABL	Disables specified assembler functions.	6.2.1
.ENABL	Enables specified assembler functions.	6.2.1
.END	Indicates end of source input.	6.6
.ENDC	Indicates end of conditional assembly block.	6.9.1
.EVEN	Ensures that current value of the location counter is even.	6.5.1
.FLT2	Generates 2 words of storage for each floating-point number argument.	6.4.2.1
.FLT4	Generates 4 words of storage for each floating-point number argument.	6.4.2.1
.GLOBL	Defines listed symbols as global.	6.8.1
.IDENT	Provides additional means of labeling an object module.	6.1.4
.IF	Assembles block if specified conditions are met.	6.9.1
.IFF	Assembles block if condition tests false.	6.9.2
.IFT	Assembles block if condition tests true.	6.9.2
.IFTF	Assembles block regardless of whether condition tests true or false.	6.9.2
.IIF	Permits writing a one line conditional assembly block.	6.9.3
.INCLUDE.	Includes another MACRO-11 source file.	6.10.2
.LIBRARY	Adds file to MACRO-11 library search list.	6.10.1

(continued on next page)

GENERAL ASSEMBLER DIRECTIVES

Table 6-1 (Cont.)
Directives in Chapter Six

Directive	Function	Section Reference
.LIMIT	Allocates two words for storage. At link time puts the lowest address of the load image in the first of the saved words and the address of the first free word following the image in the second.	6.5.4
.LIST	Increments listing count or lists certain types of code.	6.1.1
.NLIST	Decrements listing count or suppresses certain types of code.	6.1.1
.NOCROSS	Disables cross reference.	6.2.2
.ODD	Ensures that the current value of the location counter is odd.	6.5.2
.PACKED	Generates packed decimal data, two digits per byte.	6.3.8
.PAGE	Starts a new listing page.	6.1.5
.PSECT	Declares names for program sections and establishes their attributes.	6.7.1
.RAD50	Generates data in Radix-50 packed format.	6.3.6
.RADIX	Changes radices throughout or in portions of the source program.	6.4.1.1
.REM	Delimits a section of comments.	6.1.6
.RESTORE	Retrieves a previously .SAVED program section.	6.7.4
.SAVE	Places the current program section on top of the program section context stack.	6.7.3
.SBTTL	Produces a table of contents immediately preceding the assembly listing and puts subheadings on each page in the listing.	6.1.3
.TITLE	Assigns a name to the object module and puts headings on each page of the assembly listing.	6.1.2
.WEAK	Defines listed symbols as WEAK.	6.8.2
.WORD	Generates successive words of data in the object module.	6.3.2