



UNIVERSITY OF THE EAST
CALOOCAN CITY
College of Engineering
Department of Computer Studies and Systems

RIP ACTIVITIES
Packet Tracer Activities


Name: Jose, Krystoff S.

Student Number: 20241116847

Subject and Section: CIT2201 – IT1D

Activity No.	Score
ACT1	100%
ACT2	100%

Activity 01



Router>ena

Router#config t

Enter configuration commands, one per line. End with CNTL/Z.

Router(config)#hostname Manila

Manila(config)#int s2/0

Manila(config-if)#ip add 192.168.10.162 255.255.255.252

Manila(config-if)#clock rate 250000

Manila(config-if)#no shut

Manila(config-if)#

%LINK-5-CHANGED: Interface Serial2/0, changed state to up

Manila(config-if)#int s3/0

Manila(config-if)#

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to up

Manila(config-if)#ip add 192.168.10.165 255.255.255.252

Manila(config-if)#clock rate 250000

Manila(config-if)#no shut

Manila(config-if)#

%LINK-5-CHANGED: Interface Serial3/0, changed state to up

Manila(config-if)#rou

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/0, changed state to

Manila(config-if)#route rip

Manila(config-router)#version 2

Manila(config-router)#no auto-summary

Manila(config-router)#network 192.168.10.160

Manila(config-router)#network 192.168.10.164

Manila(config-router)#exit

```
Manila(config)#exit
Manila#
%SYS-5-CONFIG_I: Configured from console by console
```

```
Manila#telnet 192.168.10.161
Trying 192.168.10.161 ...Open
```

User Access Verification

```
Password:
Router>ena
Password:
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname Caloocan
Caloocan(config)#int fa0/0
Caloocan(config-if)#ip add 192.168.10.1 255.255.255.192
Caloocan(config-if)#no shut
```

```
Caloocan(config-if)#int fa1/0
Caloocan(config-if)#ip add 192.168.10.65 255.255.255.224
Caloocan(config-if)#no shut
```

```
Caloocan(config-if)#route rip
Caloocan(config-router)#version 2
Caloocan(config-router)#no auto-summary
Caloocan(config-router)#network 192.168.10.0
Caloocan(config-router)#network 192.168.10.64
Caloocan(config-router)#exit
Caloocan(config)#exit
Caloocan#exit
```

```
[Connection to 192.168.10.161 closed by foreign host]
Manila#telnet 192.168.10.166
Trying 192.168.10.166 ...Open
```

User Access Verification

```
Password:
Router>ena
Password:
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname Quezon
Quezon(config)#int fa0/0
Quezon(config-if)#ip add 192.168.10.129 255.255.255.224
Quezon(config-if)#no shut
```

```
Quezon(config-if)#int fa1/0
Quezon(config-if)#ip add 192.168.10.97 255.255.255.224
Quezon(config-if)#no shut
```

```
Quezon(config-if)#exit
Quezon(config)#route rip
```


```

Quezon(config-router)#version 2
Quezon(config-router)#no auto-summary
Quezon(config-router)#network 192.168.10.96
Quezon(config-router)#network 192.168.10.128
Quezon(config-router)#exit
Quezon(config)#exit
Quezon#exit

```

[Connection to 192.168.10.166 closed by foreign host]
 Manila#

Activity 02



```

Router>ena
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname RM
RM(config)#int se2/0
RM(config-if)#ip add 10.0.6.6 255.255.255.252
RM(config-if)#clock rate 64000
RM(config-if)#no shut

RM(config-if)#
%LINK-5-CHANGED: Interface Serial2/0, changed state to up

RM(config-if)#int se3/0
%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial2/0, changed state to up

RM(config-if)#int se3/0
RM(config-if)#ip add 10.0.6.1 255.255.255.252
RM(config-if)#no shut

%LINK-5-CHANGED: Interface Serial3/0, changed state to down

```

```
RM(config-if)#exit
RM(config)#exit
RM#
%SYS-5-CONFIG_I: Configured from console by console
```

```
RM#telnet 10.0.6.5
Trying 10.0.6.5 ...Open
```

User Access Verification

```
Password:
Router>ena
Password:
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname RL
RL(config)#int se3/0
RL(config-if)#ip add 10.0.6.10 255.255.255.252
RL(config-if)#clock rate 64000
RL(config-if)#no shut
```

```
RL(config-if)#
RL(config-if)#int fa0/0
RL(config-if)#ip add 10.0.4.1 255.255.254.0
RL(config-if)#no shut
```

```
RL(config-if)#route rip
RL(config-router)#version 2
RL(config-router)#no auto-summary
RL(config-router)#network 10.0.4.0
RL(config-router)#network 10.0.6.4
RL(config-router)#network 10.0.6.8
RL(config-router)#exit
RL(config)#ip dhcp pool F
RL(dhcp-config)#network 10.0.4.0 255.255.254.0
RL(dhcp-config)#default-router 10.0.4.1
RL(dhcp-config)#exit
RL(config)#ip dhcp excluded-address 10.0.4.1
RL(config)#exit
RL#telnet 10.0.6.9
Trying 10.0.6.9 ...
% Connection timed out; remote host not responding
RL#exit
```

```
[Connection to 10.0.6.5 closed by foreign host]
RM#telnet 10.0.6.9
Trying 10.0.6.9 ...
% Connection timed out; remote host not responding
RM#telnet 10.0.6.2
Trying 10.0.6.2 ...
% Connection timed out; remote host not responding
RM#config t
Enter configuration commands, one per line. End with CNTL/Z.
RM(config)#int se3/0
RM(config-if)#no shut
```

```
RM(config-if)#exit
RM(config)#exit
RM#
%SYS-5-CONFIG_I: Configured from console by console
```

```
RM#telnet 10.0.6.10
Trying 10.0.6.10 ...
% Connection timed out; remote host not responding
RM#telnet 10.0.6.5
Trying 10.0.6.5 ...Open
```

User Access Verification

```
Password:
RL>ena
Password:
RL#telnet 10.0.6.9
Trying 10.0.6.9 ...
% Connection timed out; remote host not responding
RL#config t
Enter configuration commands, one per line. End with CNTL/Z.
RL(config)#int se3/0
RL(config-if)#ip add 10.0.6.9 255.255.255.252
RL(config-if)#no shut
RL(config-if)#exit
RL(config)#exit
RL#telnet 10.0.6.10
Trying 10.0.6.10 ...Open
```

User Access Verification

```
Password:
Router>ena
Password:
Router#config t
Enter configuration commands, one per line. End with CNTL/Z.
Router(config)#hostname RN
RN(config)#int se2/0
RN(config-if)#ip add 10.0.6.2 255.255.255.252
RN(config-if)#clock rate 64000
RN(config-if)#no shut
%LINK-5-CHANGED: Interface Serial3/0, changed state to up

%LINEPROTO-5-UPDOWN: Line protocol on Interface Serial3/0, changed state to up
```

```
RN(config-if)#int fa0/0
RN(config-if)#ip add 10.0.0.1 255.255.252.0
RN(config-if)#no shut

RN(config-if)#ip dhcp excluded-address 10.0.0.1
RN(config)#ip dhcp pool G
RN(dhcp-config)#network 10.0.0.0 255.255.252.0
RN(dhcp-config)#default-router 10.0.0.1
```

```
RN(dhcp-config)#exit
RN(config)#router rip
RN(config-router)#version 2
RN(config-router)#no auto-summary
RN(config-router)#network 10.0.0.0
RN(config-router)#network 10.0.6.0
RN(config-router)#network 10.0.6.8
RN(config-router)#exit
RN(config)#exit
RN#exit
```

```
[Connection to 10.0.6.10 closed by foreign host]
RL#exit
```

```
[Connection to 10.0.6.5 closed by foreign host]
RM#config t
Enter configuration commands, one per line. End with CNTL/Z.
RM(config)#router rip
RM(config-router)#version 2
RM(config-router)#no auto-summary
RM(config-router)#network 10.0.6.4
RM(config-router)#network 10.0.6.0
RM(config-router)#exit
RM(config)#exit
RM#
%SYS-5-CONFIG_I: Configured from console by console
^Z
RM#
```