

Launch Settings Overview

Access:

System / Launch

The launch settings in SpeedWMS allow you to configure and control each step of the order processing launch, from start to finish.

Steps of the Launch Process

Step	Code	Purpose
Launch start	LAN_STAT_LAN	Initializes the launch
Start of order	LAN_START_CDE	Prepares each order for processing
Start line processing	LAN_START_LIN	Prepares each order line
Line processing	LAN_TRT_LIN	Core processing of each line (main focus)
End of line processing	LAN_END_LIN	Finalizes processing of the line
End of order	LAN_END_CDE	Finalizes the order
End of launch	LAN_END_LAN	Wraps up the entire launch

Typically, the main configurations are needed for line processing and end of launch.

Procedures for Order Line Processing

When processing each order line (LAN_TRT_LIN), the following procedures can be executed sequentially:

1. **Availability check** – Checks stock and generates missing/backorder samples if stock is insufficient.
2. **Service on stock (pallets)** – Proposes complete pallet samples from available stock.
3. **Picking service** – Offers retail samples in the picking area based on stock availability.
4. **Service on stock (details)** – Provides smaller quantities or detailed withdrawals not handled by the previous step.

5. **Missing service** – Any remaining quantities that couldn't be served are marked as missing.
-

Procedure Configuration

Each procedure can be configured along three main axes:

1. **Application Settings Tab** – Specifies which order lines the procedure applies to.
2. **Search Parameters Tab** – Defines the stock constraints or search rules.
3. **Generation Parameters Tab** – Determines how the samples (direct debit lines) should be generated.

The generated direct debit lines constitute the preparation mission lines.

End-of-Launch Processing (GenereMissionLan)

Once direct debit lines are generated:

- Lines are grouped into missions based on specified criteria.
- Configuration focuses on:
 1. Which lines are included in missions (Application Settings).
 2. How lines are grouped (Generation Parameters).

Example:

- Standard SpeedWMS setup generates one mission per picking area for an activity order.
 - Multiple mission generation procedures can be configured depending on the rules.
-

Key Notes

- Launch settings allow complete automation of order line processing.
- You can define how stock is allocated, how missions are grouped, and how missing items are handled.
- Proper configuration ensures preparation missions are generated efficiently and logically.

