# Managing Cloud Volumes Service for AWS

## Cloud Manager 3.7

Ben Cammett
January 03, 2020

This PDF was generated from https://docs.netapp.com/us-en/occm37/task_manage_cvs_aws.html on April 25, 2020. Always check docs.netapp.com for the latest.

# Table of Contents

Managing Cloud Volumes Service for AWS . . . 1
- Before you get started . . . 1
- Discovering your Cloud Volumes Service for AWS subscription . . . 1
- Discovering additional regions . . . 2
- Creating cloud volumes . . . 3
- Deleting cloud volumes . . . 4
- Getting help . . . 5
- Limitations . . . 5
- Related links . . . 5

# Managing Cloud Volumes Service for AWS

Cloud Manager enables you to discover the NFS cloud volumes in your Cloud Volumes Service for AWS subscription. After discovery, you can add additional NFS cloud volumes directly from Cloud Manager.

> Cloud Manager does not support SMB or dual-protocol volumes with Cloud Volumes Service for AWS.

## Before you get started

- Cloud Manager enables discovery of *existing* Cloud Volumes Service for AWS subscriptions. See the NetApp Cloud Volumes Service for AWS Account Setup Guide if you haven't set up your subscription yet.

  You must follow this setup process for each region and provision your first volume from Cloud Volumes Service before you can discover the region in Cloud Manager.

- You need to obtain the Cloud Volumes API key and secret key so you can provide them to Cloud Manager. For instructions, refer to Cloud Volumes Service for AWS documentation.

## Discovering your Cloud Volumes Service for AWS subscription

To get started, you need to discover the cloud volumes in an AWS region. You can discover additional regions later.

*Steps*

1. On the Working Environments page, click **Discover**.
2. Select **Cloud Volumes Service for AWS**.
3. Provide information about your Cloud Volumes Service subscription:
   a. Select the AWS region where your cloud volumes reside.
   b. Enter the Cloud Volumes API key and secret key. For instructions, refer to Cloud Volumes Service for AWS documentation.
   c. Click **Go**.

*Result*

Cloud Manager should now display your Cloud Volumes Service for AWS configuration on the Working Environments page.

# Discovering additional regions

If you have cloud volumes in additional regions, you need to discover each individual region.

*Steps*

1. On the Working Environments page, select the working environment (but don't open it by double-clicking).
2. In the right pane, click **Discover Cloud Volumes Service in another region**.




3. Provide information about your Cloud Volumes Service subscription:
   a. Select the AWS region where your cloud volumes reside.
   b. Enter the Cloud Volumes API key and secret key. For instructions, refer to Cloud Volumes Service for AWS documentation.
   c. Click **Go**.

*Result*

Cloud Manager discovers information about the cloud volumes in the selected region.

# Creating cloud volumes

Cloud Manager enables you to create NFSv3 cloud volumes. You can only create cloud volumes with an initial size and single export policy. Editing the volume must be done from the Cloud Volume Service

user interface.

1. Open the working environment.
2. Click **Add New Volume**.
3. Enter details about the volume:
   a. Enter a name for the volume.
   b. Specify a size within the range of 100 GiB to 90,000 GiB (equivalent to 88 TiBs).

      Cloud Manager displays volumes in GiB, while the Cloud Volumes Service displays volumes in GB.

   c. Specify a service level: Standard, Premium, or Extreme.

      Learn more about these service levels.

   d. Choose a region. You can create the volume in a region that Cloud Manager has discovered.
   e. Restrict client access by specifying an IP address or Classless Inter-Domain Routing (CIDR).




4. Click **Go**.

# Deleting cloud volumes

Delete the cloud volumes that you no longer need.

*Steps*

1. Open the working environment.
2. Hover over the volume and click the menu. Click **Delete**.

3. Confirm that you want to delete the volume.

# Getting help

Use the Cloud Manager chat for general service questions.

For technical support issues associated with your cloud volumes, use your 20 digit “930” serial number located in the "Support" tab of the Cloud Volumes Service user interface. Use this support ID when opening a web ticket or calling for support. Be sure to activate your Cloud Volumes Service serial number for support from the Cloud Volumes Service user interface. Those steps are explained here.

# Limitations

- Cloud Manager does not support SMB or dual-protocol volumes.
- You can only create cloud volumes with an initial size and single export policy. Editing the volume must be done from the Cloud Volume Service user interface.
- Cloud Manager doesn’t support data replication to or from a Cloud Volumes Service for AWS subscription.
- Removing your Cloud Volumes Service for AWS subscription from Cloud Manager isn’t supported. There are no charges to discover a region from Cloud Manager.

# Related links

- NetApp Cloud Central: Cloud Volumes Service for AWS
- NetApp Cloud Volumes Service for AWS documentation

**Copyright Information**

Copyright © 2019–2020 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

**Trademark Information**

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.