Managing backups for Cloud Volumes ONTAP and on-premises ONTAP systems

Cloud Manager 3.8

Ben Cammett
October 30, 2020

This PDF was generated from https://docs.netapp.com/us-en/occm38/task_managing_backups.html on May 31, 2021. Always check docs.netapp.com for the latest.

Table of Contents

Managing backups for Cloud Volumes ONTAP and on-premises ONTAP systems . . . 1
Changing the schedule and backup retention . . . 1
Starting and stopping backups of volumes . . . 2
Restoring a volume from a backup . . . 3
Deleting backups . . . 5
Disabling Backup to Cloud . . . 5

Managing backups for Cloud Volumes ONTAP and on-premises ONTAP systems

Manage backups for Cloud Volumes ONTAP and on-premises ONTAP systems by changing the backup schedule, restoring volumes, deleting backups, and more.

Changing the schedule and backup retention

The default policy backs up volumes every day and retains the most recent 30 backup copies of each volume. You can change to weekly or monthly backups and you can change the number of backup copies to retain. You can also select one of the system-defined policies that provide scheduled backups for 3 months, 1 year, and 7 years.

> Changing the backup policy affects only new volumes created after you change the schedule. It doesn't affect the schedule for any existing volumes.

Steps

1. Select the working environment.
2. Click ⋮ and select **Backup Settings**.



3. From the *Backup Settings page*, click ••• for the working environment and select **Modify Backup Policy**.

4. From the *Modify Backup Policy* page, change the schedule and backup retention and then click **Save**.



Starting and stopping backups of volumes

You can stop backing up a volume if you do not need backup copies of that volume and you do not want to pay for the cost to store the backups. You can also add a new volume to the backup list if it is not currently being backed up.

Steps

1. Select the working environment.
2. Click ⋮ and select **Backup Settings**.



3. From the *Backup Settings page*, click ••• for the working environment and select **Manage Volumes**.



4. Select the checkbox for volumes that you want to start backing up, and deselect the checkbox for volumes that you want to stop backing up.



Note: When stopping a volume from being backed up you'll continue to be charged by your cloud provider for object storage costs for the capacity that the backups use unless you delete the backups.

Restoring a volume from a backup

When you restore data from a backup, Cloud Manager creates a *new* volume using the data from the backup. You can restore the data to a volume in the same working environment or to a different working environment that's located in the same cloud account as the source working environment. Because the backup does not contain any snapshots, the newly restored volume does not either.

Backups created from on-premises ONTAP systems can be restored only to Cloud Volumes ONTAP systems that use the same cloud provider as where the backup resides.

Steps

1. Select the working environment.
2. Click ⋮ and select **View Backups**.



3. Select the row for the volume that you want to restore and click **View Backup List**.



4. Find the backup that you want to restore and click the **Restore** icon.



5. Fill out the *Restore Backup to new volume* page:
   a. Select the working environment to which you want to restore the volume.
   b. Enter a name for the volume.
   c. Click **Restore**.

Result

Cloud Manager creates a new volume based on the backup you selected. You can manage this new volume as required.

Deleting backups

Backup to Cloud enables you to delete *all* backups of a specific volume. You can't delete *individual* backups.

You might do this if you no longer need the backups or if you deleted the source volume and want to remove all backups.

> If you plan to delete a Cloud Volumes ONTAP or on-premises ONTAP system that has backups, you must delete the backups **before** deleting the system. Backup to Cloud doesn't automatically delete backups when you delete a system, and there is no current support in the UI to delete the backups after the system has been deleted.

Steps

1. At the top of Cloud Manager, click **Backup**.
2. From the volume list, find the volume and click **View Backup List**.
3. Click ••• and select **Delete All Backups**.



4. In the confirmation dialog box, click **Delete**.

Disabling Backup to Cloud

Disabling Backup to Cloud for a working environment disables backups of each volume on the system, and it also disables the ability to restore a volume. Any existing backups will not be deleted.

Note that you'll continue to be charged by your cloud provider for object storage costs for the capacity that your backups use unless you delete the backups.

Steps

1. Select the working environment.
2. Click ⋮ and select **Backup Settings**.



3. From the *Backup Settings page*, click ••• for the working environment and select **Deactivate Backup to Cloud**.

4. In the confirmation dialog box, click **Deactivate**.

Copyright Information

Copyright © 2021 NetApp, Inc. All rights reserved. Printed in the U.S. No part of this document covered by copyright may be reproduced in any form or by any means-graphic, electronic, or mechanical, including photocopying, recording, taping, or storage in an electronic retrieval system-without prior written permission of the copyright owner.

Software derived from copyrighted NetApp material is subject to the following license and disclaimer:

THIS SOFTWARE IS PROVIDED BY NETAPP “AS IS” AND WITHOUT ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE, WHICH ARE HEREBY DISCLAIMED. IN NO EVENT SHALL NETAPP BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

NetApp reserves the right to change any products described herein at any time, and without notice. NetApp assumes no responsibility or liability arising from the use of products described herein, except as expressly agreed to in writing by NetApp. The use or purchase of this product does not convey a license under any patent rights, trademark rights, or any other intellectual property rights of NetApp.

The product described in this manual may be protected by one or more U.S. patents, foreign patents, or pending applications.

RESTRICTED RIGHTS LEGEND: Use, duplication, or disclosure by the government is subject to restrictions as set forth in subparagraph (c)(1)(ii) of the Rights in Technical Data and Computer Software clause at DFARS 252.277-7103 (October 1988) and FAR 52-227-19 (June 1987).

Trademark Information

NETAPP, the NETAPP logo, and the marks listed at http://www.netapp.com/TM are trademarks of NetApp, Inc. Other company and product names may be trademarks of their respective owners.