

Creating instance

Name and tags [info](#)

[Add additional tags](#)

Application and OS Images (Amazon Machine Image) [info](#)

An AMI contains the operating system, application server, and applications for your instance. If you don't see a suitable AMI below, use the search field or choose [Browse more AMIs](#).

Recents

Quick Start

Amazon Linux

macOS

Ubuntu

Windows

Red Hat

SUSE Linux

Debian

AWS

Ubuntu

Microsoft

Red Hat

SUSE

Debian

Amazon Machine Image (AMI)

Ubuntu Server 26.04 LTS (HVM), SSD Volume Type

ami-0305e2e429f041a3 (64-bit (x86)) / ami-062054dc70ad09dc (64-bit (x86))

Virtualization: hvm ENA enabled: true Root device type: ebs

Free tier eligible

Description

Ubuntu Server 26.04 LTS (HVM), EBS General Purpose (SSD) Volume Type. Support available from Canonical (<http://www.ubuntu.com/cloud/services>).

Canonical, Ubuntu, 26.04, amd64 resolute image

Architecture

AMI ID

Publish Date

Username

Summary

Number of instances

1

Software Image (AMI)

Canonical, Ubuntu, 26.04, amd64...[read more](#)

ami-0305e2e429f041a3

Virtual server type (instance type)

t3.micro

Firewall (security group)

New security group

Storage (volumes)

1 volume(s) - 8 GiB

Free tier:

In your first year of opening an AWS account, you get 750 hours per month of t3.micro instance usage (or t3.micro where t3.micro isn't available) when used with free tier AMIs, 750 hours per month of public IPv4 address usage, 30 GiB of EBS storage, 2 million I/Os, 1 GiB of snapshots, and 100 GiB of bandwidth to the internet. Data transfer charges are not included as part of the free tier allowance. Charges may apply depending on your account's free tier status.

Cancel

Launch instance

[Preview code](#)

EC2

Instances

I-0c8b775a6d214a215

Dashboard

AWS Global View

Events

Instances

Instances

Instance Types

Launch Templates

Spot Requests

Savings Plans

Reserved Instances

Dedicated Hosts

Capacity Reservations

Capacity Manager

Images

AMIs

AMI Catalog

Elastic Block Store

Volumes

Snapshots

Lifecycle Manager

Network & Security

Security Groups

Elastic IPs

Placement Groups

Instance summary for i-0c8b775a6d214a215 (ServerXF01) [info](#)

Updated less than a minute ago

Instance ID

i-0c8b775a6d214a215

IPV6 address

-

Hostname type

IP name: ip-172-31-34-76.eu-central-1.compute.internal

Answer private resource DNS name

IPv4 (A)

Auto-assigned IP address

3.69.165.188 (Public IP)

IAM role

-

IMDSv2

Required

Operator

-

Public IPv4 address

3.69.165.188 | [open address](#)

Instance state

Running

Private IP DNS name (IPv4 only)

ip-172-31-34-76.eu-central-1.compute.internal

Instance type

t3.micro

VPC ID

vpc-00f27700a5c52891b | [open](#)

Subnet ID

subnet-0d9316b194cf5323d | [open](#)

Instance ARN

arn:aws:ec2:eu-central-1:992382545251:instance/i-0c8b775a6d214a215

Private IPv4 addresses

172.31.34.76

Public DNS

ec2-3-69-165-188.eu-central-1.compute.amazonaws.com | [open address](#)

Elastic IP addresses

-

AWS Compute Optimizer finding

No recommendations available for this instance.

Auto Scaling Group name

-

Managed

false

Details

Status and alarms

Monitoring

Security

Networking

Storage

Tags

Instance details [info](#)

AMI ID

ami-0305e2e429f041a3

AMI name

Ubuntu Server 26.04 LTS (HVM), SSD Volume Type

Monitoring

disabled

Platform details

Linux/UNIX

Termination protection

Not enabled

Connecting

```

Welcome to Ubuntu 26.04 LTS (GNU/Linux 7.0.0-1004-aws x86_64)

 * Documentation:  https://docs.ubuntu.com
 * Management:    https://landscape.canonical.com
 * Support:       https://ubuntu.com/pro

System information as of Sun Jun 28 06:45:05 UTC 2026

System load: 0.01   Temperature: -273.1 C
Usage of /: 30.5% of 6.61GB   Processes: 120
Memory usage: 27%   Users logged in: 0
Swap usage: 0%      IPv4 address for ens3: 172.31.34.76

Expanded Security Maintenance for Applications is not enabled.

0 updates can be applied immediately.

Enable ESM Apps to receive additional future security updates.
See https://ubuntu.com/esm or run: sudo apt update

The list of available updates is more than a week old.
To check for new updates run: sudo apt update

The programs included with the Ubuntu system are free software;
the exact distribution terms for each program are described in the
individual files in /usr/share/doc/*/*copyright*.

Ubuntu comes with ABSOLUTELY NO WARRANTY, to the extent permitted by
applicable law.

ubuntu@ip-172-31-34-76:~$
```

Creating My_file Directory the creating file1 and file2 and giving the execution permissions

```
Ubuntu comes with ABSOLUTELY NO WARRANTY, to the extent permitted by
applicable law.

ubuntu@ip-172-31-34-76:~$ mkdir My_files
ubuntu@ip-172-31-34-76:~$ ls
My_files
ubuntu@ip-172-31-34-76:~$ touch My_files/file1 My_files/file2
ubuntu@ip-172-31-34-76:~$ ls
My_files
ubuntu@ip-172-31-34-76:~$ ls My_files
file1 file2
ubuntu@ip-172-31-34-76:~$ chmod +x My_files/file1 My_files/file2
ubuntu@ip-172-31-34-76:~$ ls -l My_files
total 0
-rwxrwxr-x 1 ubuntu ubuntu 0 Jun 28 06:46 file1
-rwxrwxr-x 1 ubuntu ubuntu 0 Jun 28 06:46 file2
ubuntu@ip-172-31-34-76:~$
```

Creating volume

The screenshot displays the AWS Management Console for an EBS volume. The left sidebar shows the navigation menu with categories like EC2, Instances, Images, Elastic Block Store, and Network & Security. The main content area shows the details for volume **vol-0f65f237c71f5dfc8**. Key details include:

- Volume ID:** vol-0f65f237c71f5dfc8
- Size:** 5 GiB
- Type:** gp3
- Status check:** ✔ Okay
- Volume state:** ✔ In-use
- IOPS:** 3000
- Throughput:** 125
- Availability Zone:** eu-central-1b
- Created:** Sun Jun 28 2026 09:56:22 GMT+0300 (jpp) (٢٢) ٢٤٢٦
- Multi-Attach enabled:** No
- Operator:** -
- Managed:** False
- Encryption:** Not encrypted
- KMS key ID:** -
- KMS key alias:** -
- KMS key ARN:** -
- Fast snapshot restored:** No
- Attached resources:** i-0c8b775a6d214a215 (ServerLXF01) (EBS card index: 0; /dev/sdf (attached))
- Source:** Snapshot ID: -, Source volume ID: -
- Status checks:** ✔ Okay
- I/O status:** ✔ Enabled
- I/O status updated on:** Sun Jun 28 2026 09:56:22 GMT+0300 (jpp) (٢٢) ٢٤٢٦
- I/O performance:** ⓘ Not applicable
- I/O performance updated on:** -

Creating two partitions

```
Welcome to fdisk (util-linux 2.41.3).
Changes will remain in memory only, until you decide to write them.
Be careful before using the write command.

Device does not contain a recognized partition table.
Created a new DOS (MBR) disklabel with disk identifier 0x1c7436e2.

Command (m for help): n
Partition type
  p   primary (0 primary, 0 extended, 4 free)
  e   extended (container for logical partitions)
Select (default p): p
Partition number (1-4, default 1): 1
First sector (2048-10485759, default 2048):
Last sector, +/-sectors or +/-size[K,M,G,T,P] (2048-10485759, default 10485759): +500M

Created a new partition 1 of type 'Linux' and of size 500 MiB.
```

```

Command (m for help): n
Partition type
  p   primary (1 primary, 0 extended, 3 free)
  e   extended (container for logical partitions)
Select (default p): p
Partition number (2-4, default 2): 2
First sector (1026048-10485759, default 1026048):
Last sector, +/-sectors or +/-size[K,M,G,T,P] (1026048-10485759, default 10485759): +500M

Created a new partition 2 of type 'Linux' and of size 500 MiB.

```

```

Command (m for help): w
The partition table has been altered.
Calling ioctl() to re-read partition table.
Syncing disks.

ubuntu@ip-172-31-34-76:~$ lsblk
NAME        MAJ:MIN RM  SIZE RO TYPE MOUNTPOINTS
loop0        7:0      0  28.2M  1 loop /snap/amazon-ssm-agent/13009
loop1        7:1      0   74M   1 loop /snap/core22/2411
loop2        7:2      0  49.3M   1 loop /snap/snapd/26865
nvme0n1      259:0     0    8G   0 disk
├─nvme0n1p1  259:1     0   6.9G   0 part /
├─nvme0n1p13 259:2     0  1023M   0 part /boot
├─nvme0n1p14 259:3     0    4M   0 part
├─nvme0n1p15 259:4     0   106M   0 part /boot/efi
nvme1n1      259:5     0    5G   0 disk
├─nvme1n1p1  259:8     0   500M   0 part
└─nvme1n1p2  259:9     0   500M   0 part
ubuntu@ip-172-31-34-76:~$

```

creating an xfs filesystem on the first partition

```

ubuntu@ip-172-31-34-76:~$ sudo mkfs.xfs /dev/nvme1n1p1
mkfs.xfs: small data volume, ignoring data volume stripe unit 8 and stripe width 8
meta-data=/dev/nvme1n1p1      isize=512    agcount=4, agsize=32000 blks
                         =      sectsz=512    attr=2, projid32bit=1
                         =      crc=1        finobt=1, sparse=1, rmapbt=1
                         =      reflink=1    bigtime=1 inobtcount=1 nrext64=1
                         =      exchange=0   metadir=0
data      =      bsize=4096   blocks=128000, imaxpct=25
                         =      sunit=0      swidth=0 blks
naming    =version 2          bsize=4096   ascii-ci=0, ftype=1, parent=0
log       =internal log      bsize=4096   blocks=16384, version=2
                         =      sectsz=512   sunit=0 blks, lazy-count=1
realtime  =none              extsz=4096   blocks=0, rtextents=0
                         =      rgcount=0    rgsz=0 extents
                         =      zoned=0     start=0 reserved=0
ubuntu@ip-172-31-34-76:~$

```

Creating directory folder and checking for mountpoint

```

ubuntu@ip-172-31-34-76:~$ sudo mkdir /directory

ubuntu@ip-172-31-34-76:~$ sudo mount /dev/nvme1n1p1 /directory
ubuntu@ip-172-31-34-76:~$ df -h
Filesystem      Size  Used Avail Use% Mounted on
/dev/root        6.7G  2.1G  4.6G  31% /
tmpfs           455M    0  455M   0% /dev/shm
tmpfs           182M  912K  181M   1% /run
efivarfs        128K  3.1K  120K   3% /sys/firmware/efi/efivars
tmpfs           455M    0  455M   0% /tmp
none            1.0M    0   1.0M   0% /run/credentials/systemd-journald.service
none            1.0M    0   1.0M   0% /run/credentials/systemd-resolved.service
/dev/nvme0n1p13  989M   96M  827M  11% /boot
/dev/nvme0n1p15  105M   6.3M   99M   7% /boot/efi
none            1.0M    0   1.0M   0% /run/credentials/systemd-networkd.service
none            1.0M    0   1.0M   0% /run/credentials/serial-getty@ttyS0.service
none            1.0M    0   1.0M   0% /run/credentials/getty@tty1.service
tmpfs           91M    8.0K   91M   1% /run/user/1000
/dev/nvme1n1p1  436M   34M  403M   8% /directory

```

```
ubuntu@ip-172-31-34-76:~$ sudo mkfs.xfs /dev/nvme1nlp2
mkfs.xfs: small data volume, ignoring data volume stripe unit 8 and stripe width 8
meta-data=/dev/nvme1nlp2      isize=512    agcount=4, agsize=32000 blks
                               sectsz=512    attr=2,   projid32bit=1
                               crc=1          finobt=1, sparse=1, rmapbt=1
                               reflink=1      bigtime=1 inobtcount=1 nrext64=1
                               exchange=0     metadir=0
data      =                    bsize=4096    blocks=128000, imaxpct=25
                               sunit=0       swidth=0 blks
naming    =version 2          bsize=4096    ascii-ci=0, ftype=1, parent=0
log       =internal log      bsize=4096    blocks=16384, version=2
                               sectsz=512    sunit=0 blks, lazy-count=1
realtime  =none              extsz=4096    blocks=0, rtextents=0
                               rgcount=0     rgsz=0 extents
                               =            zoned=0     start=0 reserved=0
```

```
ubuntu@ip-172-31-34-76:~$ sudo mount /dev/nvme1nlp2 /directory2
mount: (hint) your fstab has been modified, but systemd still uses
the old version; use 'systemctl daemon-reload' to reload.
ubuntu@ip-172-31-34-76:~$ df -h
Filesystem      Size  Used Avail Use% Mounted on
/dev/root        6.7G  2.1G  4.6G  32% /
tmpfs            455M    0  455M   0% /dev/shm
tmpfs            182M   916K   181M   1% /run
efivarfs         128K   3.1K   120K   3% /sys/firmware/efi/efivars
tmpfs            455M    0  455M   0% /tmp
none             1.0M    0   1.0M   0% /run/credentials/systemd-journald.service
none             1.0M    0   1.0M   0% /run/credentials/systemd-resolved.service
/dev/nvme0nlp13  989M   96M   827M  11% /boot
/dev/nvme0nlp15  105M   6.3M   99M    7% /boot/efi
none             1.0M    0   1.0M   0% /run/credentials/systemd-networkd.service
none             1.0M    0   1.0M   0% /run/credentials/serial-getty@ttyS0.service
none             1.0M    0   1.0M   0% /run/credentials/getty@tty1.service
tmpfs            91M    8.0K   91M    1% /run/user/1000
/dev/nvme1nlp1   436M   34M   403M    8% /directory
/dev/nvme1nlp2   436M   34M   403M    8% /directory2
```

Finding the uuid

```
ubuntu@ip-172-31-34-76:~$ sudo blkid /dev/nvme1nlp1
/dev/nvme1nlp1: UUID="934537ba-6317-4d07-909b-4d174688223c" BLOCK_SIZE="512" TYPE="xfs" PARTUUID="1c7436e2-01"
```

```
ubuntu@ip-172-31-34-76:~$ sudo nano /etc/fstab
```

```
GNU nano 8.7.1 /etc
LABEL=cloudimg-rootfs / ext4 discard,commit=30,errors=remount-ro 0 1
LABEL=BOOT /boot ext4 defaults 0 2
LABEL=UEFI /boot/efi vfat umask=0077 0 1
UUID=934537ba-6317-4d07-909b-4d174688223c /directory xfs defaults 0 0
```

Filesystem	Size	Used	Avail	Use%	Mounted on
/dev/root	6.7G	2.1G	4.6G	32%	/
tmpfs	455M	0	455M	0%	/dev/shm
tmpfs	182M	916K	181M	1%	/run
efivarfs	128K	3.1K	120K	3%	/sys/firmware/efi/efivars
tmpfs	455M	0	455M	0%	/tmp
none	1.0M	0	1.0M	0%	/run/credentials/systemd-journald.service
none	1.0M	0	1.0M	0%	/run/credentials/systemd-resolved.service
/dev/nvme0n1p13	989M	96M	827M	11%	/boot
/dev/nvme0n1p15	105M	6.3M	99M	7%	/boot/efi
none	1.0M	0	1.0M	0%	/run/credentials/systemd-networkd.service
none	1.0M	0	1.0M	0%	/run/credentials/serial-getty@ttyS0.service
none	1.0M	0	1.0M	0%	/run/credentials/getty@tty1.service
tmpfs	91M	8.0K	91M	1%	/run/user/1000
/dev/nvme1n1p1	436M	34M	403M	8%	/directory